

**ExpressCluster<sup>®</sup> X SingleServerSafe 3.2**  
**for Linux**

Installation Guide

02/19/2014

1st Edition



---

Revision History

Edition	Revised Date	Description
1st	02/19/2014	New manual

---

© Copyright NEC Corporation 2014. All rights reserved.

## **Disclaimer**

Information in this document is subject to change without notice.

NEC Corporation is not liable for technical or editorial errors or omissions in the information in this document.

You are completely liable for all risks associated with installing or using the product as described in this manual to obtain expected results and the effects of such usage.

The information in this document is copyrighted by NEC Corporation.

No part of this document may be reproduced or transmitted in any form by any means, electronic or mechanical, for any purpose, without the express written permission of NEC Corporation.

## **Trademark Information**

ExpressCluster<sup>®</sup> X is a registered trademark of NEC Corporation.

FastSync<sup>™</sup> is a trademark of NEC Corporation.

Linux is a registered trademark or trademark of Linus Torvalds in the United States and other countries.

RPM is a trademark of Red Hat, Inc.

Intel, Pentium, and Xeon are registered trademarks or trademarks of Intel Corporation.

Microsoft and Windows are registered trademarks of Microsoft Corporation in the United States and other countries.

Turbolinux is a registered trademark of Turbolinux, Inc.

VERITAS, VERITAS Logo, and all other VERITAS product names and slogans are trademarks or registered trademarks of VERITAS Software Corporation.

Oracle, Java and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

VMware is a registered trademark or trademark of VMware, Inc. in the United States and other countries.

Novell is a registered trademark of Novell, Inc. in the United States and Japan.

SUSE is a registered trademark of SUSE LINUX AG, a group company of U.S. Novell.

Citrix, Citrix XenServer, and Citrix Essentials are registered trademarks or trademarks of Citrix Systems, Inc. in the United States and other countries.

WebOTX is a registered trademark of NEC Corporation.

JBoss is a registered trademark of Red Hat, Inc. in the United States and its subsidiaries.

Apache Tomcat, Tomcat, and Apache are registered trademarks or trademarks of Apache Software Foundation.

Android is a trademark or registered trademark of Google, Inc.

F5, F5 Networks, BIG-IP, and iControl are trademarks or registered trademarks of F5 Networks, Inc. in the United States and other countries.

Equalizer SVF is a registered trademark of Coyote Point Systems, Inc.

Other product names and slogans written in this manual are trademarks and registered trademarks of their respective companies.



# Table of Contents

<b>Preface</b> .....	<b>vii</b>
Who Should Use This Guide.....	vii
How This Guide Is Organized.....	vii
Terms Used in This Guide .....	viii
ExpressCluster X SingleServerSafe Documentation Set.....	ix
Conventions .....	x
Contacting NEC .....	xi
<b>Chapter 1 About ExpressCluster X SingleServerSafe</b> .....	<b>13</b>
What is ExpressCluster X SingleServerSafe?.....	14
ExpressCluster X SingleServerSafe software configuration .....	15
Checking system requirements for ExpressCluster X SingleServerSafe .....	16
Hardware .....	16
Required specifications .....	16
Servers supporting BMC-related functions .....	16
Software.....	17
Supported distributions and kernel versions.....	22
Applications supported by the monitoring options.....	33
Operation environment for SNMP linkage functions.....	39
Operation environment for JVM monitor.....	40
Preparing and verifying the server environment before installation .....	41
1. Verifying the network settings (Required) .....	41
2. Verifying the root file system (Required) .....	41
3. Verifying the firewall settings (Required).....	42
<b>Chapter 2 Installing ExpressCluster X SingleServerSafe</b> .....	<b>45</b>
Steps from installing ExpressCluster X SingleServerSafe to setting up the server .....	46
Installing the ExpressCluster X SingleServerSafe .....	47
Installing ExpressCluster X SingleServerSafe for the first time .....	47
Setting up the SNMP linkage function.....	48
Registering the license .....	50
Registering the CPU license.....	50
Registering the license by specifying the license file (for both the product version and trial version).....	51
Registering the license interactively from the command line (product version) .....	52
Registering the VM node license .....	54
Registering the VM node license by specifying the license file (Product version) .....	55
Registering the VM node license interactively from the command line (Product version) .....	56
Registering the node license.....	58
Registering the license by specifying the license file (for both the product version and trial version).....	59
Registering the node license interactively from the command line (product version).....	60
Installing the offline version of the ExpressCluster Builder .....	62
Installing the ExpressCluster Builder into a Windows machine (offline version).....	62
Starting the Builder .....	65
Starting the online version of the Builder.....	65
Starting the offline version of the Builder .....	66
<b>Chapter 3 Upgrading, uninstalling or reinstalling</b> .....	<b>67</b>
Updating ExpressCluster X SingleServerSafe .....	68
Updating the ExpressCluster X SingleServerSafe RPM .....	68
Uninstalling ExpressCluster X SingleServerSafe .....	70
Uninstalling ExpressCluster X SingleServerSafe.....	70
Uninstalling the offline version of the ExpressCluster Builder .....	70
Canceling the SNMP linkage function settings.....	71
Reinstalling ExpressCluster X SingleServerSafe .....	72
Reinstalling the ExpressCluster SingleServerSafe .....	72
Upgrading to ExpressCluster X .....	73

---

<b>Chapter 4 Latest version information.....</b>	<b>75</b>
Latest version information.....	76
ExpressCluster X SingleServerSafe version and corresponding manual editions.....	77
Enhanced function information.....	78
Corrected information.....	82
<b>Chapter 5 Additional information.....</b>	<b>95</b>
ExpressCluster X SingleServerSafe services.....	96
Migration from the trial license to the official license.....	97
<b>Chapter 6 Notes and Restrictions.....</b>	<b>99</b>
Before and at the time of installing operating system.....	100
/opt/nec/clusterpro file system.....	100
Dependent library.....	100
Dependent driver.....	100
SELinux settings.....	100
ExpressCluster X Alert Service.....	100
Before installing ExpressCluster.....	101
Communication port number.....	101
Changing the range of automatic allocation for the communication port numbers.....	102
Checking the network settings.....	103
Ipmitool and OpenIPMI.....	103
User-mode monitor resources (softdog monitoring method).....	103
Collecting logs.....	104
nsupdate and nslookup.....	104
FTP monitor resources.....	104
<b>Appendix A Troubleshooting.....</b>	<b>105</b>
Error messages when installing the ExpressCluster X SingleServerSafe.....	105
Error messages when uninstalling the ExpressCluster X SingleServerSafe.....	105
Troubleshooting for licensing.....	106
<b>Appendix B Index.....</b>	<b>107</b>

# Preface

## Who Should Use This Guide

The *ExpressCluster X SingleServerSafe for Linux Installation Guide* is intended for system engineers who intend to introduce a system using ExpressCluster X SingleServerSafe and system administrators who will operate and maintain the introduced system. This guide describes how to install ExpressCluster X SingleServerSafe.

## How This Guide Is Organized

- Chapter 1** “About ExpressCluster X SingleServerSafe”: Explains the functions and requirements of ExpressCluster X SingleServerSafe.
- Chapter 2** “Installing ExpressCluster X SingleServerSafe”: Describes how to install ExpressCluster X SingleServerSafe.
- Chapter 3** “Upgrading, uninstalling or reinstalling”: Describes how to upgrade ExpressCluster X SingleServerSafe, uninstall and reinstall ExpressCluster X SingleServerSafe, and upgrade to ExpressCluster X.
- Chapter 4** “Latest version information”: Provides the latest information about ExpressCluster X SingleServerSafe.
- Chapter 5** “Additional information”: Provides tips on installing ExpressCluster X SingleServerSafe.
- Chapter 6** “Notes and Restrictions”: Provides notes and restrictions you need to know before starting the actual operation of ExpressCluster X SingleServerSafe.

## Appendix

- Appendix A** “Troubleshooting”: Describes problems you might experience when installing or setting up ExpressCluster X SingleServerSafe and how to resolve them.
- Appendix B** “Index”

---

## Terms Used in This Guide

ExpressCluster X SingleServerSafe, which is described in this guide, uses windows and commands common to those of the clustering software ExpressCluster X SingleServerSafe to ensure high compatibility with ExpressCluster X SingleServerSafe in terms of operation and other aspects. Therefore, cluster-related terms are used in parts of the guide.

The terms used in this guide are defined below.

<b>Term</b>	<b>Explanation</b>
Cluster, cluster system	A single server system using ExpressCluster X SingleServerSafe
Cluster shutdown, reboot	Shutdown or reboot of a system using ExpressCluster X SingleServerSafe
Cluster resource	A resource used in ExpressCluster X SingleServerSafe
Cluster object	A resource object used in ExpressCluster X SingleServerSafe
Failover group	A group of group resources (such as applications and services) used in ExpressCluster X SingleServerSafe

---

## **ExpressCluster X SingleServerSafe Documentation Set**

The ExpressCluster X SingleServerSafe documentation consists of the five guides below. The title and purpose of each guide is described below:

### **ExpressCluster X SingleServerSafe Installation Guide**

This guide is intended for system engineers who intend to introduce a system using ExpressCluster X SingleServerSafe and describes how to install ExpressCluster X SingleServerSafe.

### **ExpressCluster X SingleServerSafe Configuration Guide**

This guide is intended for system engineers who intend to introduce a system using ExpressCluster X SingleServerSafe and system administrators who will operate and maintain the introduced system. It describes how to set up ExpressCluster X SingleServerSafe.

### **ExpressCluster X SingleServerSafe Operation Guide**

This guide is intended for system administrators who will operate and maintain an introduced system that uses ExpressCluster X SingleServerSafe. It describes how to operate ExpressCluster X SingleServerSafe.

### **ExpressCluster X Integrated WebManager Administrator's Guide**

This guide is intended for system administrators who manage a cluster system using ExpressCluster with ExpressCluster Integrated WebManager and for system engineers who are introducing the Integrated WebManager. Details about items required when introducing a cluster system are described in accordance with actual procedures.

### **ExpressCluster X WebManager Mobile Administrator's Guide**

This guide is intended for system administrators who manage cluster system using ExpressCluster with ExpressCluster WebManager Mobile and for system engineers who introduce the WebManager Mobile. In this guide, details on those items required for introducing the cluster system using the WebManager Mobile are explained in accordance with the actual procedures.

---

## Conventions

In this guide, **Note**, **Important**, **Related Information** are used as follows:

---

**Note:**

Used when the information given is important, but not related to the data loss and damage to the system and machine.

---

---

**Important:**

Used when the information given is necessary to avoid the data loss and damage to the system and machine.

---

---

**Related Information:**

Used to describe the location of the information given at the reference destination.

---

The following conventions are used in this guide.

Convention	Usage	Example
<b>Bold</b>	Indicates graphical objects, such as fields, list boxes, menu selections, buttons, labels, icons, etc.	In <b>User Name</b> , type your name. On the <b>File</b> menu, click <b>Open Database</b> .
Angled bracket within the command line	Indicates that the value specified inside of the angled bracket can be omitted.	<code>clpstat -s [-h <i>host_name</i>]</code>
#	Prompt to indicate that a Linux user has logged in as root user.	<code># clpcl -s -a</code>
Monospace (courier)	Indicates path names, commands, system output (message, prompt, etc), directory, file names, functions and parameters.	<code>/Linux/3.0/en/server/</code>
<b>Monospace bold (courier)</b>	Indicates the value that a user actually enters from a command line.	Enter the following: <code><b>clpcl -s -a</b></code>
<i>Monospace italic (courier)</i>	Indicates that users should replace italicized part with values that they are actually working with.	<code>rpm -i expressclssss -&lt;version_number&gt;-&lt;release_number&gt;.i686.rpm</code>

---

## **Contacting NEC**

For the latest product information, visit our website below:

<http://www.nec.com/global/prod/expresscluster/>



# Chapter 1      **About ExpressCluster X SingleServerSafe**


This chapter describes the functions and requirements of ExpressCluster X SingleServerSafe.

This chapter covers:

- What is ExpressCluster X SingleServerSafe? ..... 14
- Checking system requirements for ExpressCluster X SingleServerSafe ..... 16
- Preparing and verifying the server environment before installation ..... 41

## What is ExpressCluster X SingleServerSafe?

ExpressCluster X SingleServerSafe is set up on a server. It monitors for application errors and hardware failures on the server and, upon detecting an error or failure, restarts the failed application or reboots the server so as to ensure greater server availability.



---

### Related Information:

For details about ExpressCluster X SingleServerSafe, refer to Section I “Introducing ExpressCluster X SingleServerSafe” in the *ExpressCluster X SingleServerSafe Configuration Guide*.

---

## ExpressCluster X SingleServerSafe software configuration

ExpressCluster X SingleServerSafe consists of following three software applications:

- ◆ ExpressCluster SingleServerSafe

The main module of ExpressCluster X SingleServerSafe. Install it on the server.

- ◆ WebManager

A tool to manage ExpressCluster X SingleServerSafe operations.


It uses a Web browser as a user interface.

The WebManager is incorporated into the ExpressCluster SingleServerSafe and therefore does not have to be installed.

- ◆ Builder

A tool for creating the configuration data of ExpressCluster X SingleServerSafe.

There are two versions. The online version of the Builder runs in the configuration mode of the WebManager, and the offline version of the Builder is installed individually in a management terminal. The online version of the Builder is incorporated in the WebManager. The Builder also uses a Web browser as a user interface the same way as the WebManager.



The WebManager and the Builder are Java applets that run on Java VMs. They can run on any machine in which the Java Runtime Environment (JRE) is installed. The WebManager and the Builder can run on Windows and Linux.

In other words, once you install the JRE on a server on which ExpressCluster X SingleServerSafe is installed, you can use the WebManager and Builder on that server.

# Checking system requirements for ExpressCluster X SingleServerSafe

## Hardware

ExpressCluster X SingleServerSafe runs on a server that has either of the following architectures:

- ◆ IA-32
- ◆ x86\_64

## Required specifications

Required specifications for ExpressCluster SingleServerSafe are the following:

- ◆ Ethernet port:
- ◆ CD-ROM drive

When using the off-line Builder upon constructing and changing the existing configuration, one of the following is required for communication between the off-line Builder and servers:

- ◆ Removable media (for example, floppy disk drive or USB flash drive)
- ◆ A machine to operate the offline version of the Builder and a way to share files

## Servers supporting BMC-related functions

The table below lists the supported servers that can use the forced stop function. These are typical examples, and also some other servers can use these functions.

Server	Remarks
Express5800/120Rg-1	
Express5800/120Rf-1	
Express5800/120Rg-2	

## Software

ExpressCluster X SingleServerSafe consists of three modules: ExpressCluster SingleServerSafe, ExpressCluster WebManager, and ExpressCluster Builder. Check configuration and operation requirements of each machine where these modules will be installed. The following describes the basic system requirements for ExpressCluster X SingleServerSafe 3.2 for Linux.

- ◆ Details on operating system supporting ExpressCluster SingleServerSafe.
- ◆ It is recommended to use a file system which is capable of journaling for the root file system in the operating system.  
Linux (kernel version 2.6 or later) supports file systems such as ext3, ext4, JFS, ReiserFS, and XFS as a journaling file system. If a file system that is not capable of journaling is used, you must run an interactive command (`fsck` for the root file system) when rebooting the server after server or OS stop (when normal shutdown could not be done).

The following provides the system requirements for each module:

<b>ExpressCluster X SingleServerSafe</b>	
<b>Machine on which the ExpressCluster X SingleServerSafe can be installed</b>	PC that supports one of the following operating systems.
<b>Supported operating systems</b>	<p><b>IA-32 version</b>                      Red Hat Enterprise Linux 5 (update4 or later)                      Red Hat Enterprise Linux 6                      Asianux Server 3 (SP2 or later)                      Asianux Server 4                      Novell SUSE LINUX Enterprise Server 10 (SP2 or later)                      Novell SUSE LINUX Enterprise Server 11                      Turbolinux 11 Server (SP1 or later)                      XenServer 5.5 (update2)                      XenServer 5.6 (no update, update2)                      XenServer 6.0</p> <p><b>x86_64 version</b>                      Red Hat Enterprise Linux 5 (update4 or later)                      Red Hat Enterprise Linux 6                      Asianux Server 3 (SP2 or later)                      Asianux Server 4                      Novell SUSE LINUX Enterprise Server 10 (SP2 or later)                      Novell SUSE LINUX Enterprise Server 11                      Turbolinux 11 Server (SP1 or later)                      Oracle Enterprise Linux 5.5                      VMware ESX Server 4.0 (no update, update1, 2)                      VMware ESX Server 4.1</p>
<b>Memory size</b>	<p><b>IA-32 version</b>                      User mode        96 MB(*1)                      Kernel mode      8 MB</p> <p><b>x86_64 version</b>                      User mode        96 MB(*1)                      Kernel mode      8 MB</p>
<b>Disk Size:</b>	<p><b>IA-32 version</b>                      Initial size at installation        140 MB                      Maximum size during operation    2.0 GB</p> <p><b>x86_64 version</b>                      Initial size at installation        140 MB                      Maximum size during operation    2.0 GB</p>

(\*1) excepting for optional products.

<b>WebManager, Builder (online version)</b>	
<b>Machine on which the WebManager and Builder can be installed</b>	PC that supports one of the following operating systems.
<b>Supported operating systems</b>	Linux (IA-32) Microsoft® Windows® XP SP3 Microsoft® Windows Vista® Microsoft® Windows® 7 (IA-32, x86_64) Microsoft® Windows® 8 (IA-32, x86_64) Microsoft® Windows Server® 2003 SP1 or later Microsoft® Windows Server® 2008 Microsoft® Windows Server® 2008 R2 Microsoft® Windows Server® 2012
<b>Supported browsers</b>	Browsers supporting Java 2: Firefox (1.0.6 or later) Konqueror (3.3.1 or later) Microsoft® Internet Explorer® 7.0 Microsoft® Internet Explorer® 8.0 Microsoft® Internet Explorer® 9.0 Microsoft® Internet Explorer® 10.0
<b>Java Runtime Environment</b>	Java® Runtime Environment Version 6.0 Update 21 (1.6.0_21) or later  Java® Runtime Environment Version 7.0 Update 2 (1.7.0_2) or later  *Java Runtime Environment is necessary to use the WebManager.
<b>Memory size</b>	User mode 40 MB

Builder (offline version)		
<b>Machine on which the Builder can be installed</b>	PC that supports one of the following operating systems.	
<b>Supported operating systems</b>	Microsoft® Windows® XP SP3 Microsoft® Windows Vista® Microsoft® Windows® 7 Microsoft® Windows® 8 Microsoft® Windows Server® 2003 SP1 or later Microsoft® Windows Server® 2008 Microsoft® Windows Server® 2008 R2 Microsoft® Windows Server® 2012	
<b>Supported browsers</b>	Browsers supporting Java 2: Microsoft® Internet Explorer® 7.0 Microsoft® Internet Explorer® 8.0 Microsoft® Internet Explorer® 9.0 Microsoft® Internet Explorer® 10.0	
<b>Java Runtime Environment</b>	Sun Microsystems Java® Runtime Environment Version 6.0 Update 21 (1.6.0_21) or later  Sun Microsystems Java® Runtime Environment Version 7.0 Update 2 (1.7.0_2) or later  *Java Runtime Environment is necessary to use the Builder.	
<b>Memory size</b>	User mode 32 MB	
<b>Disk size (excluding the size required for the Java runtime environment)</b>	7 MB	
<b>Supported version</b>	Builder version	ExpressCluster X SingleServerSafe internal version
	3.0.0-1	3.0.0-1
	3.0.2-1	3.0.2-1
	3.0.3-1	3.0.3-1
	3.0.4-1	3.0.4-1
	3.1.0-1	3.1.0-1
	3.1.1-1	3.1.1-1
	3.1.3-1	3.1.3-1
	3.1.4-1	3.1.4-1
	3.1.5-1	3.1.5-1
	3.1.7-1	3.1.7-1
	3.1.8-1	3.1.8-1
	3.1.10-1	3.1.10-1
	3.2.0-1	3.2.0-1

**Note:**

The 32-bit Java Runtime is necessary to run the Builder on x86\_64 machines.

**Note:**

The WebManager does not run on a browser of a x86\_64 machine. Use a browser supporting IA32 to run the ExpressCluster X WebManager .

---

## Supported distributions and kernel versions

The environments where ExpressCluster X SingleServerSafe can run depend on the kernel module versions because there are kernel modules specific to ExpressCluster X SingleServerSafe. Kernel versions which has been verified are listed below.

### IA-32

Distribution	Kernel version	clpka supported	ExpressCluster X SingleServerSafe version
Turbolinux 11 Server (SP1)	2.6.23-10 2.6.23-10smp64G	Yes	3.0.0-1 or later
	2.6.23-12 2.6.23-12smp64G	Yes	3.0.0-1 or later
	2.6.23-15 2.6.23-15smp64G	Yes	3.2.0-1 or later
Turbolinux Appliance Server 3.0 (SP1)	2.6.23-10 2.6.23-10smp64G	Yes	3.0.0-1 or later
	2.6.23-12 2.6.23-12smp64G	Yes	3.0.0-1 or later
	2.6.23-15 2.6.23-15smp64G	Yes	3.2.0-1 or later
Red Hat Enterprise Linux 5 (update4)	2.6.18-164.el5 2.6.18-164.el5PAE 2.6.18-164.el5xen	Yes	3.0.0-1 or later
	2.6.18-164.6.1.el5 2.6.18-164.6.1.el5PAE 2.6.18-164.6.1.el5xen	Yes	3.0.0-1 or later
	2.6.18-164.9.1.el5 2.6.18-164.9.1.el5PAE 2.6.18-164.9.1.el5xen	Yes	3.0.0-1 or later
	2.6.18-164.11.1.el5 2.6.18-164.11.1.el5PAE 2.6.18-164.11.1.el5xen	Yes	3.0.0-1 or later
	2.6.18-164.15.1.el5 2.6.18-164.15.1.el5PAE 2.6.18-164.15.1.el5xen	Yes	3.0.0-1 or later
	2.6.18-164.38.1.el5 2.6.18-164.38.1.el5PAE 2.6.18-164.38.1.el5xen	Yes	3.1.4-1 or later
	2.6.18-194.el5 2.6.18-194.el5PAE 2.6.18-194.el5xen	Yes	3.0.0-1 or later
Red Hat Enterprise Linux 5 (update5)	2.6.18-194.8.1.el5 2.6.18-194.8.1.el5PAE 2.6.18-194.8.1.el5xen	Yes	3.0.0-1 or later
	2.6.18-194.11.4.el5 2.6.18-194.11.4.el5PAE 2.6.18-194.11.4.el5xen	Yes	3.0.1-1 or later

Distribution	Kernel version	clpka supported	ExpressCluster X SingleServerSafe version
	2.6.18-194.17.1.el5 2.6.18-194.17.1.el5PAE 2.6.18-194.17.1.el5xen	Yes	3.0.1-1 or later
	2.6.18-194.32.1.el5 2.6.18-194.32.1.el5PAE 2.6.18-194.32.1.el5xen	Yes	3.0.3-1 or later
Red Hat Enterprise Linux 5 (update6)	2.6.18-238.el5 2.6.18-238.el5PAE 2.6.18-238.el5xen	Yes	3.0.3-1 or later
	2.6.18-238.1.1.el5 2.6.18-238.1.1.el5PAE 2.6.18-238.1.1.el5xen	Yes	3.0.3-1 or later
	2.6.18-238.9.1.el5 2.6.18-238.9.1.el5PAE 2.6.18-238.9.1.el5xen	Yes	3.1.0-1 or later
	2.6.18-238.37.1.el5 2.6.18-238.37.1.el5PAE 2.6.18-238.37.1.el5xen	Yes	3.1.4-1 or later
Red Hat Enterprise Linux 5 (update7)	2.6.18-274.el5 2.6.18-274.el5PAE 2.6.18-274.el5xen	Yes	3.1.0-1 or later
	2.6.18-274.18.1.el5 2.6.18-274.18.1.el5PAE 2.6.18-274.18.1.el5xen	Yes	3.1.3-1 or later
Red Hat Enterprise Linux 5 (update8)	2.6.18-308.el5 2.6.18-308.el5PAE 2.6.18-308.el5xen	Yes	3.1.4-1 or later
	2.6.18-308.4.1.el5 2.6.18-308.4.1.el5PAE 2.6.18-308.4.1.el5xen	Yes	3.1.4-1 or later
	2.6.18-308.11.1.el5 2.6.18-308.11.1.el5PAE 2.6.18-308.11.1.el5xen	Yes	3.1.5-1 or later
	2.6.18-308.24.1.el5 2.6.18-308.24.1.el5PAE 2.6.18-308.24.1.el5xen	Yes	3.1.8-2 or later
Red Hat Enterprise Linux 5 (update9)	2.6.18-348.el5 2.6.18-348.el5PAE 2.6.18-348.el5xen	Yes	3.1.8-1 or later
	2.6.18-348.4.1.el5 2.6.18-348.4.1.el5PAE 2.6.18-348.4.1.el5xen	Yes	3.1.10-1 or later
	2.6.18-348.6.1.el5 2.6.18-348.6.1.el5PAE 2.6.18-348.6.1.el5xen		
	2.6.18-348.12.1.el5 2.6.18-348.12.1.el5PAE 2.6.18-348.12.1.el5xen		
	2.6.18-348.18.1.el5 2.6.18-348.18.1.el5PAE 2.6.18-348.18.1.el5xen		

Distribution	Kernel version	clpka supported	ExpressCluster X SingleServerSafe version
Red Hat Enterprise Linux 5 (update10)	2.6.18-371.el5 2.6.18-371.el5PAE 2.6.18-371.el5xen	Yes	3.2.0-1 or later
	2.6.18-371.3.1.el5 2.6.18-371.3.1.el5PAE 2.6.18-371.3.1.el5xen	Yes	3.2.0-1 or later
Red Hat Enterprise Linux 6	2.6.32-71.el6.i686	Yes	3.0.2-1 or later
	2.6.32-71.7.1.el6.i686	Yes	3.0.3-1 or later
	2.6.32-71.14.1.el6.i686	Yes	3.0.3-1 or later
	2.6.32-71.18.1.el6.i686	Yes	3.0.3-1 or later
	2.6.32-71.40.1.el6.i686	Yes	3.1.10-1 or later
Red Hat Enterprise Linux 6 (update1)	2.6.32-131.0.15.el6.i686	Yes	3.0.4-1 or later
	2.6.32-131.21.1.el6.i686	Yes	3.1.3-1 or later
	2.6.32-131.39.1.el6.i686	Yes	3.1.10-1 or later
Red Hat Enterprise Linux 6 (update2)	2.6.32-220.el6.i686	Yes	3.1.3-1 or later
	2.6.32-220.el6.4.2.i686	Yes	3.1.3-1 or later
	2.6.32-220.17.1.el6.i686	Yes	3.1.4-1 or later
	2.6.32-220.23.1.el6.i686	Yes	3.1.5-1 or later
	2.6.32-220.39.1.el6.i686	Yes	3.1.10-1 or later
	2.6.32-220.45.1.el6.i686	Yes	3.1.10-1 or later
Red Hat Enterprise Linux 6 (update3)	2.6.32-279.el6.i686	Yes	3.1.4-1 or later
	2.6.32-279.2.1.el6.i686	Yes	3.1.5-1 or later
	2.6.32-279.11.1.el6.i686	Yes	3.1.7-1 or later
	2.6.32-279.14.1.el6.i686	Yes	3.1.7-1 or later
	2.6.32-279.19.1.el6.i686	Yes	3.1.10-1 or later
	2.6.32-279.31.1.el6.i686		
	2.6.32-279.33.1.el6.i686		
2.6.32-279.37.2.el6.i686	Yes	3.2.0-1 or later	
Red Hat Enterprise Linux 6 (update4)	2.6.32-358.el6.i686	Yes	3.1.8-1 or later
	2.6.32-358.0.1.el6.i686		
	2.6.32-358.2.1.el6.i686		
	2.6.32-358.6.1.el6.i686	Yes	3.1.10-1 or later
	2.6.32-358.6.2.el6.i686	Yes	3.1.8-2 or later
	2.6.32-358.11.1.el6.i686		
	2.6.32-358.14.1.el6.i686	Yes	3.1.8-1 or later
	2.6.32-358.23.2.el6.i686	Yes	3.2.0-1 or later
Red Hat Enterprise Linux 6 (update5)	2.6.32-431.el6.i686	Yes	3.2.0-1 or later
	2.6.32-431.1.2.el6.i686	Yes	3.2.0-1 or later

Distribution	Kernel version	clpka supported	ExpressCluster X SingleServerSafe version
Asianux Server 3 (SP2)	2.6.18-128.7.AXS3 2.6.18-128.7.AXS3PAE 2.6.18-128.7.AXS3xen	Yes	3.0.0-1 or later
Asianux Server 3 (SP3)	2.6.18-194.1.AXS3 2.6.18-194.1.AXS3PAE 2.6.18-194.1.AXS3xen	Yes	3.0.0-1 or later
	2.6.18-194.2.AXS3 2.6.18-194.2.AXS3PAE 2.6.18-194.2.AXS3xen	Yes	3.0.0-1 or later
	2.6.18-194.6.AXS3 2.6.18-194.6.AXS3PAE 2.6.18-194.6.AXS3xen	Yes	3.0.1-1 or later
	2.6.18-194.9.AXS3 2.6.18-194.9.AXS3PAE 2.6.18-194.9.AXS3xen	Yes	3.0.3-1 or later
Asianux Server 3 (SP4)	2.6.18-238.2.AXS3 2.6.18-238.2.AXS3PAE 2.6.18-238.2.AXS3xen	Yes	3.1.0-1 or later
	2.6.18-308.1.AXS3 2.6.18-308.1.AXS3PAE 2.6.18-308.1.AXS3xen	Yes	3.1.5-1 or later
	2.6.18-348.1.AXS3 2.6.18-348.1.AXS3PAE 2.6.18-348.1.AXS3xen	Yes	3.1.8-1 or later
	2.6.18-348.4.AXS3 2.6.18-348.4.AXS3PAE 2.6.18-348.4.AXS3xen	Yes	3.1.8-2 or later
Asianux Server 4	2.6.32-71.7.1.el6.i686	Yes	3.0.4-1 or later
Asianux Server 4 (SP1)	2.6.32-131.12.1.el6.i686	Yes	3.1.3-1 or later
	2.6.32-220.13.1.el6.i686	Yes	3.1.4-1 or later
Asianux Server 4 (SP2)	2.6.32-279.2.1.el6.i686	Yes	3.1.7-1 or later
	2.6.32-279.14.1.el6.i686	Yes	3.1.7-2 or later
	2.6.32-279.19.1.el6.i686	Yes	3.1.8-1 or later
	2.6.32-358.2.1.el6.i686	Yes	3.1.8-2 or later
	2.6.32-358.6.1.el6.i686		
	2.6.32-358.6.2.el6.i686	Yes	3.1.10-1 or later
2.6.32-358.11.2.el6.i686			
Novell SUSE LINUX Enterprise Server 10 (SP2)	2.6.16.60-0.21-default 2.6.16.60-0.21-smp 2.6.16.60-0.21-bigsmpp 2.6.16.60-0.21-xen	Yes	3.0.0-1 or later
Novell SUSE LINUX Enterprise Server 10 (SP3)	2.6.16.60-0.54.5-default 2.6.16.60-0.54.5-smp 2.6.16.60-0.54.5-bigsmpp 2.6.16.60-0.54.5-xen	Yes	3.0.0-1 or later

Distribution	Kernel version	clpka supported	ExpressCluster X SingleServerSafe version
	2.6.16.60-0.69.1-default 2.6.16.60-0.69.1-smp 2.6.16.60-0.69.1-bigsmpt 2.6.16.60-0.69.1-xen	Yes	3.0.1-1 or later
	2.6.16.60-0.83.2-default 2.6.16.60-0.83.2-smp 2.6.16.60-0.83.2-bigsmpt 2.6.16.60-0.83.2-xen	Yes	3.1.4-1 or later
Novell SUSE LINUX Enterprise Server 10 (SP4)	2.6.16.60-0.85.1-default 2.6.16.60-0.85.1-smp 2.6.16.60-0.85.1-bigsmpt 2.6.16.60-0.85.1-xen	Yes	3.0.4-1 or later
	2.6.16.60-0.91.1-default 2.6.16.60-0.91.1-smp 2.6.16.60-0.91.1-bigsmpt 2.6.16.60-0.91.1-xen	Yes	3.1.3-1 or later
	2.6.16.60-0.93.1-default 2.6.16.60-0.93.1-smp 2.6.16.60-0.93.1-bigsmpt 2.6.16.60-0.93.1-xen	Yes	3.1.4-1 or later
	2.6.16.60-0.97.1-default 2.6.16.60-0.97.1-smp 2.6.16.60-0.97.1-bigsmpt 2.6.16.60-0.97.1-xen	Yes	3.1.5-1 or later
Novell SUSE LINUX Enterprise Server 11	2.6.27.19-5-default 2.6.27.19-5-pae 2.6.27.19-5-xen	Yes	3.0.0-1 or later
	2.6.27.48-0.12-default 2.6.27.48-0.12-pae 2.6.27.48-0.12-xen	Yes	3.0.1-1 or later
Novell SUSE LINUX Enterprise Server 11 (SP1)	2.6.27.12-0.7-default 2.6.27.12-0.7-pae 2.6.27.12-0.7-xen	Yes	3.0.0-1 or later
	2.6.32.19-0.3-default 2.6.32.19-0.3-pae 2.6.32.19-0.3-xen	Yes	3.0.1-1 or later
	2.6.32.23-0.3-default 2.6.32.23-0.3-pae 2.6.32.23-0.3-xen	Yes	3.0.1-1 or later
	2.6.32.49-0.3-default 2.6.32.49-0.3-pae 2.6.32.49-0.3-xen	Yes	3.1.3-1 or later
Novell SUSE LINUX Enterprise Server 11 (SP2)	3.0.13-0.27-default 3.0.13-0.27-pae	Yes	3.1.4-1 or later
	3.0.34-0.7-default 3.0.34-0.7-pae	Yes	3.1.5-1 or later
	3.0.80-0.7-default 3.0.80-0.7-pae	Yes	3.1.10-1 or later
Novell SUSE LINUX Enterprise Server 11	3.0.76-0.11-default 3.0.76-0.11-pae	Yes	3.2.0-1 or later

Distribution	Kernel version	clpka supported	ExpressCluster X SingleServerSafe version
(SP3)	3.0.82-0.7-default 3.0.82-0.7-pae	Yes	3.2.0-1 or later
XenServer 5.5 (update2)	2.6.18-128.1.6.el5.xs5.5.0.505.1024xen	Yes	3.0.0-1 or later
XenServer 5.6	2.6.27.42-0.1.1.xs5.6.0.44.111158xen	Yes	3.1.0-1 or later
XenServer 5.6 (SP2)	2.6.32.12-0.7.1.xs5.6.100.323.170596xen	Yes	3.1.0-1 or later
XenServer 6.0	2.6.32.12-0.7.1.xs6.0.0.529.170661xen	Yes	3.1.1-1 or later

**x86\_64**

Distribution	Kernel version	clpka supported	ExpressCluster X SingleServerSafe version
Turbolinux 11 Server (SP1)	2.6.23-10	Yes	3.0.0-1 or later
	2.6.23-12	Yes	3.0.0-1 or later
Turbolinux Appliance Server 3.0 (SP1)	2.6.23-10	Yes	3.0.0-1 or later
	2.6.23-12	Yes	3.0.0-1 or later
Red Hat Enterprise Linux 5 (update4)	2.6.18-164.el5 2.6.18-164.el5xen	Yes	3.0.0-1 or later
	2.6.18-164.6.1.el5 2.6.18-164.6.1.el5xen	Yes	3.0.0-1 or later
	2.6.18-164.9.1.el5 2.6.18-164.9.1.el5xen	Yes	3.0.0-1 or later
	2.6.18-164.11.1.el5 2.6.18-164.11.1.el5xen	Yes	3.0.0-1 or later
	2.6.18-164.15.1.el5 2.6.18-164.15.1.el5xen	Yes	3.0.0-1 or later
	2.6.18-164.38.1.el5 2.6.18-164.38.1.el5xen	Yes	3.1.4-1 or later
Red Hat Enterprise Linux 5 (update5)	2.6.18-194.el5 2.6.18-194.el5xen	Yes	3.0.0-1 or later
	2.6.18-194.8.1.el5 2.6.18-194.8.1.el5xen	Yes	3.0.0-1 or later
	2.6.18-194.11.4.el5 2.6.18-194.11.4.el5xen	Yes	3.0.1-1 or later
	2.6.18-194.17.1.el5 2.6.18-194.17.1.el5xen	Yes	3.0.1-1 or later
	2.6.18-194.32.1.el5 2.6.18-194.32.1.el5xen	Yes	3.0.3-1 or later
Red Hat Enterprise Linux 5 (update6)	2.6.18-238.el5 2.6.18-238.el5xen	Yes	3.0.3-1 or later
	2.6.18-238.1.1.el5 2.6.18-238.1.1.el5xen	Yes	3.0.3-1 or later
	2.6.18-238.9.1.el5 2.6.18-238.9.1.el5xen	Yes	3.1.0-1 or later
	2.6.18-238.37.1.el5 2.6.18-238.37.1.el5xen	Yes	3.1.4-1 or later
Red Hat Enterprise Linux 5 (update7)	2.6.18-274.el5 2.6.18-274.el5xen	Yes	3.1.0-1 or later
	2.6.18-274.18.1.el5 2.6.18-274.18.1.el5xen	Yes	3.1.3-1 or later
Red Hat Enterprise Linux 5 (update8)	2.6.18-308.el5 2.6.18-308.el5xen	Yes	3.1.4-1 or later
	2.6.18-308.4.1el5 2.6.18-308.4.1el5xen	Yes	3.1.4-1 or later

Distribution	Kernel version	clpka supported	ExpressCluster X SingleServerSafe version
	2.6.18-308.11.1.el5 2.6.18-308.11.1.el5xen	Yes	3.1.5-1 or later
	2.6.18-308.24.1.el5 2.6.18-308.24.1.el5xen	Yes	3.1.8-2 or later
Red Hat Enterprise Linux 5 (update9)	2.6.18-348.el5 2.6.18-348.el5xen	Yes	3.1.8-1 or later
	2.6.18-348.4.1.el5 2.6.18-348.4.1.el5xen	Yes	3.1.10-1 or later
	2.6.18-348.6.1.el5 2.6.18-348.6.1.el5xen	Yes	3.1.10-1 or later
	2.6.18-348.12.1.el5 2.6.18-348.12.1.el5xen	Yes	3.1.10-1 or later
	2.6.18-348.18.1.el5 2.6.18-348.18.1.el5xen	Yes	3.1.10-1 or later
Red Hat Enterprise Linux 5 (update10)	2.6.18-371.el5 2.6.18-371.el5xen	Yes	3.2.0-1 or later
	2.6.18-371.3.1.el5 2.6.18-371.3.1.el5xen	Yes	3.2.0-1 or later
Red Hat Enterprise Linux 6	2.6.32-71.el6.x86_64	Yes	3.0.2-1 or later
	2.6.32-71.7.1.el6.x86_64	Yes	3.0.3-1 or later
	2.6.32-71.14.1.el6.x86_64	Yes	3.0.3-1 or later
	2.6.32-71.18.1.el6.x86_64	Yes	3.0.3-1 or later
	2.6.32-71.40.1.el6.x86_64	Yes	3.1.10-1 or later
Red Hat Enterprise Linux 6 (update1)	2.6.32-131.0.15.el6.x86_64	Yes	3.0.4-1 or later
	2.6.32-131.21.1.el6.x86_64	Yes	3.1.3-1 or later
	2.6.32-131.39.1.el6.x86_64	Yes	3.1.10-1 or later
Red Hat Enterprise Linux 6 (update2)	2.6.32-220.el6.x86_64	Yes	3.1.3-1 or later
	2.6.32-220.4.2.el6.x86_64	Yes	3.1.3-1 or later
	2.6.32-220.17.1.el6.x86_64	Yes	3.1.4-1 or later
	2.6.32-220.23.1.el6.x86_64	Yes	3.1.5-1 or later
	2.6.32-220.39.1.el6.x86_64	Yes	3.1.10-1 or later
	2.6.32-220.45.1.el6.x86_64	Yes	3.1.10-1 or later
Red Hat Enterprise Linux 6 (update3)	2.6.32-279.el6.x86_64	Yes	3.1.4-1 or later
	2.6.32-279.2.1.el6.x86_64	Yes	3.1.5-1 or later
	2.6.32-279.11.1.el6.x86_64	Yes	3.1.7-1 or later
	2.6.32-279.14.1.el6.x86_64	Yes	3.1.7-1 or later
	2.6.32-279.19.1.el6.x86_64	Yes	3.1.10-1 or later
	2.6.32-279.31.1.el6.x86_64	Yes	
	2.6.32-279.33.1.el6.x86_64	Yes	
	2.6.32-279.37.2.el6.x86_64	Yes	3.2.0-1 or later
Red Hat	2.6.32-358.el6.x86_64	Yes	3.1.8-1 or later

Distribution	Kernel version	clpka supported	ExpressCluster X SingleServerSafe version
Enterprise Linux 6 (update4)	2.6.32-358.0.1.el6.x86_64		
	2.6.32-358.2.1.el6.x86_64		
	2.6.32-358.6.1.el6.x86_64	Yes	3.1.10-1 or later
	2.6.32-358.6.2.el6.x86_64	Yes	3.1.8-2 or later
	2.6.32-358.11.1.el6.x86_64		
	2.6.32-358.14.1.el6.x86_64	Yes	3.1.8-1 or later
	2.6.32-358.23.2.el6.x86_64	Yes	3.2.0-1 or later
Red Hat Enterprise Linux 6 (update5)	2.6.32-431.el6.x86_64	Yes	3.2.0-1 or later
	2.6.32-431.1.2.el6.x86_64	Yes	3.2.0-1 or later
Asianux Server 3 (SP2)	2.6.18-128.7.AXS3 2.6.18-128.7.AXS3xen	Yes	3.0.0-1 or later
Asianux Server 3 (SP3)	2.6.18-194.1.AXS3 2.6.18-194.1.AXS3xen	Yes	3.0.0-1 or later
	2.6.18-194.2.AXS3 2.6.18-194.2.AXS3xen	Yes	3.0.0-1 or later
	2.6.18-194.6.AXS3 2.6.18-194.6.AXS3xen	Yes	3.0.1-1 or later
	2.6.18-194.9.AXS3 2.6.18-194.9.AXS3xen	Yes	3.0.3-1 or later
Asianux Server 3 (SP4)	2.6.18-238.2.AXS3 2.6.18-238.2.AXS3xen	Yes	3.1.0-1 or later
	2.6.18-308.1.AXS3 2.6.18-308.1.AXS3xen	Yes	3.1.5-1 or later
	2.6.18-308.7.AXS3 2.6.18-308.7.AXS3xen	Yes	3.1.7-2 or later
	2.6.18-348.1.AXS3 2.6.18-348.1.AXS3xen	Yes	3.1.8-1 or later
	2.6.18-348.4.AXS3 2.6.18-348.4.AXS3xen	Yes	3.1.8-2 or later
Asianux Server 4	2.6.32-71.7.1.el6.x86_64	Yes	3.0.4-1 or later
Asianux Server 4 (SP1)	2.6.32-131.12.1.el6.x86_64	Yes	3.1.3-1 or later
	2.6.32-220.13.1.el6.x86_64	Yes	3.1.4-1 or later
Asianux Server 4 (SP2)	2.6.32-279.2.1.el6.x86_64	Yes	3.1.7-1 or later
	2.6.32-279.14.1.el6.x86_64	Yes	3.1.7-2 or later
	2.6.32-279.19.1.el6.x86_64	Yes	3.1.8-1 or later
	2.6.32-358.2.1.el6.x86_64	Yes	3.1.8-2 or later
	2.6.32-358.6.1.el6.x86_64	Yes	3.1.8-2 or later
	2.6.32-358.6.2.el6.x86_64	Yes	3.1.10-1 or later
	2.6.32-358.11.1.el6.x86_64	Yes	3.1.10-1 or later
Novell SUSE LINUX Enterprise Server 10 (SP2)	2.6.16.60-0.21-default 2.6.16.60-0.21-smp 2.6.16.60-0.21-xen	Yes	3.0.0-1 or later

Distribution	Kernel version	clpka supported	ExpressCluster X SingleServerSafe version
Novell SUSE LINUX Enterprise Server 10 (SP3)	2.6.16.60-0.54.5-default 2.6.16.60-0.54.5-smp 2.6.16.60-0.54.5-xen	Yes	3.0.0-1 or later
	2.6.16.60-0.69.1-default 2.6.16.60-0.69.1-smp 2.6.16.60-0.69.1-xen	Yes	3.0.1-1 or later
	2.6.16.60-0.83.2-default 2.6.16.60-0.83.2-smp 2.6.16.60-0.83.2-xen	Yes	3.1.4-1 or later
Novell SUSE LINUX Enterprise Server 10 (SP4)	2.6.16.60-0.85.1-default 2.6.16.60-0.85.1-smp 2.6.16.60-0.85.1-xen	Yes	3.0.4-1 or later
	2.6.16.60-0.91.1-default 2.6.16.60-0.91.1-smp 2.6.16.60-0.91.1-xen	Yes	3.1.3-1 or later
	2.6.16.60-0.93.1-default 2.6.16.60-0.93.1-smp 2.6.16.60-0.93.1-xen	Yes	3.1.4-1 or later
	2.6.16.60-0.97.1-default 2.6.16.60-0.97.1-smp 2.6.16.60-0.97.1-xen	Yes	3.1.5-1 or later
Novell SUSE LINUX Enterprise Server 11	2.6.27.19-5-default 2.6.27.19-5-xen	Yes	3.0.0-1 or later
	2.6.27.48-0.12-default 2.6.27.48-0.12-xen	Yes	3.0.1-1 or later
Novell SUSE LINUX Enterprise Server 11 (SP1)	2.6.32.12-0.7-default 2.6.32.12-0.7-xen	Yes	3.0.0-1 or later
	2.6.32.19-0.3-default 2.6.32.19-0.3-xen	Yes	3.0.1-1 or later
	2.6.32.23-0.3-default 2.6.32.23-0.3-xen	Yes	3.0.1-1 or later
	2.6.32.49-0.3-default 2.6.32.49-0.3-xen	Yes	3.1.3-1 or later
Novell SUSE LINUX Enterprise Server 11 (SP2)	3.0.13-0.27-default 3.0.13-0.27-xen	Yes	3.1.4-1 or later
	3.0.34-0.7-default 3.0.34-0.7-xen	Yes	3.1.5-1 or later
	3.0.80-0.7-default 3.0.80-0.7-xen	Yes	3.1.10-1 or later
Novell SUSE LINUX Enterprise Server 11 (SP3)	3.0.76-0.11-default 3.0.76-0.11-xen	Yes	3.2.0-1 or later
	3.0.82-0.7-default 3.0.82-0.7-xen	Yes	3.2.0-1 or later
Oracle Enterprise Linux 5 (5.5)	2.6.18-194.el5 2.6.18-194.el5xen	Yes	3.0.0-1 or later
Oracle Linux 6.2	2.6.39-200.29.1.el6uek.x86_64	Yes	3.1.5-1 or later

Distribution	Kernel version	clpka supported	ExpressCluster X SingleServerSafe version
Oracle Linux 6.4	2.6.39-400.17.1.el6uek.x86_64	Yes	3.1.10-1 or later
	2.6.39-400.109.5.el6uek.x86_64	Yes	3.1.10-1 or later
	2.6.39-400.211.1.el6uek.x86_64	Yes	3.2.0-1 or later
VMware ESX 4.0	2.6.18-128.ESX	Yes	3.0.0-1 or later
VMware ESX 4.0 (update1)			
VMware ESX 4.1	2.6.18-164.ESX	Yes	3.0.0-1 or later
VMware ESX 4.1 (update1)	2.6.18-194.ESX	Yes	3.0.3-1 or later

## Applications supported by the monitoring options

Version information of the applications to be monitored by the monitor resources is described below.

### IA-32

Monitor resource	Application to be monitored	ExpressCluster X SingleServerSafe version	Remarks
Oracle monitor	Oracle Database 10g Release 2 (10.2)	3.0.0-1 or later	
	Oracle Database 11g Release 1 (11.1)	3.0.0-1 or later	
	Oracle Database 11g Release 2 (11.2)	3.0.0-1 or later	
DB2 monitor	DB2 V9.5	3.0.0-1 or later	
	DB2 V9.7	3.0.0-1 or later	
	DB2 V10.1	3.1.3-1 or later	
PostgreSQL monitor	PostgreSQL 8.1	3.0.0-1 or later	
	PostgreSQL 8.2	3.0.0-1 or later	
	PostgreSQL 8.3	3.0.0-1 or later	
	PostgreSQL 8.4	3.0.0-1 or later	
	PostgreSQL 9.0	3.0.3-1 or later	
	PostgreSQL 9.1	3.1.0-1 or later	
	PostgreSQL 9.2	3.1.7-1 or later	
	PowerGres on Linux 6.0	3.0.0-1 or later	
	PowerGres on Linux 7.0	3.0.0-1 or later	
	PowerGres on Linux 7.1	3.0.0-1 or later	
PowerGres on Linux 9.0	3.0.3-1 or later		
MySQL monitor	MySQL 5.0	3.0.0-1 or later	
	MySQL 5.1	3.0.0-1 or later	
	MySQL 5.5	3.0.3-1 or later	
	MySQL 5.6	3.1.8-1 or later	
Sybase monitor	Sybase ASE 15.0	3.0.0-1 or later	
	Sybase ASE 15.5	3.1.0-1 or later	
	Sybase ASE 15.7	3.1.0-1 or later	
Samba monitor	Samba 3.0	3.0.0-1 or later	
	Samba 3.2	3.0.0-1 or later	
	Samba 3.3	3.0.0-1 or later	
	Samba 3.4	3.0.0-1 or later	
	Samba 3.5	3.1.5-1 or later	
nfs monitor	nfsd 2 (udp)	3.0.0-1 or later	
	nfsd 3 (udp)	3.1.5-1 or later	

	nfsd 4 (tcp)	3.1.5-1 or later	
	mountd 1 (tcp)	3.0.0-1 or later	
	mountd 2 (tcp)	3.1.5-1 or later	
	mountd 3 (tcp)	3.1.5-1 or later	
HTTP monitor	No specified version	3.0.0-1 or later	
SMTP monitor	No specified version	3.0.0-1 or later	
pop3 monitor	No specified version	3.0.0-1 or later	
imap4 monitor	No specified version	3.0.0-1 or later	
ftp monitor	No specified version	3.0.0-1 or later	
Tuxedo monitor	Tuxedo 10g Release 3	3.0.0-1 or later	
	Tuxedo 11g Release 1	3.0.0-1 or later	
OracleAS monitor	Oracle Application Server 10g Release 3 (10.1.3.4)	3.0.0-1 or later	
Weblogic monitor	WebLogic Server 10g R3	3.0.0-1 or later	
	WebLogic Server 11g R1	3.0.0-1 or later	
	WebLogic Server 12c	3.1.3-1 or later	
Websphere monitor	WebSphere 6.1	3.0.0-1 or later	
	WebSphere 7.0	3.0.0-1 or later	
	WebSphere 8.0	3.1.5-1 or later	
	WebSphere 8.5	3.1.8-1 or later	
WebOTX monitor	WebOTX V7.1	3.0.0-1 or later	
	WebOTX V8.0	3.0.0-1 or later	
	WebOTX V8.1	3.0.0-1 or later	
	WebOTX V8.2	3.0.0-1 or later	
	WebOTX V8.3	3.1.0-1 or later	
	WebOTX V8.4	3.1.0-1 or later	
	WebOTX V9.1	3.1.10-1 or later	
JVM monitor	WebLogic Server 11g R1	3.1.0-1 or later	
	WebLogic Server 12c	3.1.3-1 or later	
	WebOTX V8.2	3.1.0-1 or later	
	WebOTX V8.3	3.1.0-1 or later	
	WebOTX V8.4	3.1.0-1 or later	
	WebOTX V9.1	3.1.10-1 or later	
	WebOTX Enterprise Service Bus V8.4	3.1.3-1 or later	
	WebOTX Enterprise Service Bus V8.5	3.1.5-1 or later	
	JBoss Application Server 4.2.3.GA/5.1.0.GA	3.1.0-1 or later	

	JBoss Enterprise Application Platform 4.3.0.GA_CP06	3.1.0-1 or later	
	Apache Tomcat 6.0	3.1.0-1 or later	
	Apache Tomcat 7.0	3.1.3-1 or later	
	WebSAM SVF for PDF 9.0	3.1.3-1 or later	
	WebSAM SVF for PDF 9.1	3.1.4-1 or later	
	WebSAM Report Director Enterprise 9.0	3.1.3-1 or later	
	WebSAM Report Director Enterprise 9.1	3.1.5-1 or later	
	WebSAM Universal Connect/X 9.0	3.1.3-1 or later	
	WebSAM Universal Connect/X 9.1	3.1.5-1 or later	
	Oracle iPlanet Web Server 7.0	3.1.3-1 or later	
System monitor	No specified version	3.1.0-1 or later	

**x86\_64**

<b>Monitor resource</b>	<b>Application to be monitored</b>	<b>ExpressCluster SingleServerSafe version</b>	<b>Remarks</b>
Oracle monitor	Oracle Database 10g Release 2 (10.2)	3.0.0-1 or later	
	Oracle Database 11g Release 1 (11.1)	3.0.0-1 or later	
	Oracle Database 11g Release 2 (11.2)	3.0.0-1 or later	
	Oracle Database 12c Release 2 (12.1)	3.1.8-1 or later	
DB2 monitor	DB2 V9.5	3.0.0-1 or later	
	DB2 V9.7	3.0.0-1 or later	
	DB2 V10.1	3.1.3-1 or later	
PostgreSQL monitor	PostgreSQL 8.1	3.0.0-1 or later	
	PostgreSQL 8.2	3.0.0-1 or later	
	PostgreSQL 8.3	3.0.0-1 or later	
	PostgreSQL 8.4	3.0.0-1 or later	
	PostgreSQL 9.0	3.0.3-1 or later	
	PostgreSQL 9.1	3.1.0-1 or later	
	PostgreSQL 9.2	3.1.7-1 or later	
	PowerGres on Linux 6.0	3.0.0-1 or later	
	PowerGres on Linux 7.0	3.0.0-1 or later	
	PowerGres on Linux 7.1	3.0.0-1 or later	
	PowerGres on Linux 9.0	3.0.3-1 or later	
PowerGres Plus V5.0	3.0.0-1 or later		
MySQL monitor	MySQL 5.0	3.0.0-1 or later	
	MySQL 5.1	3.0.0-1 or later	
	MySQL 5.5	3.0.3-1 or later	
	MySQL 5.6	3.1.8-1 or later	
Sybase monitor	Sybase ASE 15.0	3.0.0-1 or later	
	Sybase ASE 15.5	3.1.0-1 or later	
	Sybase ASE 15.7	3.1.0-1 or later	
Samba monitor	Samba 3.0	3.0.0-1 or later	
	Samba 3.2	3.0.0-1 or later	
	Samba 3.3	3.0.0-1 or later	
	Samba 3.4	3.0.0-1 or later	
	Samba 3.5	3.1.5-1 or later	
	Samba 4.0	3.1.8-1 or later	
nfs monitor	nfsd 2 (udp)	3.0.0-1 or later	
	nfsd 3 (udp)	3.1.5-1 or later	

	nfsd 4 (tcp)	3.1.5-1 or later	
	mountd 1 (tcp)	3.0.0-1 or later	
	mountd 2 (tcp)	3.1.5-1 or later	
	mountd 3 (tcp)	3.1.5-1 or later	
HTTP monitor	No Specified version	3.0.0-1 or later	
SMTP monitor	No Specified version	3.0.0-1 or later	
pop3 monitor	No Specified version	3.0.0-1 or later	
imap4 monitor	No Specified version	3.0.0-1 or later	
ftp monitor	No Specified version	3.0.0-1 or later	
Tuxedo monitor	Tuxedo 10g Release 3	3.0.0-1 or later	
	Tuxedo 11g Release 1	3.0.0-1 or later	
OracleAS monitor	Oracle Application Server 10g Release 3 (10.1.3.4)	3.0.0-1 or later	
Weblogic monitor	WebLogic Server 10g R3	3.0.0-1 or later	
	WebLogic Server 11g R1	3.0.0-1 or later	
	WebLogic Server 12c	3.1.3-1 or later	
Websphere monitor	WebSphere 6.1	3.0.0-1 or later	
	WebSphere 7.0	3.0.0-1 or later	
	WebSphere 8.0	3.1.5-1 or later	
	WebSphere 8.5	3.1.8-1 or later	
WebOTX monitor	WebOTX V7.1	3.0.0-1 or later	
	WebOTX V8.0	3.0.0-1 or later	
	WebOTX V8.1	3.0.0-1 or later	
	WebOTX V8.2	3.0.0-1 or later	
	WebOTX V8.3	3.1.0-1 or later	
	WebOTX V8.4	3.1.0-1 or later	
	WebOTX V8.5	3.1.5-1 or later	
	WebOTX V9.1	3.1.10-1 or later	
JVM monitor	WebLogic Server 11g 1	3.1.0-1 or later	
	WebLogic Server 12c	3.1.3-1 or later	
	WebOTX V8.2	3.1.0-1 or later	
	WebOTX V8.3	3.1.0-1 or later	
	WebOTX V8.4	3.1.0-1 or later	
	WebOTX V8.5	3.1.5-1 or later	
	WebOTX V9.1	3.1.10-1 or later	
	WebOTX Enterprise Service Bus V8.4	3.1.3-1 or later	
	WebOTX Enterprise Service Bus V8.5	3.1.5-1 or later	

	JBoss Application Server 4.2.3.GA/5.1.0.GA	3.1.0-1 or later	
	JBoss Enterprise Application Platform 4.3.0.GA_CP06	3.1.0-1 or later	
	Apache Tomcat 6.0	3.1.0-1 or later	
	Apache Tomcat 7.0	3.1.3-1 or later	
	WebSAM SVF for PDF 9.0	3.1.3-1 or later	
	WebSAM SVF for PDF 9.1	3.1.4-1 or later	
	WebSAM Report Director Enterprise 9.0	3.1.3-1 or later	
	WebSAM Report Director Enterprise 9.1	3.1.5-1 or later	
	WebSAM Universal Connect/X 9.0	3.1.3-1 or later	
	WebSAM Universal Connect/X 9.1	3.1.5-1 or later	
	Oracle iPlanet Web Server 7.0	3.1.3-1 or later	
System monitor	No specified version	3.1.0-1 or later	

## Operation environment for SNMP linkage functions

The tables below list the SNMP agents on which the operation of the SNMP linkage functions was verified.

IA32

Distribution	SNMP agent	ExpressCluster version	Remarks
Red Hat Enterprise Linux 5.4	Net-SNMP 5.3.2.2	3.1.0-1 or later	
Red Hat Enterprise Linux 5.6	Net-SNMP 5.3.2.2	3.1.0-1 or later	
Red Hat Enterprise Linux 6.1	Net-SNMP 5.5	3.1.0-1 or later	
Novell SUSE LINUX Enterprise Server 11 (SP1)	Net-SNMP 5.4.2.1	3.1.0-1 or later	

x86\_64

Distribution	SNMP agent	ExpressCluster version	Remarks
Red Hat Enterprise Linux 5.4	Net-SNMP 5.3.2.2	3.1.0-1 or later	
Red Hat Enterprise Linux 5.6	Net-SNMP 5.3.2.2	3.1.0-1 or later	
Red Hat Enterprise Linux 6.1	Net-SNMP 5.5	3.1.0-1 or later	
Novell SUSE LINUX Enterprise Server 11 (SP1)	Net-SNMP 5.4.2.1	3.1.0-1 or later	
Oracle Enterprise Linux 5 (5.5)	Net-SNMP 5.3.2.2	3.1.0-1 or later	

---

**Note:** Use Novell SUSE LINUX Enterprise Server 11 (SP1) or later to obtain SNMP information on a Novell SUSE LINUX Enterprise Server.

---

## Operation environment for JVM monitor

The use of the JVM monitor requires a Java runtime environment.

Java<sup>®</sup> Runtime Environment  
Version 6.0 Update 21 (1.6.0\_21) or later

Java<sup>®</sup> SE Development Kit  
Version 6.0 Update 21 (1.6.0\_21) or later

Java<sup>®</sup> Runtime Environment  
Version 7.0

Java<sup>®</sup> SE Development Kit  
Version 7.0

Open JDK

The tables below list the load balancers that were verified for the linkage with the JVM monitor.

IA32

Load balancer	ExpressCluster version	Remarks
Express5800/LB400h	3.1.0-1 or later	
BIG-IP v11	3.1.3-1 or later	
MIRACLE LoadBalancer	3.1.3-1 or later	
CoyotePoint Equalizer	3.1.3-1 or later	

x86\_64

Load balancer	ExpressCluster version	Remarks
Express5800/LB400h	3.1.0-1 or later	
BIG-IP v11	3.1.3-1 or later	
MIRACLE LoadBalancer	3.1.3-1 or later	
CoyotePoint Equalizer	3.1.3-1 or later	

# Preparing and verifying the server environment before installation

After installing the hardware, verify the following:

1. Network settings (Required)
2. Root file system (Required)
3. Firewall settings (Required)

## 1. Verifying the network settings (Required)

Check the following network settings by using the `ifconfig` and `ping` commands.

- ◆ IP Address
- ◆ Host name

## 2. Verifying the root file system (Required)

It is recommended to use a file system which is capable of journaling for the root file system in the operating system. Linux (version 2.6 or later) supports journaling file systems such as `ext3`, `JFS`, `ReiserFS`, and `XFS`.

---

### **Important:**

If a file system that is not capable of journaling is used, you must run an interactive command (`fsck` for the root file system) when rebooting the server after server or OS stop (when normal shutdown could not be done).

---

### 3. Verifying the firewall settings (Required)

By default, ExpressCluster X SingleServerSafe uses the port numbers below. You can change these port numbers by using the Builder. Do not access any of these port numbers from a program other than ExpressCluster X SingleServerSafe. When setting up a firewall, set up ExpressCluster X SingleServerSafe so that it can access the port numbers below.

Internal processing in the local server					
From			To		Remarks
Server	Automatic allocation	→	Server	29001/TCP	Internal communication
Server	Automatic allocation	→	Server	29002/TCP	Data transfer
Server	Automatic allocation	→	Server	29003/UDP	Alert synchronization
Server	Automatic allocation	→	Server	XXXX/UDP	Internal communication for log

From the WebManager to the server					
From			To		Remarks
WebManager	Automatic allocation	→	Server	29003/TCP	http communication

From the server connected to the Integrated WebManager to the target server					
From			To		Remarks
Server connected to the Integrated WebManager	Automatic allocation	→	Server	29003/TCP	http communication
Server to be managed by the Integrated WebManager	29003	→	Client	29010/UDP	UDP communication

From the server connected to the Integrated WebManager to the target server					
From			To		Remarks
Server	Automatic allocation	→	Monitoring target	Management port number set by the Builder	JVM monitor
Server	Automatic allocation	→	Monitoring target	Connection port number set by the Builder	JVM monitor
Server	Automatic allocation	→	Monitoring target	Load balancer linkage management port number set by the Builder	JVM monitor
Server	Automatic allocation	→	Monitoring target	Communication port number set by the Builder	JVM monitor

---

**Note 1:**

An available port number at the time is automatically assigned.

**Note 2:**

On the **Port Number** tab in **Cluster Properties**, select **UDP** for log communication, and use the port number specified for **Port Number**. The default log communication method, **UNIX Domain**, does not use a communication port.

---



# Chapter 2      Installing ExpressCluster X SingleServerSafe

This chapter describes how to install ExpressCluster X SingleServerSafe. To install ExpressCluster X SingleServerSafe, install the ExpressCluster X SingleServerSafe, which is the main module of ExpressCluster SingleServerSafe. If you have a separate machine for setting up SingleServerSafe, install the Builder on that machine.

This chapter covers:

- Steps from installing ExpressCluster X SingleServerSafe to setting up the server..... 46
- Installing the ExpressCluster X SingleServerSafe..... 47
- Registering the license ..... 50
- Installing the offline version of the ExpressCluster Builder ..... 62
- Starting the Builder..... 65

## Steps from installing ExpressCluster X SingleServerSafe to setting up the server

The following summarizes the steps of ExpressCluster X SingleServerSafe installation, system creation, license registration, and confirmation of the installed system described in this chapter.

Before proceeding to the steps, make sure to read Chapter 1, “About ExpressCluster X SingleServerSafe” to confirm the system requirements and configuration.

### 1. Installing the ExpressCluster X SingleServerSafe

Install the ExpressCluster X SingleServerSafe, which is the core ExpressCluster X SingleServerSafe module, on each target server.

### 2. Registering the license

Register the license by running the `clplcncs` command.

### 3. Creating the configuration data by using the ExpressCluster Builder

Create the configuration data by using the ExpressCluster Builder.

Refer to Chapter 2, “Creating configuration data” in the *ExpressCluster X SingleServerSafe Configuration Guide*.

### 4. Setting up a server

Apply the configuration data created using the Builder to set up a server.

When using the online version of the ExpressCluster Builder, Apply the configuration data by using `it` or `clpcfctrl` command.

When using the offline version of the ExpressCluster Builder, Apply the configuration data by using `clpcfctrl` command.

Refer to Chapter 2, “Creating the configuration data” in the *ExpressCluster X SingleServerSafe Configuration Guide*.

### 5. Verifying the cluster status using the WebManager

Check the status of the server by using the ExpressCluster WebManager.

Refer to Chapter 3, “Verifying the system” in the *ExpressCluster X SingleServerSafe Configuration Guide*.

---

#### Related Information:

Refer to the *ExpressCluster X SingleServerSafe Configuration Guide* as you proceed in accordance with the procedures in this guide. For the latest information on the system requirements and release information, see Chapter 1, “About ExpressCluster X SingleServerSafe” and Chapter 4, “Latest version information” in this guide.

---

## Installing the ExpressCluster X SingleServerSafe

Install the ExpressCluster X SingleServerSafe, which is the main module of ExpressCluster X SingleServerSafe, into the target server machine.

License registration is required in installing the ExpressCluster X SingleServerSafe. Make sure to have the required license file or license sheet.

### Installing ExpressCluster X SingleServerSafe for the first time

To install ExpressCluster X SingleServerSafe, follow the procedure below.

---

**Note:**

Log in as a root user when installing the ExpressCluster X SingleServerSafe RPM.

---

1. Mount (mount) the installation CD-ROM.
2. Run the rpm command to install the package file.  
The installation RPM varies depending on the products.

Navigate to the folder, /Linux/3.2/en/server, in the CD-ROM and run the following:

```
rpm -i expressclssss-version.architecture.rpm
```

The architecture is i686 or x86\_64. Select one of them according to the environment where the server RPM is installed. Verify the architecture by running the arch command.

The installation starts.

---

**Note:** ExpressCluster X SingleServerSafe will be installed in the following directory. You will not be able to uninstall the ExpressCluster if you change this directory.  
Installation directory: /opt/nec/clusterpro

---

3. When the installation is completed, unmount (umount) the installation CD-ROM.
4. Remove the installation CD-ROM.

---

**Related Information:**

The use of the SNMP linkage function requires additional settings.

For how to set up the SNMP linkage function, see "Setting up the SNMP linkage function"

---

## Setting up the SNMP linkage function

To handle information acquisition requests on SNMP, Net-SNMP must be installed separately and the SNMP linkage function must be registered separately.

Follow the procedure below to set up the SNMP linkage function.

---

**Note 1:**

To set up the SNMP linkage function, you must log in as the root user.

**Note 2:**

The description related to Net-SNMP in the installation procedure may vary depending on the distribution.

---

1. Install Net-SNMP.
2. Stop the snmpd daemon.

---

**Note:** The daemon can usually be stopped by the following command:  
`/etc/init.d/snmpd stop`

---

3. Register the SNMP linkage function of ExpressCluster in the configuration file for the snmpd daemon.

Open the configuration file with a text editor, and then add the following description to the end of the file.

```
dlmod clusterManagementMIB /opt/nec/clusterpro/lib/libclpmtmib.so
```

---

**Note 1:**

The configuration file for the Net-SNMP snmpd daemon is usually located in the following directory:

```
/etc/snmp/snmpd.conf
```

**Note 2:**

Add the OID of ExpressCluster in the MIB view (view definition by snmpd.conf) permitted by the snmpd daemon.

The OID of ExpressCluster is ".1.3.6.1.4.1.119.2.3.207".

---

4. Create symbolic links to libraries needed by the SNMP linkage function.

The following three symbolic links are needed.

libnetsnmp.so  
libnetsnmpagent.so  
libnetsnmphelpers.so

Follow the procedure below to create the symbolic links.

4 - 1. Confirm the presence of the symbolic links.

Change to following directory.

If those symbolic links exist in the following directory, proceed to step 5.

IA-32 : /usr/lib  
x86\_64, ppc64 : /usr/lib64

4 - 2. Create symbolic links

Run the following commands.

```
ln -s libnetsnmp.so.X libnetsnmp.so  
ln -s libnetsnmpagent.so.X libnetsnmpagent.so  
ln -s libnetsnmphelpers.so.X libnetsnmphelpers.so
```

Substitute a numeric value for X according to the environment.

5. Start the snmpd daemon.

---

**Note:** The daemon can usually be started by the following command:  
`/etc/init.d/snmpd start`

---

---

**Related Information:**

You must cancel the settings of the SNMP function when uninstalling the ExpressCluster Server. For how to cancel the settings of the SNMP linkage function, see "Canceling the SNMP linkage function settings"

---

---

**Note:**

The settings required for SNMP communication are to be made on the SNMP agent.

---

## Registering the license

### Registering the CPU license

You must register the CPU license to run the system you create.

---

**Related Information:** When the virtual server exists in the cluster system to be constructed, VM node license can be used not CPU license for the virtual server. CPU license and VM node license cannot be mixed. For the details about registration of VM node license, see “Registering the VM node license”.

---

There are two ways of license registration; using the information on the license sheet and specifying the license file. These two ways are described for both the product and trial versions.

#### Product version

- ◆ Specify the license file as the parameter of the license management command. (Refer to “Registering the license by specifying the license file (for both the product version and trial version)”.)
- ◆ Register the license by running the license management command and interactively entering the license information that comes with the licensed product. (Refer to “Registering the license interactively from the command line (product version)”.)

#### Trial version

- ◆ Specify the license file as the parameter of the license management command. (Refer to “Registering the license by specifying the license file (for both the product version and trial version)”.)

## Registering the license by specifying the license file (for both the product version and trial version)

The following describes how you register the license by specifying the license file when you have a license for the product version or trial version.

Check the following before executing these steps.

- ◆ You can log on as a root user to the server on which you are going to set up a system.
1. Log on to the server you are going to set up as a root user, and then run the following command:

```
# clplcns -i filepath -p PRODUCT-ID
```

Specify the path to the license file for *filepath* specified by the *-i* option.

Specify the following product ID for *PRODUCT-ID* specified by the *-p* option. Enter the product ID of the product which you are using.

License product name	Product ID
ExpressCluster X SingleServerSafe 3.2 for Linux	XSS32

When the command is successfully executed, the message “Command succeeded.” is displayed in the console. If another message is displayed, refer to Chapter 2, “ExpressCluster X SingleServerSafe command reference” in the *ExpressCluster X SingleServerSafe Operation Guide*.

2. Run the following command to verify the licenses registered. In *PRODUCT-ID*, enter the product ID specified in step 1.

```
# clplcns -l -p PRODUCT-ID
```

3. When an optional product is not used, proceed to “Registering the node license”.
4. When not using any optional products, restart the server by using the OS shutdown command to validate the license registration and run the server.  
After restarting, proceed to Chapter 2, “Creating the configuration data” in the *ExpressCluster X SingleServerSafe Configuration Guide*, and follow the procedure.

## Registering the license interactively from the command line (product version)

The following describes how you register the license for the product version interactively from the command line.

Before you register the license, make sure that:

- ◆ You have the license sheet you officially obtained from the sales agent. The license sheet is sent to you when you purchase the product. The values on this license sheet are used for registration.
- ◆ You can log on to the server on which you are going to set up a system as a root user.

### Related Information:

The `clplcnsnc` command is used in the following procedures. For details about how to use the `clplcnsnc` command, refer to Chapter 2, “ExpressCluster X SingleServerSafe command reference” in the *ExpressCluster X SingleServerSafe Operation Guide*.

1. Have the license sheet.

The instruction here is given using the values in the following license sheet as an example. When actually entering the values, modify them according to the information on your license sheet.

Product	<b><u>ExpressCluster X SingleServerSafe 3.2 for Linux</u></b>
License information:	
Type	Product version
License Key	A1234567- B1234567- C1234567- D1234567
Serial Number	AAA0000000
Number of Licensed CPUs	2

2. Log on to the server you are going to set up as a root user, and then run the following command:

```
# clplcnsnc -i -p PRODUCT-ID
```

Specify the following product ID for *PRODUCT-ID* specified by the `-p` option. Enter the product ID of the product which you are using.

License product name	Product ID
ExpressCluster X SingleServerSafe 3.2 for Linux	XSS32

3. The text that prompts you to enter the license version is displayed. Enter **1** when using a product version:

```
Selection of License Version.
 1 Product version
 2 Trial version
Select License Version [1 or 2]...1
```

- The text that prompts you to enter the number of licenses is displayed. The default value 2 is set for the number of licenses. If the number written in your license sheet is 2, simply press ENTER without entering any value. When the value written in your license sheet is other than 2, enter the correct value and press ENTER.

```
Enter the number of license [0(Virtual OS) or 1 to 99
(default:2)]... 2
```

- The text that prompts you to enter the serial number is displayed. Enter the serial number written in your license sheet. Note this is case sensitive.

```
Enter serial number [Ex. XXX0000000]... AAA0000000
```

- The text that prompts you to enter the license key is displayed. Enter the license key written in your license sheet. Note this is case sensitive.

```
Enter license key
[XXXXXXXX-XXXXXXXX-XXXXXXXX-XXXXXXXX]...
A1234567-B1234567-C1234567-D1234567
```

When the command is successfully executed, the message “Command succeeded.” is displayed in the console. If another message is displayed, refer to Chapter 2, “ExpressCluster X SingleServerSafe command reference” in the *ExpressCluster X SingleServerSafe Operation Guide*.

- Run the following command to verify the licenses registered. In *PRODUCT-ID*, enter the product ID specified in step 2.

```
# clplcncs -l -p PRODUCT-ID
```

- When an optional product is used, proceed to “Registering the node license”.
- If no optional product is used, run the OS shutdown command to reboot the server. After rebooting the server, proceed to Chapter 3, “Verifying the cluster system” in the *ExpressCluster X SingleServerSafe Configuration Guide*, and follow the procedure.

## Registering the VM node license

When the virtual server exists in the cluster system to be constructed, VM node license can be used not CPU license for the virtual server.

CPU license and VM node license cannot be mixed.

There are two ways of license registration; using the information on the license sheet and specifying the license file.

### Product version

- ◆ Specify the license file as the parameter of the license management command. Refer to, Page55, "Registering the VM node license by specifying the license file (Product version)."
- ◆ Register the license by running the license management command and interactively entering the license information that comes with the licensed product. Refer to, Page56, "Registering the VM node license interactively from the command line (Product version)."

## Registering the VM node license by specifying the license file (Product version).

The following describes how you register the license by specifying the license file when you have a license for the product version.

1. A virtual server of which you intend to construct a cluster, log on to the server as root user and run the following command.

```
# clplcncs -i filepath -p PRODUCT-ID
```

Specify the path to the license file for filepath specified by the `-i` option.

Specify the product ID for PRODUCT-ID specified by the `-p` option. The following is the product ID list.

License Product Name	Product ID
ExpressCluster X SingleServerSafe 3.2 for Linux VM	XSS32

When the command is successfully executed, the message “Command succeeded” is displayed on the console. When a message other than this is displayed, see Chapter 2, “ExpressCluster X SingleServerSafe command reference” in the *ExpressCluster X SingleServerSafe Operation Guide*.

2. Run the following command to verify the licenses registered. In PRODUCT-ID, enter the product ID specified in Step 1 of this procedure.

```
# clplcncs -l -p PRODUCT-ID
```

3. When using option products, see “Registering the node license”.
4. When not using option products, run the OS shutdown command to reboot the server. By doing this, the license registration becomes effective and you can start using the cluster. After rebooting the server, proceed to Chapter 3, “Checking the cluster system” in the *ExpressCluster X SingleServerSafe Configuration Guide*.



4. The text that prompts you to enter the number of licenses is displayed. The default value 2 is being displayed. For VM license, enter 0 and press Enter.

```
Enter the number of license [0(Virtual OS) or 1 to 99  
(default:2)]... 0
```

5. The text that prompts you to enter the serial number is displayed. Enter the serial number written in your license sheet. Note this is case sensitive.

```
Enter serial number [Ex. XXX0000000]... AAA0000000
```

6. The text that prompts you to enter the license key is displayed. Enter the license key written in your license sheet. Note this is case sensitive.

```
Enter license key  
[XXXXXXXX-XXXXXXXX-XXXXXXXX-XXXXXXXX]...  
A1234567-B1234567-C1234567-D1234567
```

When the command is successfully executed, the message "Command succeeded" is displayed on the console. When a message other than this is displayed, see Chapter 2, "ExpressCluster X SingleServerSafe command reference" in the *ExpressCluster X SingleServerSafe Operation Guide*.

7. Run the following command to verify the licenses registered. In PRODUCT-ID, enter the product ID specified in the Step 2.

```
# clplcncs -l -p PRODUCT-ID
```

8. When using option products, see "Registering the node license".
9. When not using option products, run the OS shutdown command to reboot the server. After rebooting the server, proceed to next Chapter 3, "Checking the cluster system" in the *ExpressCluster X SingleServerSafe Configuration Guide*.

## Registering the node license

It is required to register a node license for X 3.2 Agent products and X 3.2 Alert Service (hereafter referred to as “optional products”) to operate them on the system.

Register the node license for the set up server on which to use optional products. There are two ways of license registration; using the information on the license sheet and specifying the license file. These two ways are described for both the product and trial versions.

### Product version

- ◆ Specify the license file as the parameter of the license management command.  
(Refer to “Registering the license by specifying the license file (for both the product version and trial version)”.)
- ◆ Register the license by running the license management command and interactively entering the license information that comes with the licensed product.  
(Refer to “Registering the node license interactively from the command line (product version)”.)

### Trial version

- ◆ Specify the license file as the parameter of the license management command.  
(Refer to “Registering the license by specifying the license file (for both the product version and trial version)”.)

## Registering the license by specifying the license file (for both the product version and trial version)

The following describes how you register the license by specifying the license file when you have a license for the product version or trial version.

Check the following before executing these steps.

- ◆ You can log on as a root user to the server on which you are going to use an optional product.
1. Of the servers you are going to set up, log on to the server on which the optional product is to be used as a root user, and then run the following command:

```
# clplcncs -i filepath -p PRODUCT-ID
```

Specify the path to the license file for *filepath* specified by the *-i* option.

Specify the product ID for *PRODUCT-ID* specified by the *-p* option. The product IDs are listed below. Enter the product ID that corresponds to the optional product you are using.

License product name	Product ID
ExpressCluster X Database Agent 3.2 for Linux	DBAG32
ExpressCluster X Internet Server Agent 3.2 for Linux	ISAG32
ExpressCluster X File Server Agent 3.2 for Linux	FSAG32
ExpressCluster X Application Server Agent 3.2 for Linux	ASAG32
ExpressCluster X Alert Service 3.2 for Linux	ALRT32
ExpressCluster X Java Resource Agent 3.2 for Linux	JRAG32
ExpressCluster X System Resource Agent 3.2 for Linux	SRAG32

When the command is successfully executed, the message “Command succeeded.” is displayed in the console. If another message is displayed, see Chapter 2, “ExpressCluster X SingleServerSafe command reference” in the *ExpressCluster X SingleServerSafe Configuration Guide*.

2. Run the following command to verify the licenses registered. In *PRODUCT-ID*, enter the product ID specified in step 1.

```
# clplcncs -l -p PRODUCT-ID
```

3. Restart the server by using the OS shutdown command to validate the license registration and run the server.  
After restarting, proceed to Chapter 2, “Creating the configuration data” in the *ExpressCluster X SingleServerSafe Configuration Guide*, and follow the procedure.

## Registering the node license interactively from the command line (product version)

The following describes how you register the license for the product version interactively from the command line.

Before you register the license, make sure that:

- ◆ You have the license sheet you officially obtained from the sales agent. The license sheet is sent to you when you purchase the product. The number of license sheets you need is as many as the number of servers on which the option product will be used. The values on this license sheet are used for registration.
- ◆ Of the servers you are going to set up, you can log on to the server on which the optional product is to be used as a root user.

---

### Related Information:

The `clplcnsnc` command is used in the following procedures. For details about how to use the `clplcnsnc` command, refer to Chapter 2, “ExpressCluster X SingleServerSafe command reference” in the *ExpressCluster X SingleServerSafe Configuration Guide*.

---

1. Have the license sheet.

The instruction here is given using the values in the following license sheet (Database Agent) as an example. When actually entering the values, modify them according to the information on your license sheet.

Product	<b><u>ExpressCluster X Database Agent 3.2 for Linux</u></b>
License information:	
Type	Product version
License Key	A1234567- B1234567- C1234567- D1234567
Serial Number	AAA0000000
Number of nodes	1

2. Of the servers you are going to set up, log on to the server on which the optional product is to be used as the root user, and then run the following command:

```
# clplcnsnc -i -p PRODUCT-ID
```

Specify the product ID for *PRODUCT-ID* specified by the `-p` option. The product IDs are listed below. Enter the product ID that corresponds to the optional product you are using.

License product name	Product ID
ExpressCluster X Database Agent 3.2 for Linux	DBAG32
ExpressCluster X Internet Server Agent 3.2 for Linux	ISAG32
ExpressCluster X File Server Agent 3.2 for Linux	FSAG32
ExpressCluster X Application Server Agent 3.2 for Linux	ASAG32
ExpressCluster X Alert Service 3.2 for Linux	ALRT32
ExpressCluster X Java Resource Agent 3.2 for Linux	JRAG32
ExpressCluster X System Resource Agent 3.2 for Linux	SRAG32

3. The text that prompts you to enter the license version is displayed. Enter **1** since it is a product version:

```
Selection of License Version.  
 1 Product Version  
 2 Trial Version  
Select License Version [1 or 2]...1
```

4. The text that prompts you to enter the serial number is displayed. Enter the serial number written in your license sheet. Note this is case sensitive.

```
Enter serial number [Ex. XXX0000000]... AAA0000000
```

5. The text that prompts you to enter the license key is displayed. Enter the license key written in your license sheet. Note this is case sensitive.

```
Enter license key  
[XXXXXXXX-XXXXXXXX-XXXXXXXX-XXXXXXXX]...  
A1234567-B1234567-C1234567-D1234567
```

When the command is successfully executed, the message “Command succeeded.” is displayed in the console. If another message is displayed, refer to Chapter 2, “ExpressCluster X SingleServerSafe command reference” in the *ExpressCluster X SingleServerSafe Operation Guide*.

6. Run the following command to verify the licenses registered. In **PRODUCT-ID**, enter the product ID specified in the step 2.

```
# clplcns -l -p PRODUCT-ID
```

7. Restart the server by using the OS shutdown command to validate the license registration and run the server.  
After restarting, proceed to Chapter 2, “Creating the configuration data” in the *ExpressCluster X SingleServerSafe Configuration Guide*, and follow the procedure.

## Installing the offline version of the ExpressCluster Builder

It is not necessary to install the offline version of the ExpressCluster Builder on the server on which ExpressCluster X SingleServerSafe is installed. If you will create or modify the configuration data of ExpressCluster X SingleServerSafe by using a machine that cannot access ExpressCluster X SingleServerSafe through a Web browser, you need to install the offline version of the ExpressCluster Builder on that machine.

### Installing the ExpressCluster Builder into a Windows machine (offline version)

Follow the procedures below to install the offline version of the ExpressCluster Builder .

---

**Note:**

Install the ExpressCluster Builder with the administrator privileges. In case the ExpressCluster Builder has already been installed, first uninstall and install again, or install by specify another install destination.

---

1. Insert the Installation CD-ROM to the CD-ROM drive.
2. The menu screen for installation is displayed.



- 3.

---

**Note:**

If the menu screen does not open automatically, double-click menu.exe in the root folder of the CD-ROM.

---

4. Select **ExpressCluster(R) SingleServerSafe for Linux**.




5. Select **ExpressCluster(R) SingleServerSafe Builder**.



6. Select **ExpressCluster(R) SingleServerSafe Builder**.



7. Select where to install in the **Cluster Builder self-extracting dialog** and click **Extract**.




---

**Note:**

The folder `\EXPRESSCLUSTER SSS \clpbuilder-1` is created in the specified installation folder, and the HTML file `clptrek.htm`, which is for Builder window display, and various configuration data files are installed in this folder.

---

8. Click **OK** in the **ZIP self-extract** dialog box. Installation is completed.



## Starting the Builder

The *online version of the Builder* runs on a machine (including the local server) capable of connecting to the server that uses ExpressCluster X SingleServerSafe over the network. The Builder that you start without a network connection is called the *offline version of the Builder*. While what you see and specify on the screen are the same for both versions, the way you start the Builder and how the settings are applied differ.


The procedure for each version is described below.

### Starting the online version of the Builder

To start the online version of the ExpressCluster Builder, follow the procedure below.

1. Start the WebManager. Start your browser, and then enter the IP address and port number of the server where ExpressCluster X SingleServerSafe is installed in the Address bar.

`http://192.168.0.3:29003/`



The port number for the WebManager specified at installation. (Default value 29003)

Specify the IP address of the server on which ExpressCluster X SingleServerSafe is installed. For the local server, the IP address may be specified as `localhost`.

---

#### Note 1:


You cannot start the WebManager unless you restart the server after installing ExpressCluster X SingleServerSafe. Be sure to restart the server.

#### Note 2:

Starting the WebManager requires the JRE. Be sure to install the JRE in advance.

---


2. Click **Config Mode** on the **View** menu to switch to the setup mode (Builder (online version)).



## Starting the offline version of the Builder

To start the offline version of the ExpressCluster Builder, follow the procedure below.

1. Double-click the HTML file `clptrek.htm`, which is for the Builder window display and is in the installation folder.
2. The browser opens.
3. If a security warning is displayed, click **OK**.



---

**Note:**

Starting the Builder requires the JRE. Be sure to install the JRE in advance.

---

# Chapter 3      Upgrading, uninstalling or reinstalling

This chapter describes how to upgrade ExpressCluster X SingleServerSafe, uninstall and reinstall ExpressCluster X SingleServerSafe, and upgrade to ExpressCluster X.

This chapter covers:

- Updating ExpressCluster X SingleServerSafe ..... 68
- Uninstalling ExpressCluster X SingleServerSafe ..... 70
- Reinstalling ExpressCluster X SingleServerSafe ..... 72
- Upgrading to ExpressCluster X ..... 73

---

**Linkage Information:**

For the update from X3.0/X3.1 to X3.2, see "Update Guide".

---

## Updating ExpressCluster X SingleServerSafe

An older version of ExpressCluster X SingleServerSafe can be updated to the latest version.

### Updating the ExpressCluster X SingleServerSafe RPM

Before starting the upgrade, read the following notes.

- ◆ ExpressCluster X SingleServerSafe 2.1 for Linux can be upgraded to ExpressCluster X SingleServerSafe 3.2 for Linux. Upgrading from other versions is not possible.
- ◆ To upgrade from ExpressCluster X SingleServerSafe 2.1 for Linux to ExpressCluster X SingleServerSafe 3.2 for Linux, the license for ExpressCluster X SingleServerSafe 3.2 for Linux (including the licenses for any used optional products) is required.

To update server rpm version 2.1.0-1 or later to 3.0.0-1 or later, perform the following procedure.

---

**Note:**

To upgrade, use an account that has root privileges.

---

1. Run `chkconfig --del name` and follow the procedures below to disable services. For *name*, specify one of the following:
  - `clusterpro_alertsync`
  - `clusterpro_webmgr`
  - `clusterpro`
  - `clusterpro_trn`
  - `clusterpro_evt`
2. Shut down the server by using the WebManager or `clpstdn` command, and then reboot it.
3. Mount the installation CD-ROM.
4. Make sure that the ExpressCluster services are not running, and then execute the `rpm` command to install the package file.  
The installation RPM varies depending on the architecture.

Navigate to the folder, `/Linux/3.2/en/server`, in the CD-ROM and run the following:

```
rpm -U expressclssss-version.architecture.rpm
```

The architecture is `i686` or `x86_64`. Select one of them according to the environment where the server RPM is installed. Verify the architecture by running the `arch` command.

ExpressCluster X SingleServerSafe is installed in the directory below. You will not be able to uninstall the ExpressCluster if you change this directory.

Installation directory: `/opt/nec/clusterpro`

5. After installation, `umount` (umount) and remove the installation CD-ROM.

6. Run **chkconfig --add name** and follow the procedures below to enable the service. For *name*, specify one of the names below. For SuSE Linux, execute the command with the *--force* option.
  - clusterpro\_evt
  - clusterpro\_trn
  - clusterpro\_webmgr
  - clusterpro\_alertsync
7. Restart the server.
8. Register the license. For details on registering license, see “Chapter 2 Registering the license” in this guide.
9. Connect the WebManager to one of the server of the cluster.
10. Start the Builder from the connected WebManager. For details on how to start the online Builder, see “Starting the online version of the Builder”.
11. Confirm that the server of the cluster is started, and then upload the configuration data from the online Builder. For details on how to operate the online Builder, see the *ExpressCluster X SingleServerSafe Configuration Guide*.
12. Enable the services in the following order by running the **chkconfig --add name** command. Specify the following services on *name*.
  - clusterpro
13. Run **Restart Manager** on the WebManager.
14. Restart the browser connecting the WebManager.
15. Run **Start Cluster** on the WebManager.

## Uninstalling ExpressCluster X SingleServerSafe

### Uninstalling ExpressCluster X SingleServerSafe

---

**Note:**

You must log on as a root user to uninstall ExpressCluster X SingleServerSafe.

---

To uninstall ExpressCluster X SingleServerSafe, follow the procedure below.

1. If the SNMP linkage function has been used, you must cancel the linkage before uninstalling ExpressCluster Server. For how to cancel the settings of the SNMP linkage function, see "Canceling the SNMP linkage function settings"
  2. Run the `chkconfig --del name` to disable the following services in this order.
    - clusterpro\_alertsync
    - clusterpro\_webmgr
    - clusterpro
    - clusterpro\_trn
    - clusterpro\_evt
  3. Shut down the server by using the WebManager or `clpstdn` command, and then restart it.
  4. Run the `rpm -e expressclssss` command.
- 

**Note:**

Do not specify other options than the one stated above.

---

### Uninstalling the offline version of the ExpressCluster Builder

**For Windows**

To uninstall the ExpressCluster Builder, follow the procedures below:

1. Close all Web browsers (and then confirm that the JavaVM icon is no longer in the task tray).
2. Delete the ExpressCluster Builder installation folder from Windows Explorer.

## Canceling the SNMP linkage function settings

You must cancel the SNMP function settings before uninstalling the ExpressCluster Server.

Follow the procedure below to cancel the SNMP linkage function settings.

---

**Note 1:**

To cancel the SNMP linkage function settings, you must log in as the root user.

**Note 2:**

The description related to Net-SNMP in the uninstallation procedure may vary depending on the distribution.

---

1. Stop the Net-SNMP snmpd daemon.

---

**Note:** The daemon can usually be stopped by the following command:  
`/etc/init.d/snmpd stop`

---

2. Cancel registration of the SNMP linkage function in the configuration file for the snmpd daemon.

Open the configuration file with a text editor, and then delete the following line from the file.

```
dlmod clusterManagementMIB /opt/nec/clusterpro/lib/libclpmgmtmib.so
```

---

**Note 1:**

The configuration file for the snmpd daemon is usually located in the following directory:  
`/etc/snmp/snmpd.conf`

**Note 2:**

Delete the OID of ExpressCluster from the MIB view (view definition by snmpd.conf) permitted by the snmpd daemon.

The OID of ExpressCluster is ".1.3.6.1.4.1.119.2.3.207".

---

3. If you created symbolic links at "Setting up the SNMP linkage function", delete them.
4. Start the snmpd daemon.

---

**Note:** The daemon can usually be started by the following command:  
`/etc/init.d/snmpd start`

---

## Reinstalling ExpressCluster X SingleServerSafe

### Reinstalling the ExpressCluster SingleServerSafe

To reinstall the ExpressCluster X SingleServerSafe, you have to prepare the cluster configuration data floppy disk created by the Builder (or the latest data floppy disk if you reconfigured the cluster).

If you do not have the cluster configuration data floppy disk created by the Builder (or the latest data floppy disk if you reconfigured the cluster) at hand, you can back up the data with the `clpcfctrl` command. Refer to “Backing up the configuration data” in Chapter 2, “*ExpressCluster X SingleServerSafe* Command reference” in the *ExpressCluster X SingleServerSafe Operation Guide*.

To reinstall the ExpressCluster X, follow the procedures below:

1. Uninstall the ExpressCluster X SingleServerSafe.  
For details about the uninstallation procedure, see “Uninstalling ExpressCluster X SingleServerSafe” in this chapter.
2. Install the ExpressCluster X SingleServerSafe and re-create the servers.  
For details about the installation procedure, see Chapter 2, “Installing ExpressCluster X SingleServerSafe” in this guide.

## Upgrading to ExpressCluster X

When upgrading ExpressCluster X SingleServerSafe to ExpressCluster X, you can migrate the configuration data created using the Builder (or the latest data if you changed the configuration).

In this case, save the latest configuration data before starting the upgrade. In addition to saving it to the Builder after creation, you can back up the configuration data by using the `clpcfctrl` command. Refer to “Backing up the configuration data” in Chapter 2, “*ExpressCluster X SingleServerSafe* Command reference” in the *ExpressCluster X SingleServerSafe Operation Guide*.

To upgrade ExpressCluster X SingleServerSafe to ExpressCluster X, follow the procedure below.

1. Back up the configuration data.
2. Uninstall ExpressCluster X SingleServerSafe from the server for which to perform the upgrade. For details about the uninstallation procedure, see “Uninstalling ExpressCluster X SingleServerSafe” in this chapter.
3. Shut down the OS when uninstalling the ExpressCluster X SingleServerSafe is completed.
4. Install ExpressCluster X, and set up its environment. You can use the backup configuration data for this process. For details about how to set up ExpressCluster X, see the ExpressCluster X manual.

---

**Note:**

For ExpressCluster X, register the following licenses:

\* ExpressCluster X SingleServerSafe (two-CPU license)

\* ExpressCluster X SingleServerSafe upgrade license

These licenses can be used for ExpressCluster X (two-CPU license).

---



# Chapter 4 Latest version information

The latest information on the upgraded and improved functions is described in details. The latest information on the upgraded and improved functions is described in details.

This chapter covers:

- Latest version information ..... 76
- ExpressCluster X SingleServerSafe version and corresponding manual editions ..... 77
- Enhanced function information ..... 78
- Corrected information ..... 82

## Latest version information

The latest internal version of ExpressCluster X SingleServerSafe 3.2 for Linux, as of February 2014, is 3.2.0-1.

For the latest information, refer to the latest manual on ExpressCluster website.

Check the internal version of ExpressCluster X SingleServerSafe by using the WebManager.

You can display the internal version of a server by selecting the icon for the server in the tree view of the WebManager.

## ExpressCluster X SingleServerSafe version and corresponding manual editions

This guide assumes the version of ExpressCluster X SingleServerSafe below for its descriptions. Note the version of ExpressCluster X SingleServerSafe and corresponding manual edition.

ExpressCluster X SingleServerSafe internal version	Manual	Edition	Remarks
3.2.0-1	Installation Guide	First Edition	
	Configuration Guide	First Edition	
	Operation Guide	First Edition	
	Integrated WebManager Administrator's Guide	Seventh Edition	
	WebManager Mobile Administrator's Guide	First Edition	

## Enhanced function information

The following functions have been enhanced for each minor versions.

Number	Version	Enhanced function
1	3.0.0-1	It is now possible to operate both the WebManager and Builder from the same browser window.
2	3.0.0-1	The configuration wizard has been updated.
3	3.0.0-1	The configuration wizard can now automatically obtain some settings.
4	3.0.0-1	The Integrated WebManager can now be operated from a browser.
5	3.0.0-1	The settings can now be checked when uploading configuration data.
6	3.0.0-1	ExpressCluster can now be used to manage external failures.
7	3.0.0-1	Dump data can now be obtained if a monitored application times out.
8	3.0.0-1	Detailed Oracle information can now be obtained if an error is detected during Oracle monitoring.
9	3.0.0-1	Guest operating systems of vSphere/XenServer/kvm can now be handled as resources.
10	3.0.0-1	A guest operating system on a virtual platform is now automatically followed even if it is moved by an operation not from ExpressCluster.
11	3.0.0-1	The number of supported operating systems has been increased.
12	3.0.0-1	The number of supported applications has been increased.
13	3.0.2-1	The newly released kernel is now supported.
14	3.0.3-1	The newly released kernel is now supported.
15	3.0.4-1	The newly released kernel is now supported.
16	3.1.0-1	The number of group and resource has been doubled.
17	3.1.0-1	Waiting for startup or stopping a failover group has been enabled.
18	3.1.0-1	A function whereby the WebManager and the clpmonctrl command can be used to trigger a Dummy Failure for a monitor resource has been implemented.
19	3.1.0-1	WebManager that can be connected from an Android terminal has been implemented.
20	3.1.0-1	The MIB of ExpressCluster has been defined.
21	3.1.0-1	An SNMP trap transmission function has been added.
22	3.1.0-1	Information acquisition requests on SNMP are now supported.
23	3.1.0-1	A function has been implemented to execute a specified script to recover a monitor resource. In addition, script execution has been enabled prior to reactivation or failover.
24	3.1.0-1	A function has been implemented to disable recovery action caused by monitor resource error.
25	3.1.0-1	Database monitoring functions have been enhanced.
26	3.1.0-1	Some environment variables have been added for use in scripts.
27	3.1.0-1	Script setting has been simplified by the use of script templates.

28	3.1.0-1	The display of the configuration mode screen has been corrected for the 800*600 screen size.
29	3.1.0-1	Logs can be downloaded even if the browser is set to block popups.
30	3.1.0-1	Functions for which licenses have not been installed are no longer displayed during setup.
31	3.1.0-1	The number of monitor resources that are automatically registered has been increased.
32	3.1.0-1	The default command timeout value for the clprexec command has been changed from 30 seconds to 180 seconds.
33	3.1.0-1	Process name monitor resource (psw) has been added.
34	3.1.0-1	JVM monitor resource (jraw) has been added.
35	3.1.0-1	System monitor resource (sraw) has been added.
36	3.1.0-1	A function has been added to prevent the startup of the ExpressCluster services when the operating system has been shut down abnormally.
37	3.1.0-1	Conditions for triggering the function that stalls shutdown can now be specified.
38	3.1.0-1	Rotating log (internal log) can now be selected as the script execution log for EXEC resources and custom monitor resources (genw).
39	3.1.0-1	A list of registered licenses can now be displayed by using the clplcns command.
40	3.1.0-1	A function for using the clplcns command to delete only the trial license has been added.
41	3.1.0-1	The newly released kernel is now supported.(RHEL5.7, AXS3SP4)
42	3.1.0-1	In linkage with vSphere5, the cluster on the guest operating system has been enabled to control startup and stopping of another guest operating system.
43	3.1.0-1	Timeout decision processing has been improved when an invalid OS time is returned from while running for 447 or 497 continuous days.
44	3.1.1-1	The newly released kernel is now supported. (XenServer6)
45	3.1.1-1	The conditions to wait for the group stop can now be specified. (Cluster stop, server stop)
46	3.1.1-1	The view of the recovery action control function popup window that is displayed at the end of the Cluster Generation Wizard is improved.
47	3.1.1-1	The number of disks of which size is to be monitored by System Resource Agent has been changed from 10 to 64.
48	3.1.3-1	The newly released kernel is now supported.
49	3.1.3-1	A function for displaying time information has been added to WebManager.
50	3.1.3-1	A function for automatically starting or resuming the cluster after reflecting the configuration data has been added.
51	3.1.3-1	A function has been added to prevent a Web browser from being terminated or reloaded when the configuration data is edited in WebManager Config Mode.
52	3.1.3-1	WebManager can now set and display physical machines and virtual machines separately.
53	3.1.3-1	The setting that assumes that a diskfull detection is not an error has been added to the disk monitor resource.
54	3.1.3-1	A function for monitoring the number of processes has been added to the process name monitor resource.
55	3.1.3-1	The Oracle monitor resource has been improved so that a specific error (ORA-1033) which occurs when Oracle is being started is regarded as being the

		normal state.
56	3.1.3-1	The conditions to determine whether a timeout occurs in Database Agent, Java Resource Agent, and System Resource Agent has been enhanced.
57	3.1.3-1	The process to deactivate a resource has been improved so that the process can be executed as far as possible in case of emergency shutdown.
58	3.1.3-1	A message queue has been added as an internal log communication method.
59	3.1.3-1	The JVM monitor resource now supports OpenJDK.
60	3.1.4-1	The newly released kernel is now supported.
61	3.1.4-1	WebManager now supports Java SE Runtime Environment 7.
62	3.1.4-1	The load imposed by the WebLogic monitoring processing by the WebLogic monitor resource has been reduced.
63	3.1.5-1	The newly released kernel is now supported.
64	3.1.5-1	The license information list can be now viewed from WebManager.
65	3.1.5-1	The start/stop linkage processing between the monitor resources and the group resources when the monitoring time is “Active” has been reviewed and accelerated.
66	3.1.5-1	The NFS monitor resource now supports NFS v3 and v4.
67	3.1.5-1	The samba monitor resource now supports samba 3.5.
68	3.1.5-1	The Websphere monitor resource now supports WebSphere 8.0.
69	3.1.5-1	The load balancer link function for the JVM monitor resource now supports BIG-IP LTM.
70	3.1.5-1	The JVM monitor resource now supports WebOTX 8.5 (x86_64 only), WebOTX ESB 8.5, MasterScope/NEC Storage SVF for PDF 9.1, MasterScope/NEC Storage Report Director Enterprise 9.1, and MasterScope/NEC Storage Universal Connect/X 9.1.
71	3.1.5-1	The WebOTX monitor resource now supports WebOTX 8.5 (x86_64 only).
72	3.1.5-1	A command that can be used for capacity planning (clpprer) has been added. This command can estimate future values based on time-series data indicating system resource usage.
73	3.1.5-1	A function to collect system resource information that can be used to easily determine the cause of a failure resulting from a shortage of system resources has been added.
74	3.1.5-1	The stack size of applications started from the EXEC resources now matches the OS setting value.
75	3.1.7-1	The newly released kernel is now supported.
76	3.1.7-1	PostgreSQL monitor now supports PostgreSQL9.2.
77	3.1.8-1	The newly released kernel is now supported.
78	3.1.8-1	The log collection types have been added. (By default, the logs of Java Resource Agent and System Resource Agent are not collected.)
79	3.1.8-1	The operation at generation of group resource activation/deactivation stall has been made selectable.
80	3.1.8-1	The samba monitor resource now supports samba 4.0.
81	3.1.8-1	The Websphere monitor resource now supports WebSphere 8.5.
82	3.1.10-1	The newly released kernel is now supported.
83	3.1.10-1	The model of script of exec resource was changed.

---

84	3.1.10-1	The offline Builder now supports JRE7 update25.
85	3.1.10-1	The WebOTX monitor resource now supports WebOTX 9.1.
86	3.1.10-1	The JVM monitor resource now supports WebOTX 9.1.
87	3.2.0-1	The newly released kernel is now supported.

## Corrected information

Modification has been performed on the following minor versions.

Number	Version (in detail)	Upgraded section	Cause
1	3.0.1-1 /3.0.0-1	A problem that a cluster cannot start up with VM license has been fixed.	Error in the license management table
2	3.0.2-1 /3.0.0-1 to 3.0.1-1	The final action upon group resource or monitor resource failure was displayed as a final action upon cluster service failure for Builder, and a final action upon cluster daemon failure for WebManager.	The terms have not been unified among the functions.
3	3.0.2-1 /3.0.0-1 to 3.0.1-1	In Builder, an exclusive attribute could be specified from the virtual machine properties.	Specifying exclusive attributes from the properties was not prohibited. (In the case of the wizard, this has been prohibited.)
4	3.0.2-1 /3.0.0-1 to 3.0.1-1	In an environment where XenServer could not be used, the VM monitor abnormally terminated (core dump) when the XenServer VM monitor was set up.	A NULL pointer was issued in the VM monitor initialization.
5	3.0.2-1 /3.0.0-1 to 3.0.1-1	When using the <code>clprexec</code> command, <code>Unknown request</code> was output to <code>syslog</code> and the alert log.	Script execution and group failover were not taken into consideration for the process to create a character string output to <code>syslog</code> and the alert log.
6	3.0.2-1 /3.0.0-1 to 3.0.1-1	When changing the settings on the monitor resource properties dialog box, <b>Apply</b> could not be clicked.	There was no consideration for the decision process.
7	3.0.2-1 /3.0.0-1 to 3.0.1-1	On the Builder Interconnect Setting window, when attempting to delete interconnect settings by selecting all settings, only some settings were deleted.	There was no consideration for selecting multiple interconnects.
8	3.0.2-1 /3.0.0-1 to 3.0.1-1	The system abnormally terminated when the WebManager service was stopped.	The timing to release the Mutex resource, which was used by the realtime update thread, was not correct.
9	3.0.2-1 /3.0.0-1 to 3.0.1-1	The alert synchronization service abnormally terminated when restarting the server after changing its name.	There was an error in the process to obtain the server list.
10	3.0.2-1 /3.0.0-1 to 3.0.1-1	When a cluster name was changed in the Cluster Generation Wizard, the name was reset to a default name.	This occurred when returning to the cluster name change screen after the cluster name was changed in the Cluster Generation Wizard and the next step was selected.
11	3.0.2-1 /3.0.0-1 to 3.0.1-1	When a keyword over 256 characters was specified, linkage with external monitoring was not started even if the <code>mnw</code> monitor was set.	The size of the buffer to save the keyword was insufficient.
12	3.0.2-1 /3.0.0-1 to 3.0.1-1	When disabling shutdown monitoring, user space monitoring could not be started.	The check process of shutdown monitoring was executed by the initialization process of user space monitoring.

13	3.0.2-1 /3.0.0-1 to 3.0.1-1	The timeout for shutdown monitoring could not be changed.	The heartbeat timeout was specified to use at any time.
15	3.0.3-1 /3.0.0-1 to 3.0.2-1	In config mode, non-numeric data (alphabetic characters and symbols) could be incorrectly entered for <b>Wait Time When External Migration Occurs</b> for VM monitor resources.	There was an error in the design of the Builder input control.
16	3.0.3-1 /3.0.0-1 to 3.0.2-1	When "0" was specified as the timeout period for EXEC resources, the activation of EXEC resources failed and emergency shutdown was performed.	There was an error in the design of the Builder input control.
17	3.0.3-1 / 3.0.0-1 to 3.0.2-1	In Chinese environment, Starting Cluster Generation Wizard of the Builder caused an application error.	There was an illegal memory access in some cases.
18	3.0.3-1 /3.0.0-1 to 3.0.2-1	In a specific environment, pressing the <b>Add Server</b> button in the Cluster Generation Wizard of the Builder caused an application error.	The error was caused by a problem with JRE.
19	3.0.3-1 /3.0.0-1 to 3.0.2-1	The units of the time values to be displayed in the alert (syslog) for delay warning in the user space monitor resources were incorrect, and the values to be displayed in units of tick count were displayed in units of seconds.	The output conversion method was incorrect.
20	3.0.3-1 /3.0.0-1 to 3.0.2-1	When the size of an alert message exceeded 512 bytes, the alert daemon terminated abnormally.	The size of the alert message buffer was insufficient.
21	3.0.3-1 / 3.0.2-1	When selecting <b>Exit</b> in File menu of WebManager, WebManager did not terminate normally.	Processing of config mode termination was incorrect.
22	3.1.0-1 / 3.0.0-1~3.0.4-1	Uploading is unavailable if the cluster has been suspended and a temporary suspension of a monitored resource modified a necessary configuration	When checking processes while uploading, a cluster configuration file only judged whether the status of monitor resources was suspended.
23	3.1.0-1 / 3.0.0-1~3.0.4-1	When waiting to start monitoring a resident monitor resource, the timeout time rather than the start wait time is referenced.	The processing for the monitor start wait time was invalid.
24	3.1.0-1 / 3.0.0-1~3.0.4-1	An error occurred when collecting logs, delivering settings information, or during other activities, but the process appears to have terminated normally.	There were faults in the processing that determines whether the action was successful or nor.
25	3.1.0-1 / 3.0.0-1~3.0.4-1	When the IP address for integrated WebManager was not specified, error messages output due to failures to connect to clusters were invalid.	The names of previous setting items were not updated.
26	3.1.0-1 / 3.0.0-1~3.0.4-1	Sometimes core dump occurred while stopping a cluster service when max reboot count limitation was set.	Illegal memory access occurred when a log was output after log library termination processing during termination processing.
27	3.1.0-1 / 3.0.0-1~3.0.4-1	A minor memory leak occurred when performing a group or resource operation.	Thread information was not discarded after the thread terminated.
28	3.1.0-1 / 3.0.0-1~3.0.4-1	When a script execution process times out before the final operation runs and is force killed, sometimes a zombie process was generated.	Sometimes waitpid() was executed before a process was terminated by SIGKILL.

29	3.1.0-1 / 3.0.0-1~3.0.4-1	Recovery action counts were not reset by the clpmonctrl command when the monitor error recovery action was fully executed.	Shared memory values were reset, but values saved in the memory of monitor resource processes are not reset.
30	3.1.0-1 / 3.0.0-1~3.0.4-1	The name of a server cannot be fully displayed in the list of available servers in the server tab of group properties.	A horizontal scroll bar was not displayed.
31	3.1.0-1 / 3.0.0-1~3.0.4-1	When stopping a monitor resource which is being continuously monitored, Application Server Agent sometimes terminated other processes when it was stopped.	There was a flaw in the processing that terminates the child processes of the Application Server Agent.
32	3.1.0-1 / 3.0.0-1~3.0.4-1	Monitor status changed to a status other than "suspend" after suspending the monitor resource.	Sometimes the status was overwritten after it was set to suspend.
33	3.1.0-1 / 3.0.0-1~3.0.4-1	When a monitor resource is suspended, it sometimes remained as a zombie process.	Depending on timing, waitpid() was not executed when child processes were terminated.
34	3.1.0-1 / 3.0.0-1~3.0.4-1	When using diverse resources or monitors, if the number of ExpressCluster module types that output logs exceeds 128, sometimes internal logs are not output.	The initialized area that manages the types is only for use with 128 types.
35	3.1.0-1 / 3.0.0-1~3.0.4-1	MA memory leak occurred when suspending a cluster failed because a group was moving.	Internal information was not discarded at the time of the failure to suspend the cluster.
36	3.1.0-1 / 3.0.0-1~3.0.4-1	A memory leak occurred when stopping a cluster failed because a group was moving.	Internal information was not discarded at the time of the failure to stop the cluster.
37	3.1.0-1 / 3.0.0-1~3.0.4-1	Child processes remained when a genw monitor timeout occurred while the enw settings were set to synchronous and the dump collection function was enabled..	The custom monitor terminated before the child process.
38	3.1.0-1 / 3.0.0-1~3.0.4-1	When the host name was FQDN, requests from the clprexec command failed.	If the host name which was obtained from the OS was FQDN, the server cannot find items from a cluster configuration file.
39	3.1.0-1 / 3.0.0-1~3.0.4-1	If there are many objects will be displayed on WebManager, WebManager server process may be terminated abnormally.	There was a problem in the source code to allocate memory to display objects.
40	3.1.1-1 / 3.0.0-1 to 3.1.0-1	If initializing XenServer virtual machine resources failed in an environment where XenServer could not be used, WebManager server process might be terminated abnormally.	Environments where XenServer could not be used were not considered.
41	3.1.1-1 / 3.0.0-1 to 3.1.0-1	If initializing XenServer virtual machine monitor resources failed in an environment where XenServer could not be used, WebManager server process might be terminated abnormally.	Environments where XenServer could not be used were not considered.
42	3.1.1-1 / 3.0.0-1 to 3.1.0-1	After collecting logs, some OS resources of the log collection function might remain.	After initializing threads is complete, if the process to wait for the initialization completion is executed on the parent thread, the command waits for the

			initialization completion endlessly.
43	3.1.1-1 / 3.0.0-1 to 3.1.0-1	After collecting logs, the files that must be deleted might remain.	For SuSE Linux, the tar command options were not considered.
44	3.1.1-1 / 3.0.0-1 to 3.1.0-1	If the VM license is used, an unnecessary alert might be output when starting the cluster.	The message that was not necessary to output when using the VM license has been output.
45	3.1.1-1 / 3.0.0-1 to 3.1.0-1	If the configuration data is uploaded with clearing the default resource dependency and without specifying any dependencies, only the cluster suspend is requested even if it is necessary to stop a group.	The file that defines the method to reflect changes is inadequate.
46	3.1.1-1 / 3.0.0-1 to 3.1.0-1	WebManager might abnormally terminate if there is a lot of information to be displayed for WebManager because there are a lot of servers.	Since the size of the temporary buffer is fixed to 4096 bytes, an illegal memory access occurs if there is information exceeding 4096 bytes.
47	3.1.1-1 / 3.1.0-1	The description (in English) of rc message ID=26 was not correct.	In the current description, “has started” was used, but, “has been completed” is correct.
48	3.1.1-1 / 3.1.0-1	The correct method to reflect the added group resource is “stopping/suspending the group”, but “stopping the cluster” was performed.	The file that defines the method to reflect changes was inadequate.
49	3.1.1-1 / 3.1.0-1	If the Oracle monitor resource is selected, WebManager can not display information.	Internal information file of Oracle monitor resource was not correct.
50	3.1.1-1 / 3.0.0-1 to 3.1.0-1	The file descriptor used by the clprc process might leak if WebManager was frequently updated or clpstat was frequently executed.	The process to close the file descriptor might not be performed.
51	3.1.1-1 / 3.1.0-1	A monitor resource name was not correctly output in the alert of rm ID=170 or 171.	The process to output ID=170 and 171 was not correct.
52	3.1.1-1 / 3.0.0-1 to 3.1.0-1	If an error was detected when multiple resources were being activated, the final action was performed for the abnormal resource that was found at first in the alphabetical order. Therefore, if the resource to which <b>No Operation</b> was set, the operation such as shutdown was not performed.	Only the final action for the abnormal resource that was found at first was performed.
53	3.1.1-1 / 3.1.0-1	Multiple confirmation dialog boxes might be displayed when continuously pressing the operation button in WebManager Mobile.	An exclusive processing when pressing the operation button was inadequate.
54	3.1.1-1 / 3.1.0-1	The ulimit setting of the default script was deleted in WebManager config mode.	The default script was not correct in config mode.
55	3.1.1-1 / 3.0.0-1 to 3.1.0-1	When deleting a virtual machine resource, a related virtual machine resource could not be deleted automatically.	The delete condition decision process of the automatic monitor resource delete process was inadequate.
56	3.1.1-1	When linkage with a server management infrastructure was available, the status	The process to update the message receive monitor status was inadequate.

	/ 3.0.0-1 to 3.1.0-1	might remain OFFLINE if monitoring the message receive monitor was started before starting the infrastructure module.	
57	3.1.1-1 / 3.0.3-1 to 3.1.0-1	The NFS monitor resource could not detect that only nfsd was disappeared.	It was determined normal that the unmount process was normally performed.
58	3.1.1-1 / 3.0.3-1 to 3.1.0-1	If multiple targets were registered to a JVM monitor resource, monitoring might fail and a warning might be issued when starting to monitor the JVM monitor resource.	Java API was not thread-safe.
59	3.1.1-1 / 3.1.0-1	If a process of which name length was 1024 bytes or more existed, a process name monitor resource might abnormally terminate.	An environment that included a process of which name length was 1024 bytes or more was not considered.
60	3.1.1-1 / 3.1.0-1	If the monitoring level is level 2 and no records were created at creation of a table for monitoring, the PostgreSQL monitor resource might abnormally terminate.	The action to be taken when there is no record when reading data from a database by select during level 2 monitoring was not defined.
61	3.1.1-1 / 3.1.0-1	When Database Agent detected a timeout, monitoring was immediately retried without waiting for the monitoring interval.	The retry process after a monitoring timeout was not considered.
62	3.1.0-1/ 3.0.0-1 to 3.0.4-1	It might fail to start a specific monitor resource for the first time, causing a monitor error. In a specific machine environment, this might occur for message receive monitor resource resource.	There was a variable that had not been initialized.
63	3.1.3-1/ 3.1.0-1 to 3.1.1-1	When the cluster was resumed from WebManager, <b>Failed to resume</b> was mistakenly displayed instead of <b>The request to resume the cluster failed on some servers</b> . This occurred when the cluster was forcibly suspended and then resumed with some servers stopped.	The message text was not correct.
64	3.1.3-1/ 3.0.0-1 to 3.1.1-1	After the ExpressCluster Web Alert service might abnormally terminate, this service might start. When the ExpressCluster Web Alert service was killed for some reason, this infrequently occurred at the next service startup. Also, this might infrequently occur in normal operation.	The buffer area used to read /proc/pid/cmdline was insufficient, or strerr(), which was not thread-safe, was sometimes used by multiple threads.
65	3.1.3-1/ 3.0.0-1 to 3.1.1-1	In SuSE11 environments, an internal log was not output when UDP was set to a log communication method. This occurred when UDP was set to a log communication method in SuSE11 environments.	The method to create a socket was inadequate.
66	3.1.3-1/ 3.1.1-1	In an environment where a specific monitor resource existed, suspending and resuming the monitor resource might fail. This might occur in an environment that included any of the following monitor	The monitor resource name save area was not initialized.

		resources: - User mode monitor resource - Message receive monitor resource - Virtual machine monitor resource	
67	3.1.3-1/ 3.0.0-1 to 3.1.1-1	Executing a script by the clprexec command might fail. This occurred when a script to be executed by the clprexec command was stored in the path described in the guide.	The path to store a clptrnreq command script was used.
68	3.1.3-1/ 3.0.0-1 to 3.1.1-1	It took extra five seconds to perform a final retry upon a group resource activation/deactivation error. This occurred upon a group resource activation/deactivation error when it was set to retry activate or deactivate the group resource.	A final retry entered in unnecessary sleep state (five seconds) when an activation or deactivation retry was performed upon a group resource activation/deactivation error.
69	3.1.3-1/ 3.0.0-1 to 3.1.1-1	A message receive monitor error might be detected when the cluster was being stopped. This might occur when a message receive monitor was monitored when the cluster was being stopped.	A monitor process was not generated when the cluster was being stopped, and the stopping process was always assumed to be completed successfully. In such a case, it was checked whether a monitor process existed or not.
70	3.1.3-1/ 3.0.2-1 to 3.1.1-1	When collecting logs, a rotated syslog file might not be collected. This occurred when logs were collected in RHEL6 or later environments.	The name of the rotated messages file did not comply with the changed naming rule.
71	3.1.3-1/ 3.0.0-1 to 3.1.1-1	Stopping the cluster might not be completed. This might infrequently occur when a message receive monitor resource was set.	A termination process was missing in the process to check a thread termination request.
72	3.1.3-1/ 3.1.0-1 to 3.1.1-1	33 or more destinations to which a SNMP trap was sent could be set. This occurred when the SNMP trap sending destination settings screen was started again after 32 destinations had been set.	The control processing of the <b>Add</b> button on the SNMP trap sending destination settings screen was inadequate.
73	3.1.3-1/ 3.0.0-1 to 3.1.1-1	When <b>READ</b> was selected as <b>Method</b> to monitor a disk resource, <b>I/O Size</b> might return to the default value. This occurred when <b>Method</b> was changed from <b>READ</b> to <b>TUR</b> , and then returned to <b>READ</b> .	A process to store the value specified for <b>I/O Size</b> was missing when changing <b>Method</b> .
74	3.1.3-1/ 3.0.0-1 to 3.1.1-1	A monitor resource might mistakenly detect an error when uploading the configuration data. This occurred on very rare occasions when uploading the configuration data.	Reading the configuration data file failed if a monitor resource tried to refer to the configuration data when the file was being replaced.
75	3.1.3-1/ 3.0.0-1 to 3.1.1-1	An FTP monitor resource might mistakenly detect a monitoring timeout. This occurred when an FTP server returned an intermediate response and final response together.	The process to be performed when an intermediate response and final response were returned together was not correct.
76	3.1.3-1/ 3.0.0-1 to 3.1.1-1	When a monitoring timeout occurred in a PostgreSQL monitor resource, the next monitoring might fail because a PostgreSQL session remained.	The process to cancel monitoring a PostgreSQL monitor resource when a timeout occurred was inadequate.

		This occurred when a monitoring timeout occurred and the specified timeout interval was short.	
77	3.1.3-1/ 3.0.0-1 to 3.1.1-1	It might take 10 seconds or more to display the execution results of the clpstat command. This occurred on very rare occasions when executing the clpstat command.	Waiting for the completion of the thread initialization might fail depending on the timing, and the clpstat command might wait for a timeout.
78	3.1.4-1/ 3.1.3-1	The time information icon might not blink on WebManager even when the time information was updated. This occurred when a server was stopped and started after WebManager connection.	It was determined that the server had not been connected before when it was started.
79	3.1.4-1/ 3.0.0-1 to 3.1.3-1	Restart of the alert synchronization service might occur. This occurred on very rare occasions during normal operation.	A system call, which was not thread-safe, was sometimes used by multiple threads.
80	3.1.4-1/ 3.0.0-1 to 3.1.3-1	Information on WebManager, clpstat command, SNMP manager linkage, etc., could fail to display. This occurred when internal communication timed out for some reason such as interconnect disconnection or overload, after which control returned to the state existing before interconnect switchover.	Information acquisition requests between servers were made in an irregular order.
81	3.1.4-1/ 3.0.0-1 to 3.1.3-1	The clplogcf command execution results may not be displayed. This occurred when the event service updated a temporary file for storing display information upon execution of the clplogcf command.	When the event service updated the file of display information, it emptied the file once for writing.
82	3.1.4-1/ 3.1.0-1 to 3.1.3-1	When the clpstat command was used to display property information for a disk monitor resource, "Disk full Action" was not displayed. This occurred when the following command was executed: clpstat --mon disk_monitor_name --detail	There was an error in the parameter display settings.
83	3.1.4-1/ 3.0.0-1 to 3.1.3-1	Stopping a monitor resource sometimes caused other processes to be killed. This might occur when stopping a monitor resource if the pid of a monitor resource managed by ExpressCluster is used for other processes.	Whether the process was alive, and the process name, were not checked before SIGKILL was issued.
84	3.1.4-1/ 3.0.0-1 to 3.1.3-1	The configuration information may not be reflected. This might occur when the OS language setting was other than Japanese, English, or Chinese.	The setting of environment variable LANG was missing when obtaining system information.
85	3.1.4-1/ 3.0.0-1 to 3.1.3-1	The user mode monitor resource might mistakenly detect a delay warning. In a 32-bit OS environment, this might occur when the OS was running for 198 or more consecutive days with the user	Difference calculation was performed on the number of clock ticks using a sign.

		mode monitor resources set up.	
86	3.1.4-1/ 3.1.3-1	Some monitor resources might mistakenly detect monitor errors. In a 32-bit OS environment, this might occur when the OS was running for 198 or more consecutive days with any of the following monitor resources set up. [Relevant monitor resources] - db2w - ddns - genw - jraw - mysqlw - oraclew - psqw - psw - srw - sybasew - vipw	Difference calculation was performed on the number of clock ticks using a sign.
87	3.1.4-1/ 3.1.0-1 to 3.1.3-1	The process name monitor resource might end abnormally. This might occur when the cluster was suspended/stopped in an environment in which the process name monitor resource was set up.	The reception of a suspension/stop request was not properly handled in the internal operation.
88	3.1.4-1/ 3.0.0-1 to 3.1.3-1	Monitoring by the HTTP monitor resource might fail. This occurred in an environment in which renegotiate was requested upon reception via SSL due to monitoring on https.	The HTTP monitor resource did not properly deal with a renegotiate request.
89	3.1.4-1/ 3.1.1-1 to 3.1.3-1	Some core files might not be collected during log collection. This might occur when multiple core files existed during log collection.	When compressing log files, the first core file was compressed, but the subsequent core files were deleted.
90	3.1.5-1/ 3.0.0-1 to 3.1.4-1	The clpmonctrl command displays the recovery action execution count in an invalid order. This problem always occurs when you execute clpmonctrl -v.	The restart count and the failover count are displayed in the reverse order.
91	3.1.5-1/ 3.1.0-1 to 3.1.4-1	The comment field will be blank when you click Get License Info on the resource addition wizard in Config Mode in WebManager. This problem always occurs when you click the Get License Info button.	The entry field was not properly initialized after Get License Info was executed.
92	3.1.5-1/ 3.1.0-1 to 3.1.4-1	When you click the Get License Info button in the monitor addition wizard in Config Mode in WebManager, the initial value is not set to the Name field. This problem always occurs when you click the Get License Info button.	The entry field was not properly initialized after Get License Info was executed.
93	3.1.5-1/ 3.0.0-1 to 3.1.4-1	Monitor resources may be created more than the upper limit in the setup mode in WebManager. This problem occurs if you add resources that trigger the automatic addition of monitor resources when the upper limit of	The automatic monitor resource addition process did not include an upper limit check.

		monitor resources has been reached.	
94	3.1.5-1/ 3.0.0-1 to 3.1.4-1	An application error may occur causing an emergency shutdown in the group resource management process. This problem occurs if internal communication is established when the maximum number of file descriptors that can be used in the OS is exceeded.	When the maximum number of file descriptors that can be used in the OS is exceeded, the currently used socket is improperly operated.
95	3.1.5-1/ 3.1.0-1 to 3.1.4-1	exec resources may fail to activate. This problem may occur if you simultaneously execute multiple exec resources for which the setting to rotate logs has been specified and it is the first startup for the server.	If directory creation processes for temporary files are executed at the same time, the directory creation process started later fails.
96	3.1.5-1/ 3.0.0-1 to 3.1.4-1	For some monitor resources, an abnormal alert may be continuously logged at each interval. This problem occurs when an initialization error (such as an invalid library path) occurs in the following monitor resources. Relevant monitor resources - db2w - ddns - genw - jraw - mysqlw - oraclew - psqw - psw - sraw - sybasew - vipw	A setting to log an alert every time an initialization error occurs had been specified.
97	3.1.5-1/ 3.0.0-1 to 3.1.4-1	The FTP monitor resource may mistakenly detect a monitor error. This problem occurs if the banner message registered in the FTP server or the message at the time of connection is a long character string or spans multiple lines.	The FTP monitor executes the next command before receiving all responses from the FTP server.
98	3.1.5-1/ 3.1.0-1 to 3.1.4-1	An unnecessary message about a System Resource Agent background process may be output in when a cluster stops. This problem occurs if the cluster stops in an environment in which System Resource Agent is used.	A case in which resources are released in a multi-thread process was not taken into consideration.
99	3.1.5-1/ 3.0.0-1 to 3.1.4-1	The mail report function might fail to send a mail. This problem occurs when a domain name is not included in the greeting message of the destination SMTP server.	The domain name of the greeting message returned by the SMTP server is used as the domain of the HELO or EHLO command.
100	3.1.7-1/ 3.0.0-1 to 3.1.6-1	When the configuration information is uploaded using the clpcfcctl command, an OS memory shortage error might occur although this is not the case.	This occurred when the configuration information including interconnect settings having IPs not existing on the sever is uploaded.
101	3.1.7-1/	The result of virtual machine resource activation processing was reflected on the	This occurred while virtual machine resources were used.

	3.0.0-1 to 3.1.6-1	environment variable CLP_DISK to be used for EXEC resources.	
102	3.1.7-1/ 3.1.5-1 to 3.1.6-1	Sometimes recovery action upon monitor error could not be executed.	This occurred when recovery action by another monitor resource on the same server was tried for the group and resource for which group stop had been executed as the final action upon monitor error.
103	3.1.7-1/ 3.0.0-1 to 3.1.6-1	In executing the clplogcc command, a log file might not be saved in a directory specified by the -o option.	This occurred when a directory in a file system other than the ExpressCluster installation path was specified by the -o option in executing clplogcc -l.
104	3.1.7-1/ 3.0.0-1 to 3.1.6-1	In Config Mode of the WebManager, Executing failover could be selected on the recovery action setting in message receive monitor resource properties.	This occurred when message receive monitor resources were used.
105	3.1.7-1/ 3.0.0-1 to 3.1.6-1	In Config Mode of the WebManager, the final action setting might be changed at an unintended timing.	This occurred when the recovery target was changed on the recovery action tab of monitor resource properties.
106	3.1.7-1/ 3.0.0-1 to 3.1.6-1	The same monitor resource might be started redundantly, resulting in unnecessary recovery action being executed.	This occurred on very rare occasions when a monitor resource set to Always monitors and a monitor resource set to Monitors while activated were started simultaneously when the cluster started.
107	3.1.7-1/ 3.1.5-1	The following alerts might be output to the WebManager.  TYPE:rm, ID:9 Detected an error in monitoring <monitor_resource_name>. (<error_number> :<error_message>  TYPE:rm, ID:25 Recovery will not be executed since the recovery target <group_name_or_group_resource_name> is not active.	This occurred when it took time to stop a failover group in stopping the cluster.
108	3.1.7-1/ 3.0.0-1 to 3.1.6-1	The following alert might not be output to the WebManager.  TYPE:rm, ID:100 Restart count exceeded the maximum of <count>. Final action of monitoring <monitor_resource_name> will not be executed.	This occurred when the monitor resource returned to normal once after the alert was output, and upon detecting an error again within 24 hours, and the final action was ignored.
109	3.1.7-1/ 3.0.3-1 to 3.1.6-1	In Config Mode of the WebManager, Nursery Space and Old Space might not become monitor targets when a JVM monitor resource is created.	This occurred when a new JVM monitor resource was created by selecting Oracle JRockit for JVM Type and not opening Tuning Properties.
110	3.1.7-1/ 3.0.0-1 to 3.1.6-1	In Config Mode of the WebManager, executing Apply the Configuration File caused a memory leak to occur in the WebManager server process. A leak of 80 + 256 * number of monitor types in use + 256 * number of monitor resources occurred per execution.	This occurred when Apply the Configuration File was executed.

111	3.1.7-1/ 3.0.0-1 to 3.1.6-1	When an IP address or the like is changed in Server Properties - BMC Tab in Config Mode of the WebManager, the execution of Suspend and Resume might not apply the change.	This occurred when the Chassis Identify function was used.
112	3.1.7-1/ 3.1.3-1 to 3.1.6-1	There might be a delay in executing recovery action upon detection of a monitoring error.	This occurred when the time information display function was enabled and a monitor resource detected an error at disconnection of the primary interconnect.
113	3.1.7-1/ 3.0.0-1 to 3.1.6-1	A VMW monitor resource might make erroneous detection of an error.	This occurred when the monitor interval of the VMW monitor resource was set to 15 seconds or more.
114	3.1.8-1/ 3.1.0-1 to 3.1.7-1	The WebManager service process may terminate abnormally.	This problem may occur when an invalid packet has been received.
115	3.1.8-1/ 3.1.7-1	Only part of an alert message or syslog may be output.	This problem occurs when the alert notification setting for customizing the alert destination has been enabled.
116	3.1.8-1/ 3.1.0-1 to 3.1.7-1	A monitor timeout may be mistakenly detected for the process name monitor resource.	This problem may occur when the configured monitor interval is equal to or greater than the monitor timeout.
117	3.1.8-1/ 3.1.0-1 to 3.1.7-1	When the activation monitor resource stops with group stop, it may stop temporarily.	This problem may occur when monitor by the clpmonctrl command has been temporarily stopped during group stop processing.
118	3.1.8-1/ 3.1.7-1	Deactivation of a virtual machine resource may fail.	This problem occurs when UUID is set for the virtual machine resource (XenServer).
119	3.1.10-1/ 3.0.0-1 to 3.1.8-1	An invalid error message may be displayed when the clprsc command is executed. 「Internal error. Check if memory or OS resources are sufficient」	This failure occurs if a resource stop is executed with the clprsc command but stopping of the resource fails.
120	3.1.10-1/ 3.0.0-1 to 3.1.8-1	The clpcfctrl command may terminate abnormally.	A core dump is performed if a timeout occurs in the internal processing of the clpcfctrl command.
121	3.1.10-1/ 3.1.0-1 to 3.1.8-1	A log may not be output if the exec resource log output function is set.	This failure occurs if the log file name exceeds 32 bytes.
122	3.1.10-1/ 3.1.0-1 to 3.1.8-1	When the browser connected to WebManager is to be terminated, a security warning dialog box may be displayed.	This failure always occurs when the browser connected to WebManager is to be terminated in an environment in which the JRE version is JRE7 update 21 or later.
123	3.2.0-1/ 3.1.5-1to3.1.10-1	A file of 0byte as wlst_xxxx.log and wlst_xxxx.out is output by a [Middleware_Home] /logs follower every interval in a WebLogic monitor resource.	WebLogic monitor resource is executes WLST every interval and is executes a watch of life and death of WebLogic Server. WebLogic Server Because it started to output a logfile every WLST execution by a change of

			specifications after 10.3.4.
124	3.2.0-1/ 3.1.3-1to3.1.10-1	In a monitor resource of database, when a monitoring timeout occurred, recovery action will be carried out. A monitoring error occur independently of the retry number of times.	After a monitoring timeout occurred, a renewal of inside information is leaking by processing before a performed watch retry, because a resource monitor process judged the state of the watch resource to be abnormal.



# Chapter 5 Additional information

This chapter provides tips on installing ExpressCluster X SingleServerSafe.

This chapter covers:

- ExpressCluster X SingleServerSafe services ..... 96
- Migration from the trial license to the official license ..... 97

## ExpressCluster X SingleServerSafe services

ExpressCluster X SingleServerSafe consists of the system services listed below.

System Service Name	Explanation
clusterpro	ExpressCluster daemon: Main ExpressCluster service
clusterpro_evt	ExpressCluster event: Service for controlling <code>syslog</code> and logs output by ExpressCluster
clusterpro_trn	ExpressCluster data transfer: Service for controlling license synchronization and configuration data transfers
clusterpro_alertsync	ExpressCluster alert synchronization: Service for alert synchronization
clusterpro_webmgr	ExpressCluster WebManager: WebManager service

## Migration from the trial license to the official license

When registering the official license to a server running with the trial license, you can add the official license without deleting the trial license. When you list the registered licenses, both the official and trial licenses are shown, but there is no problem.

For details about adding a license, see Chapter 2, “Installing ExpressCluster X SingleServerSafe” in this guide.



# Chapter 6 Notes and Restrictions

This chapter provides information on known problems and how to troubleshoot the problems.

This chapter covers:

- Before and at the time of installing operating system ..... 100
- Before installing ExpressCluster ..... 101

## Before and at the time of installing operating system

Notes on parameters to be determined when installing an operating system, allocating resources, and naming rules are described in this section.

### `/opt/nec/clusterpro` file system

It is recommended to use a file system that is capable of journaling to avoid system failure.

### Dependent library

`libxml2`

Install `libxml2` when installing the operating system.

### Dependent driver

`softdog`

- ◆ This driver is necessary when `softdog` is used to monitor user mode monitor resource.
- ◆ Configure a loadable module. Static driver cannot be used.

### SELinux settings

- ◆ Configure **permissive** or **disabled** for the SELinux settings.
- ◆ If you set `enforcing`, communication required in ExpressCluster may not be achieved.

### ExpressCluster X Alert Service

The license for the ExpressCluster X Alert Service allows you to use the mail report function, but not the warning light function.

## Before installing ExpressCluster

Notes after installing an operating system, when configuring OS and disks are described in this section.

### Communication port number

ExpressCluster X SingleServerSafe employs the following port numbers by default. You can change the port number by using the Builder.

Do not allow other programs to access any port with the following port numbers.

Configure to be able to access the port number below when setting a firewall on a server.

#### Server

From			To		Remarks
Server	Automatic allocation <sup>1</sup>	-	Server	29001/TCP	Internal communication
Server	Automatic allocation	-	Server	29002/TCP	Data transfer
Server	Automatic allocation	-	Server	29002/UDP	Heartbeat
Server	Automatic allocation	-	Server	29003/UDP	Alert synchronization
Server	Automatic allocation	-	Server	XXXX <sup>5</sup> /UDP	Internal communication for log

#### Server – WebManager

From			To		Remarks
WebManager	Automatic allocation	-	Server	29003/TCP	http communication

#### Integrated WebManager connected server - Server to be managed

					Remarks
Integrated WebManager connected server	Automatic allocation	-	Server	29003/TCP	http communication

#### Others

From			To		Remarks
Server	snmp trap	→	Monitoring target	162/UDP	Monitoring target of the external linkage monitor configured for BMC linkage
Server	icmp	→	Monitoring target	icmp	IP monitor
Server	Management port number set by the Builder	-	Monitoring target	-	JVM monitor
Server	Connection port number	-	Monitoring target	-	JVM monitor

	set by the Builder		
Server	Load balancer linkage management port number set by the Builder	Monitoring target	JVM monitor

1. An available port number at the time is automatically assigned.
2. In the **Port Number** (log) tab in **Cluster Properties**, select **UDP** for log communication, and use the port number configured at **Port Number**. The default log communication method, **UNIX Domain**, does not use a communication port.

## Changing the range of automatic allocation for the communication port numbers

- ◆ The range of automatic allocation for the communication port numbers managed by the OS might overlap the communication port numbers used by ExpressCluster.
- ◆ Change the OS settings to avoid duplication when the range of automatic allocation for the communication numbers managed by OS and the communication numbers used by ExpressCluster are duplicated.

Examples of checking and displaying OS setting conditions.

The range of automatic allocation for the communication port numbers depends on the distribution.

```
# cat /proc/sys/net/ipv4/ip_local_port_range
1024 65000
```

This is the condition to be assigned for the range from 1024 to 65000 when the application requests automatic allocation for the communication port numbers to the OS.

```
# cat /proc/sys/net/ipv4/ip_local_port_range
32768 61000
```

This is the condition to be assigned for the range from 32768 to 61000 when the application requests automatic allocation for the communication port numbers to the OS.

Examples of OS settings change

Add the line below to `/etc/sysctl.conf`. (When changing to the range from 30000 to 65000)

```
net.ipv4.ip_local_port_range = 30000 65000
```

## Checking the network settings

- ◆ Check the network settings by using the `ifconfig` and `ping` commands.
  - Public LAN (used for communication with all the other machines)
  - Host name

## Ipmitool and OpenIPMI

- ◆ The following functions use ipmitool or OpenIPMI:
  - Final Action at Activation Failure / Deactivation Failure
  - Monitor resource action upon failure
  - User mode monitor resource
  - Shutdown monitoring
- ◆ When the monitor method is ipmi, ipmitool or OpenIPMI is used.
- ◆ ExpressCluster X SingleServerSafe does not come with ipmitool. The user is required to install the rpm file for ipmitool or OpenIPMI separately.
- ◆ We do not handle ipmitool or OpenIPMI matters. NEC does not support or assume any responsibilities for:
  - Inquiries about ipmitool or OpenIPMI
  - Guarantee of the operation of ipmitool or OpenIPMI
  - Errors of or failures caused by ipmitool or OpenIPMI
  - Inquiries about whether ipmitool or OpenIPMI is supported by servers
- ◆ Check whether your servers (hardware) support ipmitool or OpenIPMI in advance.
- ◆ Note that hardware conforming to the IPMI specifications might not be able to run ipmitool or OpenIPMI.
- ◆ When server monitoring software provided by another server vendor is used, do not select IPMI for the monitoring method of user-mode monitor resources and shutdown monitoring. Such server monitoring software and ipmitool both use BMC (Baseboard Management Controller) on the server, which causes a conflict and makes monitoring impossible.

## User-mode monitor resources (softdog monitoring method)

- ◆ When softdog is set up as the monitoring method, disable the heartbeat function of the operating system.
- ◆ For SUSE LINUX 10/11, the softdog monitoring method cannot be set up when the `i8xx_tco` driver is in use. If you do not intend to use the `i8xx_tco` driver, set up the system so that the driver is not loaded.

## Collecting logs

- ◆ For SUSE LINUX 10/11, when the log collection function of ExpressCluster is used for OS syslog acquisition, the suffixes of syslog (message) files are rotated and changed, so the function for specifying syslog generation does not operate.  
To make the syslog generation specifiable for the log collection function, change the syslog rotation setting as described below.
  - Comment out compress and dateext in the /etc/logrotate.d/syslog file

## nsupdate and nslookup

- ◆ The following functions use nsupdate and nslookup.
  - Dynamic DNS monitor resource of monitor resource (ddns)
- ◆ ExpressCluster does not include nsupdate and nslookup. Therefore, install the rpm files of nsupdate and nslookup, in addition to the ExpressCluster installation.
- ◆ NEC does not support the items below regarding nsupdate and nslookup. Use nsupdate and nslookup at your own risk.
  - Inquiries about nsupdate and nslookup
  - Guaranteed operations of nsupdate and nslookup
  - Malfunction of nsupdate or nslookup or failure caused by such a malfunction
  - Inquiries about support of nsupdate and nslookup on each server

## FTP monitor resources

- ◆ If a banner message to be registered to the FTP server or a message to be displayed at connection is long or consists of multiple lines, a monitor error may occur. When monitoring by the FTP monitor resource, do not register a banner message or connection message.

# Appendix A Troubleshooting

## Error messages when installing the ExpressCluster X SingleServerSafe

	Error Message	Cause	Solution
1	failed to open //var/lib/rpm/packages.rpm error: cannot open //var/lib/rpm/packages.rpm	The user logged on is not a root user.	Log on as a root user.
2	error: package expressclssss-* is already installed	The ExpressCluster X SingleServerSafe is already installed.	Uninstall the ExpressCluster X SingleServerSafe and reinstall it.

## Error messages when uninstalling the ExpressCluster X SingleServerSafe

	Error Message	Cause	Solution
1	failed to open //var/lib/rpm/packages.rpm error: cannot open //var/lib/rpm/packages.rpm	The user logged on is not a root user.	Log on as a root user.
2	error: expressclssss is running	The ExpressCluster X SingleServerSafe is active.	Disable services by using the <code>chkconfig</code> command, restart the server, and uninstall the ExpressCluster SingleServerSafe again.

## Troubleshooting for licensing

Behavior and Message	Cause	Solution
<p>When the command was executed, the following message appeared in the console:</p> <pre>Log in as root.</pre>	The command was executed by a general user.	Log on as root user or log on again after changing to root user with <code>su -</code> .
<p>When the command was executed at the license registration, the following message appeared in the console:</p> <pre>Command succeeded. But the license was not applied to all the servers in the cluster because there are one or more servers that are not started up.</pre>	The data transfer service might not be running or the configuration data might not have been distributed.	Double check whether the transaction server is running and the configuration data has been distributed. If either of them is not done yet, complete the task and register the license again.
<p>When the configuration data created by the Builder was distributed to all servers and then the server was shut down and rebooted, the WebManager showed the following message on the alert view and the server stopped:</p> <pre>The license is not registered. (%1)  %1: Product ID</pre>	The server was shut down and rebooted without registering a license.	Register the license from the server.
<p>After the configuration data created by the Builder was distributed to all servers and the server is shut down and rebooted, the Web Manager showed the following message on the alert view but the server is operating normally:</p> <pre>The license is insufficient. The number of insufficient is %1. (%2)  %1: The number of licenses in short of supply  %2: Product ID</pre>	Licenses are insufficient.	Obtain a license and register it.
<p>While the servers were operated using the trial license, the following message was displayed and the servers stopped:</p> <pre>The license of trial expired by %1. (%2)  %1: Trial end date %2: Product ID</pre>	The license has already expired.	Ask your sales agent for extension of the trial version license, or obtain and register the product version license.

# Appendix B Index

## A

applications supported, 33

## C

Canceling the SNMP linkage function settings, 71  
Checking system requirements for each ExpressCluster module, 16  
Collecting logs, 104  
Communication port number, 101  
Corrected information, 82

## D

Dependent driver, 100  
Dependent library, 100  
distribution, 22

## E

ExpressCluster, vii, 13, 14, 46  
ExpressCluster X Alert Service, 100  
ExpressCluster X SingleServerSafe services, 96

## F

file system, 100  
function enhancement, 76, 77, 78

## H

Hardware, 16

## I

installation, 47, 62, 65, 66  
Installing ExpressCluster X SingleServerSafe, 46, 62  
Installing the ExpressCluster X SingleServerSafe, 47  
Installing the ExpressCluster X SingleServerSafe, 47  
Installing the offline version of the ExpressCluster Builder, 62, 66  
Installing the online version of the ExpressCluster Builder, 65

## K

kernel, 22

## N

Network, 103

nslookup, 104  
nsupdate, 104

## R

Registering the CPU license, 50  
Registering the license, 50  
Registering the license by specifying the license file, 50, 51, 58, 59  
Registering the license interactively from the command line, 50, 52  
Registering the node license, 58  
Registering the node license interactively from the command line, 58, 60  
Registering the VM node license, 54  
reinstallation, 72  
Reinstalling the ExpressCluster X SingleServerSafe, 72  
Required specifications, 16

## S

SELinux settings, 100  
Servers supporting BMC-related functions, 16  
setting after hardware configuration, 41  
Setting up the SNMP linkage function, 48  
software configuration, 15  
Starting the Builder, 65  
system requirements, 16

## T

Troubleshooting, 105

## U

uninstallation, 70  
Uninstalling the Builder, 70  
Uninstalling the ExpressCluster X SingleServerSafe, 70  
Updating ExpressCluster X SingleServerSafe, 68  
Updating the ExpressCluster X SingleServerSafe RPM, 68  
Upgrading to ExpressCluster X, 73  
user-mode monitor resource, 103

## V

Verifying of the firewall settings, 42  
Verifying the network settings, 41  
Verifying the root file system, 41