# ExpressCluster® X 2.1 for Windows

Reference Guide

09/30/2009
Second Edition

EXPRESSCLUSTER

X

#### **Revision History**

Edition	Revised Date	Description
First	06/15/2009	New manual
Second	09/30/2009	This manual has benn updated for the internal version 10.11.

© Copyright NEC Corporation 2009. All rights reserved.

## **Disclaimer**

Information in this document is subject to change without notice. No part of this document may be reproduced or transmitted in any form by any means, electronic or mechanical, for any purpose, without the express written permission of NEC Corporation.

#### **Trademark Information**

ExpressCluster® X is a registered trademark of NEC Corporation.

Intel, Pentium and Xeon are registered trademarks and trademarks of Intel Corporation.

Microsoft and Windows are registered trademarks of Microsoft Corporation in the United State and other countries.

Other product names and slogans written in this manual are trademarks and registered trademarks of their respective companies.

# **Table of Contents**

Preface		xvii
Who Should Use	e This Guide	xvii
	is Organized	
	X Documentation Set	
Section I	Detailed functions of ExpressCluster	21
Section 1	Detailed functions of Expresseruster	
Chapter 1	Functions of the WebManager	23
Window of the V	VebManager	24
	the WebManager	
	WebManager	
Searching for an	alert by using the WebManager	25
	by using the WebManager	
	ebManager information	
	der from the WebManager	
	topping the cluster services from the WebManager	
	reen layout on the WebManager	
	tus of each object in the tree view of WebManager	
	e icons displayed in the WebManager tree view	
	the WebManager	
	ster status by the WebManager list view	
	mation on the whole cluster	
	nole status of the server in the WebManager list view	
	tus of individual server in the WebManager list viewtus of the whole monitor in the WebManager list view	
	using the WebManager	
	using the webivianager	
	tion	
	er	
	mirror disk helper	
	rror (forcefully)	
	recovery	
	s restriction	
	ng and starting the WebManager	
	t want to use the WebManager	
	as on the connection and operation of the WebManager	
	on	
	ntion of the WebManager	
	ter by using the WebManager	
	n and cluster shutdown reboot	
	urce and hybrid disk resource	
	ers	
	nd rebooting an individual server	
	g, and moving an individual group	
	pping a group resource	
	spending a monitor resource	
	e WebManager	
Error messages of	on the WebManager	78
Chapter 2	Functions of the Integrated WebManager	85
What is the Integ	grated WebManager?	86
	egrated WebManager	
	he Integrated WebManager	
	w of the WebManager	

	e status of each object in the tree view of the Integrated WebManager	
	the Integrated WebManager	
	cluster to the Integrated WebManager	
	e information on the Integrated WebManager	
	WebManager from the Integrated WebManager	
	cluster from the Integrated WebManager	
Error messages or	n the Integrated WebManager	92
Chapter 3	Function of the Builder	95
Overview of the I	Builder	96
	or using the Builder	
	sing the Builder	
	ilder screen	
	ExpressCluster X Builder	
	- F	
	name selection	
	election	
	ame selection	
	r resource selection	
	selection	
	name selection	
	group selection	
	group name selection	
	of the Builder	
	oar of the Builder	
	luster	
	iguration file	
	guration file	
	configuration file	
	nfiguration file	
	el settings of Builder	
	er logs	
	Builder	
C		
	ect	
	ect	
Properties		117
Checking the vers	sion information of the Builder	117
Parameter details		118
1 1	S	
	n Resolution I/F tab	
	)	
3		
	lanager tab	
	tanager (ab	
	ıb	
•		
	ıb	
· · · · · · · · · · · · · · · · · · ·		
Alert service tab		143
U		
Server Properties		150

Interface of each	server	150
	N I/F tab	
	ab	
U		
	F tab ~ for Replicator/Replicator DR ~	
~ ~	)	
**	egistration	
Chapter 4	ExpressCluster command reference	
	ster from the command line	
ExpressCluster co	ommands	202
Displaying the cl	uster status (clpstat command)	204
	cuting the command that displays status (clpstat command)	
Displaying the sta	atus	207
Displaying a grou	ıp map (clpstat command)	208
	atus of monitor resources (clpstat command)	
	atus of heartbeat resources (clpstat command)	
	atus of network partition resolution resources (clpstat command)	
Displaying the cl	uster configuration data (clpstat command,cl option)	211
	he configuration data of certain servers (clpstat command with thesv option)	
	he resource information of certain heartbeats (clastat command with thehb option)	215
	he resource information of certain network partition resolutions (clpstat command with the	21.5
	he configuration data of certain server groups (clostat command with thesvg option)	
	he configuration data of certain groups (clastat command with thegrp option)	
	he configuration data of a certain group resource (clostat command with thersc option)	
	he data of a certain monitor resource (clpstat command with themon option)	
	ns	
	ster (clpcl command)	
	specified server (clpdown command)	
	e entire cluster (clpstdn command)	
1 00 1	(clpgrp command)	
	elplogee command)	
	y specifying a type (-t option)	
Output paths of lo	og files (-o option)	267
	ollector server (-n option)	
	nation at emergency OS shutdown	
	and backing up configuration data (clpcfctrl command)	
Creating a cluster	· (clpcfctrlpush)	269
	uster configuration data	
Adjusting time-or	ut temporarily	276
	g level and size	
	mmands	
	play commands	
	after running the mirror status display command	
	rce operation command	
	ing command	
	command of hybrid disk resource	
	s display command	
	s of hybrid disk status display command	
	rce operation command	
	ommand	
-	tor resources (clpmonctrl command)	
Controlling groun	p resources (clarsc command)	318

Network warning	light switch off command	322
CPU frequency co	ontrol command	323
	ontrol command	
	essing request command	
	change command	
Shutdown hook co	onfiguration command	332
Chapter 5	Compatible command reference	335
Compatible comn	nand overview	336
	le commands	
Compatible comn	nands	336
	essages on ExpressCluster clients (armbcast command)	
	essages on a log file or an alert log (armlog command)	
	cations or services (armload command)	
	pplication or service (armkill command)	
	art or stop of groups (armgwait command)	
	between servers command (armcall command)	
	ster wide variable or local variable (armgeted command)	
	wide variable or local variable (armseted command)	
	on the connection to the shared resources (armwhshr command)	354
	oplications or services started by the armload command (ExpressCluster Task	358
	e server (armdown command)	
Moving or failing	over a group (armfover command)	362
Starting a group (	armgstrt command)	363
	(armgstop command)	364
	ng the application or service, suspending or resuming the monitoring (armloadcd)	265
	eript execution until the user's direction (armpause command)	
	eript execution until the user's direction (armpause command)	
	ork sharing of the directory (armnsadd command)	
	ork sharing of the directory (armnsdel command)	
	ress returned by gethostbyname() (armwsset command)	
	ing the start delay time (armdelay command)	
	ing operations at the occurrence of the emergency shutdown (armem command)	
Shutting down the	e whole cluster (armstdn command)	375
Returning the serv	ver with the status of "Suspension (isolated)" (armmode command)	376
Permitting an acco	ess to the mirror disk (mdopen command)	377
	cess to the mirror disk (mdclose command)	
	ess to the shared disk (sdopen command)	
	cess to the shared disk (sdclose command)	
Error messages of	f the compatible commands	381
Section II	Resource details	391
Chapter 6	Group resource details	393
-	3-0 <b>-4</b> - 1-3-0-1-3-1-3-1-3-1-3-1-3-1-3-1-3-1-3-1-	
1		
	ilover policy	
	ection of activation and inactivation errors	
Final action		406
	it	
	oot count	
	nanging the settings of group properties	
	p nanging the comment of a group	
	nanging the settings of servers that starts up the group	
	anging the server group settings	
	nanging the group attribute	

Displaying and changing Logical Service	
Displaying and changing the settings of group resources	417
Renaming a group resource	
Displaying and changing the comment of a group resource	
Understanding the settings of dependency among group resources	418
Displaying and configuring the settings of dependency among group resources	419
Displaying and changing the operation settings when a group resource error is detected	
Displaying the properties of the whole groups by using the WebManager	
Displaying the properties of a certain group by using the WebManager	
Understanding server groups	
Displaying / changing the server group settings	
Renaming a server group (Server group properties)	
Displaying and changing the comment of a server group (Server group properties)	
Displaying and changing the settings of servers belonging to a server group (Server group properties)	
Displaying the server group properties with WebManager	
Understanding application resources	432
Dependency of application resources	
Application resources.	
Note on application resources	432
Displaying and changing the application resource details	432
Displaying the application resource properties with the WebManager	
Understanding floating IP resources	
Dependencies of floating IP resources	
Floating IP	
Notes on floating IP resources	
Displaying the properties of floating IP resource with the WebManager	
Understanding mirror disk resources	
Dependencies of mirror disk resources	
Mirror disk	
Understanding mirror parameters	
Examples of mirror disk construction	
Note on mirror disk resources	
Displaying and changing the details of mirror disk resources	
Tuning mirror disk resource	459
Displaying the mirror disk resource properties with the WebManager	461
Understanding registry synchronization resources	
Dependencies of registry synchronization resources	
Registry synchronization resources	
Notes on registry synchronization resources	
Displaying and changing the details of registry synchronization resource	
Displaying the registry synchronization resource properties with the WebManager	
Understanding script resources	
Dependencies of script resources	
Scripts in script resources.	
Environment variables in script of script resource	
Execution timing of script resource scripts	
Writing scripts	
Tips for creating scripts	
Displaying and changing the settings of the script resource details	
Displaying and changing the script resource details	
Displaying and/or changing the script resource script created by the Builder	
Tuning script resource	
Displaying the script resource properties with the WebManager	
Understanding disk resources	
Dependencies of disk resources	
Disk resources	
Notes on disk resources	
Displaying and changing the details of disk resources	
Understanding service resources	
Dependencies of service resources.	

Service resources	
Notes on service resources	
Displaying and changing the details of service resource	
Displaying the service resource properties with the WebManager	507
Understanding print spooler resources	
Dependencies of print spooler resources	
Print spooler resources	
Notes on print spooler resources	
Displaying and changing the details of print spooler resources	
Displaying the print spooler resource properties with the WebManager	
Understanding virtual computer name resources	
Dependencies of virtual computer name resources	
Virtual computer name resources	
Determining virtual computer name	
Configuring WINS server	514
Services available to the virtual computer name	
Notes on virtual computer name resources.	
Displaying and changing the details of virtual computer name resource	
Displaying the virtual computer name resource properties with the WebManager	
Understanding virtual IP resources	
Dependencies of virtual IP resources.	
Virtual IP resources	
Determining virtual IP address	
Controlling path	525
Requirement to use virtual IP address	
Notes on IP resources	
Displaying and changing the details of virtual IP resource	
Displaying the virtual IP resource properties with the WebManager	532
Understanding CIFS resources	535
Dependencies of CIFS resources	535
CIFS resources	535
Notes on CIFS resources	
Displaying and changing the details of CIFS resources	
Displaying CIFS resource properties with the WebManager	
Understanding NAS resources	
Dependencies of NAS resources	
NAS resources	
Notes on NAS resources	
Displaying and changing NAS resources	
Displaying NAS resource properties with the WebManager	
Understanding hybrid disk resources	
Dependencies of hybrid disk resources	
Hybrid disk	
Notes on hybrid disk  Displaying / changing the details of hybrid disk	
Tuning hybrid disk resources	
Displaying hybrid disk resource properties with WebManager	
Displaying hybrid disk resource properties with webwahager	
Chapter 7 Monitor resource details	551
	550
Monitor resources	
Monitor timing of monitor resources	
Monitoring interval for monitor resources	
Behavior when an error is detected by a monitor resource	
Activation and deactivation error of recovery target when executing recovery operation	
Delay warning of monitor resources	
Waiting for monitor resource to start monitoring	
Monitor resources that require a license	
Displaying and changing the settings of group resources	
Changing the name of a monitor resource	
Displaying and changing the comment of a monitor resource	
Displaying and changing the settings of a monitor resource	
Displaying and changing the settings when an error is detected by a monitor resource	

Displaying and changing parameters of a monitor resource	602
Understanding application monitor resources	
Monitoring by application monitor resources	603
Displaying the application monitor resource properties with the WebManager	
Understanding disk RW monitor resources	
Monitoring by disk RW monitor resources	605
Displaying and changing disk RW monitor resource details	
Displaying the disk RW monitor resource properties with the WebManager	
Understanding floating IP monitor resources	
Monitoring by floating IP monitor resources	
Displaying and changing floating IP monitor resource details	
Displaying the floating IP monitor resource properties with the WebManager	
Understanding IP monitor resources	
Monitoring by IP monitor resources	612
Displaying and changing IP monitor resource details	613
Displaying the IP monitor resource properties with the WebManager	
Understanding mirror connect monitor resources	
Note on mirror connect monitor resources.	
Displaying and changing the mirror connect monitor resource details ~For Replicator ~	
Displaying the mirror connect monitor resource properties with the WebManager	
Understanding mirror disk monitor resources	
Note on mirror disk monitor resources.	
Displaying and changing the mirror disk monitor resource details	
Displaying the mirror disk monitor resource properties with the WebManager	
Understanding NIC link up/down monitor resources  Note on NIC link up/down monitor resources	
Configuration and range of NIC link up/down monitoring	
Displaying and changing the NIC link up/down monitor resource details	
Displaying the NIC link up/down monitor resource properties with the WebManager	
Understanding multi target monitor resources	
Multi target monitor resource status.	
Displaying and changing the details of the multi target monitor resource	
Tuning multi target monitor resource	631
Displaying the properties of the multi target monitor resource with the WebManager	633
Understanding registry synchronization monitor resources	
Displaying and changing the details of the registry synchronization monitor resources	
Displaying the registry synchronization monitor resources properties with the WebManager	
Understanding disk TUR monitor resources	
Notes on disk TUR monitor resources	
Displaying and changing the disk TUR monitor resource details	
Displaying the disk TUR monitor resources properties with the WebManager	638
Understanding service monitor resources	640
Monitoring by service monitor resources	640
Displaying and changing the details of the service monitor resources	640
Displaying the service monitor resources properties with the WebManager	
Understanding print spooler monitor resources	
Displaying and changing the details of the print spooler monitor resources	
Displaying the print spooler monitor resources properties with the WebManager	
Understanding virtual computer name monitor resources	
Monitoring by virtual computer name monitor resources	
Virtual computer name monitor resource	
Displaying and changing the details of the virtual computer name resources	
Displaying the virtual computer name monitor resource properties with the WebManager	
Understanding virtual IP monitor resources	
Monitoring by virtual IP monitor resources	
Displaying and changing the details of the virtual IP monitor resources	
Displaying the virtual IP monitor resource properties with the WebManager	
Understanding CIFS monitor resources	
Monitoring by CIFS monitor resources.	
Notes on CIFS monitor resources	
Displaying and changing the details of CIFS monitor resources	
Understanding NAS monitor resources	
Onderstanding IVAD Infinite resources	032

Monitoring by NAS monitor resources	652
Displaying and changing the details of NAS monitor resources	
Displaying NAS monitor resources properties with the WebManager	
Understanding hybrid disk monitor resources	
Note on hybrid disk monitor resources	
Displaying and changing the hybrid disk monitor resource details	
Displaying the hybrid disk monitor resource properties with the WebManager	
Understanding hybrid disk TUR monitor resources	
Notes on hybrid disk TUR monitor resources	657
Displaying and changing the hybrid disk TUR monitor resource details	657
Displaying the hybrid disk TUR monitor resources properties with the WebManager	
Understanding custom monitor resources	
Monitoring by custom monitor resources	
Displaying and changing the details of the custom monitoring resources	
Displaying the custom monitor resource properties with the Web Manager	
Understanding DB2 monitor resources	
DB2 monitor resources	
Displaying and changing the disk DB2 monitor resource details	
Displaying the DB2 monitor resource properties with the WebManager	
Understanding FTP monitor resources	
FTP monitor resources	
Monitoring by FTP monitor resources.	
Displaying and changing the FTP monitor resource details	
Displaying the FTP monitor resource properties with the WebManager	
Understanding HTTP monitor resources	
HTTP monitor resources	
Monitoring by HTTP monitor resources	
Displaying and changing the HTTP monitor resource details	
Displaying the HTTP monitor resource properties with the WebManager	
Understanding IMAP4 monitor resources	
IMAP4 monitor resources	
Monitoring by IMAP4 monitor resources	
Displaying and changing the IMAP4 monitor resource details	676
Displaying the IMAP4 monitor resource properties with the WebManager	677
Understanding ODBC monitor resources	680
ODBC monitor resources	680
Monitoring by ODBC monitor resources	680
Displaying and changing the ODBC monitor resource details	
Displaying the ODBC monitor resource properties with the WebManager	
Understanding Oracle monitor resources	
Oracle monitor resources	
Monitoring by Oracle monitor resources	
Displaying and changing the Oracle monitor resource details	684
Displaying the Oracle monitor resource properties with the WebManager	
Understanding OracleAS monitor resources	
Note on OracleAS monitor resources	
How OracleAS monitor resources perform monitoring	
Displaying and changing the OracleAS monitor resource details	689
Displaying and changing the OracleAS monitor resource properties with the WebManager	
Understanding OfficeScan CL monitor resource	
Notes on OfficeScan CL monitor resource	
How OfficeScan CL monitor resource performs monitoring	
Displaying and changing OfficeScan CL monitor resource details	
Displaying OfficeScan CL monitor resource properties with Web Manager	
Understanding OfficeScan SV monitor resource	
Notes on OfficeScan SV monitor resource	
How OfficeScan SV monitor resource perform monitoring	
Displaying OfficeScan SV monitor resource details	
Displaying OfficeScan SV monitor resource properties with Web Manager	
Understanding POP3 monitor resources	
Monitoring by POP3 monitor resources	
Displaying and changing the POP3 monitor resource details	
Displaying and changing the for a monitor resource details	

	P3 monitor resource properties with the WebManager	
	stgreSQL monitor resources	
	for resources	
	stgreSQL monitor resources	
	anging the PostgreSQL monitor resource details	
	stgreSQL monitor resource properties with the WebManager	
	ITP monitor resources	
	TP monitor resources.	
	anging the SMTP monitor resource details	
	ITP monitor resource properties with the WebManager	
	L Server monitor resources	
	or resources	
	L Server monitor resources	
	anging the SQL Server monitor resource details	
	L Server monitor resource properties with the WebManager	
	xedo monitor resources	
	esources	
	xedo monitor resources	
	anging the Tuxedo monitor resource detailsxedo monitor resource properties with the WebManager	
	ebsphere monitor resources	
	or resources	
	bsphere monitor resources	
	anging the Websphere monitor resource details	
	bsphere monitor resource properties with the WebManager	
	eblogic monitor resources	
	resources	
	blogic monitor resources	
	anging the Weblogic monitor resource details	
	blogic monitor resource properties with the WebManager	
Understanding We	ebOTX monitor resources	726
	resources	
	anging the WebOTX monitor resource details Websphere	
Displaying and Cli	bOTX monitor resource properties with the WebManager	727 728
Chapter 8	Heartbeat resources	731
_		
Heartbeat resource	es	732
Heartbeat resource Understanding ker		
Heartbeat resource Understanding ker Kernel mode LAN	es nel mode LAN heartbeat resources	732 733
Heartbeat resource Understanding ker Kernel mode LAN Settings of the ker Notes on the kerne	es	
Heartbeat resource Understanding ker Kernel mode LAN Settings of the ker Notes on the kerne	es	
Heartbeat resource Understanding ker Kernel mode LAN Settings of the ker Notes on the kerne Displaying the pro	es	
Heartbeat resource Understanding ker Kernel mode LAN Settings of the ker Notes on the kerne Displaying the pro	es	
Heartbeat resource Understanding ker Kernel mode LAN Settings of the ker Notes on the kerne Displaying the pro  Chapter 9  Network partitions	es	
Heartbeat resource Understanding ker Kernel mode LAN Settings of the ker Notes on the kerne Displaying the pro  Chapter 9  Network partitions Understanding the	rnel mode LAN heartbeat resources	
Heartbeat resource Understanding ker Kernel mode LAN Settings of the ker Notes on the kerne Displaying the pro  Chapter 9  Network partitions Understanding the Understanding net	rnel mode LAN heartbeat resources	
Heartbeat resource Understanding ker Kernel mode LAN Settings of the ker Notes on the kerne Displaying the pro  Chapter 9  Network partitions Understanding the Understanding net Settings of the CO	rnel mode LAN heartbeat resources	
Heartbeat resource Understanding ker Kernel mode LAN Settings of the ker Notes on the kerne Displaying the pro  Chapter 9  Network partitions Understanding the Understanding net Settings of the CO COM network par	rnel mode LAN heartbeat resources I heartbeat resources Inde LAN heartbeat resources with the WebManager Inde LAN heartbeat resources with the WebManager Index on network partition resolution resources Index on network partition resour	
Heartbeat resource Understanding ker Kernel mode LAN Settings of the ker Notes on the kerne Displaying the pro  Chapter 9  Network partitions Understanding the Understanding net Settings of the CO COM network par Displaying the pro	rnel mode LAN heartbeat resources	
Heartbeat resource Understanding ker Kernel mode LAN Settings of the ker Notes on the kerne Displaying the pro  Chapter 9  Network partitions Understanding the Understanding net Settings of the CO COM network par Displaying the pro Understanding net	rnel mode LAN heartbeat resources	
Heartbeat resource Understanding ker Kernel mode LAN Settings of the ker Notes on the kerne Displaying the pro  Chapter 9  Network partitions Understanding the Understanding net Settings of the CO COM network par Displaying the pro Understanding net Settings of the Displaying the pro	rnel mode LAN heartbeat resources	
Heartbeat resource Understanding ker Kernel mode LAN Settings of the ker Notes on the kerne Displaying the pro  Chapter 9  Network partitions Understanding the Understanding net Settings of the CO COM network par Displaying the pro Understanding net Settings of the DIS DISK network par	rnel mode LAN heartbeat resources I heartbeat resources Index LAN heartbeat resources with the WebManager Index LAN heartbeat resources Index LAN heartbeat resources with the WebManager Index LAN heartbeat resources Index LAN heartbeat resources Index LAN heartbeat resources with the WebManager Index LAN heartbeat resources Index LAN heartbeat resources Index LAN heartbeat resources Index LAN heartbeat resources with the WebManager Index LAN heartbeat resources with the WebManager Index LAN heartbeat resources Index LAN heartbeat resources Index LAN heartbeat resources with the WebManager Index LAN heartbeat resources with the WebManager Index LAN heartbeat resources	
Heartbeat resource Understanding ker Kernel mode LAN Settings of the ker Notes on the kerne Displaying the pro  Chapter 9  Network partitions Understanding net Settings of the CO COM network par Displaying the pro Understanding net Settings of the DIS DISK network par Displaying the pro Understanding net Settings of the DIS DISK network par Displaying the pro Understanding net	rnel mode LAN heartbeat resources I heartbeat resources Index LAN heartbeat resources with the WebManager Index LAN heartbeat resources Index LAN heartbeat resources with the WebManager Index LAN heartbeat resources Index LAN heartbeat resources Index LAN heartbeat resources with the WebManager Index LAN heartbeat resources Index LAN heartbeat resources Index LAN heartbeat resources with the WebManager Index LAN heartbeat resources Index LAN heartbeat resources Index LAN heartbeat resources with the WebManager Index LAN heartbeat resources with the WebManager Index LAN heartbeat resources Index LAN heartbeat	
Heartbeat resource Understanding ker Kernel mode LAN Settings of the ker Notes on the kerne Displaying the pro  Chapter 9  Network partitions Understanding the Understanding net Settings of the CO COM network par Displaying the pro Understanding net Settings of the DIS DISK network par Displaying the pro Understanding net Settings of the DIS Settings of the PIN Understanding net Settings of the PIN	rnel mode LAN heartbeat resources I heartbeat resources Index LAN heartbeat resources with the WebManager Index LAN heartbeat resources Index LAN heartbeat resources Index LAN heartbeat resources with the WebManager Index LAN heartbeat resources Index LAN heartbeat resources Index LAN heartbeat resources Index LAN heartbeat resources with the WebManager Index LAN heartbeat resources Index LAN heartbeat	
Heartbeat resource Understanding ker Kernel mode LAN Settings of the ker Notes on the kerne Displaying the pro  Chapter 9  Network partitions Understanding the Understanding net Settings of the CO COM network par Displaying the pro Understanding net Settings of the DIS DISK network par Displaying the pro Understanding net Settings of the PIS Understanding net Settings of the PIN PING network par	rnel mode LAN heartbeat resources I heartbeat resources Indicate the precision of kernel mode LAN heartbeat resources Indicate the precision of kernel mode LAN heartbeat resources with the WebManager Indicate the precision of kernel mode LAN heartbeat resources with the WebManager Indicate the precision of kernel mode LAN heartbeat resources with the WebManager Indicate the precision of kernel mode LAN heartbeat resources with the WebManager Indicate the precision of the work partition resolution resources Indicate the precision of the work partition resolution resources with the WebManager Indicate the work partition resolution resources with the WebManager Indicate the work partition resolution resources with the WebManager Indicate the work partition resolution resources with the WebManager Indicate the work partition resolution resources with the WebManager Indicate the work partition resolution resources with the WebManager Indicate the work partition resolution resources with the WebManager Indicate the work partition resolution resources with the WebManager Indicate the work partition resolution resources with the WebManager Indicate the work partition resolution resources with the WebManager Indicate the work partition resolution resources with the WebManager Indicate the work partition resolution resources with the WebManager Indicate the work partition resolution resources with the WebManager Indicate the work partition resolution resources with the WebManager Indicate the work partition resolution resources with the WebManager Indicate the work partition resolution resources with the WebManager Indicate the work partition resolution resources with the WebManager Indicate the work partition resolution resources with the WebManager Indicate the work partition resolution resources with the WebManager Indicate the work partition resolution resources with the WebManager Indicate the work partition resolution resources with the WebManager Indicate the work partition resolution resources with the WebManager	
Heartbeat resource Understanding ker Kernel mode LAN Settings of the ker Notes on the kerne Displaying the pro  Chapter 9  Network partitions Understanding the Understanding net Settings of the CO COM network par Displaying the pro Understanding net Settings of the DIS DISK network par Displaying the pro Understanding net Settings of the PIS PING network par Displaying the pro	nel mode LAN heartbeat resources heartbeat resources nel mode LAN heartbeat resources her mode LAN heartbeat resources with the WebManager her mode LAN heartbeat resources with the WebManager  Details on network partition resolution resources  network partition resolution by COM method Munetwork partition resolution resources her mode LAN heartbeat resources her mode LAN heartbeat resources her mode LAN heartbeat resources with the WebManager  Note of the WebManager  Note of COM network partition resolution resources with the WebManager  Note of COM network partition resolution resources with the WebManager  Note of COM network partition resolution resources with the WebManager  Note of COM network partition resolution resources with the WebManager  Note of COM network partition resolution resources with the WebManager  Note of COM network partition resolution resources with the WebManager  Note of COM network partition resolution resources with the WebManager  Note of COM network partition resolution resources with the WebManager  Note of COM network partition resolution resources with the WebManager  Note of COM network partition resolution resources with the WebManager	732 733 733 733 734 735 736 736 736 739 740 741 741 742 743 744 744 745
Heartbeat resource Understanding ker Kernel mode LAN Settings of the ker Notes on the kerne Displaying the pro  Chapter 9  Network partitions Understanding the Understanding net Settings of the CO COM network par Displaying the pro Understanding net Settings of the DIS DISK network par Displaying the pro Understanding net Settings of the PIN PING network par Displaying the pro Understanding net Settings of the PIN PING network par Displaying the pro Understanding net	nel mode LAN heartbeat resources I heartbeat resources nel mode LAN heartbeat resources nel mode LAN heartbeat resources I mode LAN heartbeat resources nel mode LAN heartbeat resources I mode LAN heartbeat resources I mode LAN heartbeat resources with the WebManager  Details on network partition resolution resources I network partition resolution by COM method I network partition resolution resources I network partition resolution resolution resources with the WebManager I network partition resolution resources I network partition resolution resolution resources with the WebManager I network partition resolution resources with the WebManager I network partition resolution resources I network partition resolution resources I network partition resolution resources with the WebManager I network partition resolution resolution resources with the WebManager I network partition resolution resources with the WebManager I network partition resolution resources with the WebManager I network partition resolution resolution resources with the WebManager I network partition resoluti	732 733 733 733 734 735 736 736 737 739 740 741 741 742 743 744 744 745 745
Heartbeat resource Understanding ker Kernel mode LAN Settings of the ker Notes on the kerne Displaying the pro  Chapter 9  Network partitions Understanding the Understanding net Settings of the CO COM network par Displaying the pro Understanding net Settings of the DIS DISK network par Displaying the pro Understanding net Settings of the PIN PING network par Displaying the pro Understanding net Settings of the PIN PING network par Displaying the pro Understanding net Settings of the ma	nel mode LAN heartbeat resources heartbeat resources nel mode LAN heartbeat resources her mode LAN heartbeat resources with the WebManager her mode LAN heartbeat resources with the WebManager  Details on network partition resolution resources  network partition resolution by COM method Munetwork partition resolution resources her mode LAN heartbeat resources her mode LAN heartbeat resources her mode LAN heartbeat resources with the WebManager  Note of the WebManager  Note of COM network partition resolution resources with the WebManager  Note of COM network partition resolution resources with the WebManager  Note of COM network partition resolution resources with the WebManager  Note of COM network partition resolution resources with the WebManager  Note of COM network partition resolution resources with the WebManager  Note of COM network partition resolution resources with the WebManager  Note of COM network partition resolution resources with the WebManager  Note of COM network partition resolution resources with the WebManager  Note of COM network partition resolution resources with the WebManager  Note of COM network partition resolution resources with the WebManager	732 733 733 733 734 735 736 736 737 737 737 740 741 741 742 743 744 744 745 745

	operties of majority network partition resolution resources with the WebManager	
	work partition resolution by COM method and DISK method	
	work partition resolution by PING method and DISK method	
Not resolving netv	vork partition	748
Chapter 10	Other monitor settings	749
The forced stop fu	nction	750
What is the forced	stop function?	750
	forming forced stop	
	used for forced stop	
	anging the details of forced stop	
	d stop	
	entify?	
	assis ID lamp to blink	
	assis ID lamp blinking when the cluster stops	
	ised for chassis identify	
	anging the chassis identify details	
	dentify	
	rice?	
	S	
	tus	
	ing icon	
Section III	Maintenance information	
Section III		
Chapter 11	The system maintenance information	
Directory structure	e of ExpressCluster	760
	orts	
	essCluster to shut down servers	
Final action for an	error in group resource activation or deactivation	763
	ection of an error in monitor resource	
	r shutdown	
	tion error in stopping the ExpressCluster Server service	
	restart	
	ettings to temporarily prevent execution of failover	
	server with a new one	
	Chronized cluster startup	
	er configuration (add/delete).	
	er configuration (add/derec)	
	er IP address	
	e mirror connect IP address is not required	
	e mirror connect IP address is required	
	name	
	re the mirror disk / hybrid disk does not exist	
	re the mirror disk / hybrid disk exists	
Replacing the netv	work card	772
	configuration ~For a shared disk~	
	<u> </u>	
	configuration ~For a mirror disk~	
	<u> </u>	
•		
C		
- 1	ing data	
Performing a snap	shot backup	778

	shot backup	
Linking to ESMPF	RO Agent	779
Environment setting	1gs	779
Setting the UPS		780
Restoring the syste	em disk	780
Replacing the shar	ed disk	
Replacing the mirr	ror disk	
Replacing FibreCh	nannel HBA / SCSI controller	
Information requir	ed for inquiry	786
Ohamtan 12	Tuonblashaatina	707
Chapter 12	Troubleshooting	/8/
	Cluster system does not start or end	
	r deactivating network partition resolution resource fails	
	artition resolution resource error is detected	
	resolution resource becomes unavailable	
When activating or	r deactivating group resources fails	790
	esource error occurs	
	time-out occurs	
•	ailure of one server	
	ailure of both serversended server (with unresolved network partition)	
	titioning occurs	
	nands when interconnections are disconnected	
	disks/hybrid disks manually	
	ing mirror disk when mirroring is available	
	ng mirror disk when mirroring is not available	
	nirror breaks	
	overing from mirroring	
	or break status with a command	
	or recovery progress with a command	
	with a command	
Running the forcib	ole mirror recovery with a command	802
	ole mirror recovery with a command only on one server	
	or break status from the WebManager	
	or recovery progress from the WebManager	
	using the WebManager	
	ble mirror recovery using the WebManager	
	ble mirror recovery from the WebManager only on one server	
Media sense functi	ion becomes invalid	809
Chapter 13	Error messages	811
Messages		812
	etup	
	l by event log and alert	
	nessages	
	6-	
	heartbeat driver	
	on in activating and deactivating group resources	
	rce	
* *		
	ce	
	ce / hybrid disk resource	
Registry synchroni	ization resource	841
Disk resource		843
Service resource		844
•	ırce	
	name resource	
	2	
Detailed info of me	onitor resource errors	848

Appendix B	Index	881
Appendix A	Glossary	879
Appendix		877
	resource	
C	resource	
	or resource	
	resource	
Virtual computer i	name monitor resource	871
Tuxedo monitor re	esource	871
SQL Server monit	or resource	870
SMTP monitor res	source	869
Print spooler moni	itor resource	868
	esource	
	r resource	
	ization monitor resource	
	tor resource	
	ource	
	onitor resource	
	onitor resource	
	resource	
	source	
	source	
	/n monitor resource	
•	or resourceurce	
	onitor resource	
	or resource	
	ce	
	source	
	ource	
•	or resource	
	monitor resource	
	esource	
	ırce	
	or resource	
Disk RW monitor	resource	850
DB2 monitor reso	urce	849
* *	ource	
Application monit	or resource	848

# **Preface**

#### Who Should Use This Guide

The ExpressCluster X Reference Guide is intended for system administrators. Detailed information for setting up a cluster system, function of the product, maintenance related information, and how to troubleshoot the problems are covered in this guide. The guide provides supplemental information to the Installation and Configuration Guide.

## **How This Guide is Organized**

Section I Detailed functions of ExpressCluster

Chapter 1 Detailed functions of ExpressCluster

Provides information on function of the ExpressCluster WebManager.

**Chapter 2** Functions of the Integrated WebManager

Provides information on function of the Integrated WebManager.

**Chapter 3** Function of the Builder

Provides information on function of the ExpressCluster Builder.

Chapter 4 ExpressCluster command reference

Provides information on commands available to use in ExpressCluster.

Chapter 5 Compatible command reference

Provides information on the commands that are compatible to the commands used in the older

versions of ExpressCluster.

Section II Resource details

**Chapter 6** Group resource details

Provides information on group resource which configures a failover group.

**Chapter 7** Monitor resource details

Provides information on monitor resource which works as a monitoring unit in ExpressCluster.

Chapter 8 Heartbeat resources

Provides information on heartbeat resource.

Chapter 9 Details of the network partition resolution resource

Provides information on the network partition resolution resource.

Chapter 10 Other monitor settings

Provides information on other monitor settings.

**Section III** Maintenance information

**Chapter 11** The system maintenance information

Provides maintenance information for ExpressCluster.

**Chapter 12** Troubleshooting

Provides instruction on how to troubleshoot the problem.

**Chapter 13** Error messages

Provides explanation on error messages displayed during ExpressCluster operation.

**Appendix** 

Appendix A Glossary Appendix B Index

# **ExpressCluster X Documentation Set**

The ExpressCluster X manuals consist of the following four guides. The title and purpose of each guide is described below:

#### **Getting Started Guide**

This guide is intended for all users. The guide covers topics such as product overview, system requirements, and known problems.

#### **Installation and Configuration Guide**

This guide is intended for system engineers and administrators who want to build, operate, and maintain a cluster system. Instructions for designing, installing, and configuring a cluster system with ExpressCluster are covered in this guide.

#### **Reference Guide**

This guide is intended for system administrators. The guide covers topics such as how to operate ExpressCluster, function of each module, maintenance-related information, and troubleshooting. The guide is supplement to the *Installation and Configuration Guide*.

#### Integrated WebManager Administrator's Guide

This guide is intended for system administrators who manage the cluster system using ExpressCluster with Integrated WebManager and for system engineers introducing the Integrated WebManager. Details on the actual procedures required when introducing cluster system are described in this guide.

# **Conventions**

In this guide, **Note**, **Important**, **Related Information** are used as follows:

#### Note:

Used when the information given is important, but not related to the data loss and damage to the system and machine.

#### Important:

Used when the information given is necessary to avoid the data loss and damage to the system and machine.

#### **Related Information:**

Used to describe the location of the information given at the reference destination.

The following conventions are used in this guide.

Convention	Usage	Example
Bold	Indicates graphical objects, such as fields, list boxes, menu selections, buttons, labels, icons, etc.	In <b>User Name</b> , type your name. On the <b>File</b> menu, click <b>Open Database</b> .
Angled bracket within the command line	Indicates that the value specified inside of the angled bracket can be omitted.	clpstat -s[-h host_name]
#	Prompt to indicate that a Linux user has logged on as root user.	clpcl -s -a
Monospace (courier)	Indicates path names, commands, system output (message, prompt, etc), directory, file names, functions and parameters.	c:\Program files\EXPRESSCLUSTER
Monospace bold (courier)	Indicates the value that a user actually enters from a command line.	Enter the following: clpcl -s -a
Monospace italic (courier)	Indicates that users should replace italicized part with values that they are actually working with.	clpstat -s [-h host_name]

# **Contacting NEC**

For the latest product information, visit our website below:

http://www.nec.com/global/prod/expresscluster/

# Section I Detailed functions of ExpressCluster

This section explains the details of ExpressCluster functions. Specifically, the function of the ExpressCluster X WebManager and the Builder is described. It also gives the description of the available commands on ExpressCluster.

- Chapter 1 Functions of the WebManager
- Chapter 2 Functions of the Integrated WebManager
- Chapter 3 Function of the Builder
- Chapter 4 ExpressCluster command reference
- Chapter 5 Compatible command reference

# Chapter 1 Functions of the WebManager

This chapter describes the functions of the WebManager.

#### This chapter covers:

•	Window of the WebManager	24
•	Checking the status of each object in the tree view of WebManager	31
•	Checking the cluster status by the WebManager list view	51
•	Checking alerts using the WebManager	56
•	Mirror disk helper	59
•	Manually stopping and starting the WebManager	71
•	When you do not want to use the WebManager	71
•	Setting limitations on the connection and operation of the WebManager	72
•	Operating a cluster by using the WebManager	
•	Limitations of the WebManager	77
•	Error messages on the WebManager	78

# Window of the WebManager


This chapter provides information about the WebManager window.

#### Note:

The information in this chapter is based on the window representation in an English environment. The language representation on the screen will depend on the locale of the OS of a management PC.

# Main window of the WebManager

The WebManager window consists of four views.



Title view Alert view

Six buttons in this view allow you to:

- ♦ Search for alert logs
- ◆ Collect ExpressCluster operation logs
- ♦ Reload the window
- ♦ Start the Builder
- ♦ Execute services
- ♦ Display or hide split bars

For more information, see "Title view of the WebManager" on page 25.

#### Tree view

Allows you to see a status of each cluster's resources such as server and group resources. For more information, refer to "Checking the status of each object in the tree view of WebManager" on page 30.

#### List view

Provides information on each cluster resource selected in the tree view.

If you click the **Details** button located on the upper right of the view, further information will be displayed in a dialog. For more information, see "Checking the cluster status by the WebManager list view" on page 51.

#### Alert view

Shows messages describing ExpressCluster operating status. For further information, see "Checking alerts using the WebManager" on page 56.

# Title view of the WebManager

Six types of operations are available by using the buttons in the title view.




## Searching for an alert by using the WebManager

You can search for an alert by using the WebManager. Searching in this method is useful to view only a specific type alert.

#### Note:

For the information on alert logs, see "Checking alerts using the WebManager" on page 56.

- 1. Start the WebManager. (http://FIP\_address\_for\_the\_WebManager\_group:port\_number (default value is 29003))
- **2.** In the title view, click **Filter Alerts** to display the window for setting search conditions for an alert.



#### To search only the specified number of past alert logs:

- 1. Select Display only the specified number of alerts.
- **2.** Enter the number of past alert logs to search, and click **OK**. Past alert logs are displayed as many as you have specified.

#### Note:

The maximum value to enter is the number configured in **Max Number to Save Alert Records**. To configure **Max Number to Save Alert Records**, right-click the cluster icon in the Builder and click **Properties** on the shortcut menu. In the properties dialog box click the **Alert Log** tab.

#### To search by specifying search conditions:

- 1. Click Select the filter option.
- **2.** Enter the search conditions in each field and start searching.

Alert Type: Select this to search by alert type.

**Module Name**: Select this to search by module type. The values you can enter are as follows:

Module Name	Category	
pm	Whole ExpressCluster	
rc	Group/resource related	
rm	Monitor resource related	
nm	Heartbeat resource related	
lankhb	Kernel mode LAN heartbeat resource	
disknp	DISK network partition resolution resource	
fip	Floating IP resource	
vcom	Virtual computer name resource	
vip	Virtual IP resource	
cifs	CIFS resource	
diskw	Disk RW monitor resource	
mdw	Mirror disk monitor resource	
sdw	Disk TUR monitor resource	
hdtw	Hybrid disk TUR monitor resource	
diskagent	Disk agent monitor resource	
sdfunc	Disk function related	
mdadmn	Mirror disk related	
hdadmn	Hybrid disk related	
armcmd	Compatible commands	
event	Event log	
Icns	License related	
logcmd	Message output command	
ptun	Parameter tuning related	
dn1000s	Network warning light alert related	

mail	Mail alert related
------	--------------------

**Server Name**: Select this to search by server name.


**Event ID**: Select this to search by an event ID. For more information on event ID, refer to Chapter 12, "Error Messages."

**Start Time, Stop Time**: Select this to search by the time of the event occurrence. Enter the values in **Start Time** and **Stop Time**.

- 3. Enter the number of alerts to display on one page in **The number of alerts to be displayed per page:** and click **OK**. Research results are displayed based on the time an alert occurred.
- **4.** If the results of research are displayed on more than one page, move the page by clicking **Back**, **Next**, and **Jump** buttons.

## Collecting logs by using the WebManager

Click the **Collect Logs** button to open the log collection dialog box.



#### Check box

Select check boxes of the servers that have the logs you want to collect.

#### Pattern

Select the information to be collected. For information on each pattern, refer to Chapter 4, "ExpressCluster command reference."

#### OK

Starts log collection and displays the dialog box of log collection progress.

#### Cancel


Closes this dialog box.

#### Info

Displays the information for each pattern.

#### **Default**

Resets the selections of servers and collect patterns to default values.



The dialog box of the log collection progress

#### **Update**

Updates the dialog box of the log collection progress.

#### Abort

Aborts the log collection.

#### Close

Closes the Log Collection Progress dialog box. Log collection is continued.

At this time, the display of **Collect Logs** in title view has changed to **Progress**. Click **Progress** to display the **Log Collection Progress** dialog box again.

#### **Collect Logs Results**

Result	Description	
Normal	Log collection succeeded.	
Abort	Log collection was cancelled by user.	
Invalid Parameters	Internal error may have occurred.	
Communication Error	Connecting error occurred.	
Timeout	Timeout occurred.	
Busy	Server is busy.	
Compression Error	Error occurred when compressing a file.	
File I/O Error	File I/O failed.	
Not Enough Free Space	There is not enough available space on the disk.	
Unknown Error	File does not exist.	

When the log collection completes, the browser displays a dialog box that asks where you want to save the logs. Download the logs to any location.



#### Note:

Logs may not be downloaded properly if nothing is changed for more than 10 minutes.

If you are using Internet Explorer 6.0 SP1 or later, the window described above may not be displayed. If the window is not displayed, enable the setting "Automatic prompting for file downloads" in the security settings, and collect logs again. Logs may not be downloaded properly when the window shown above is left without any action for more than 10 minutes.

If other modal dialog is displayed while collecting logs, the file saving dialog for the log collection will not be displayed. To display the file saving dialog, close the modal dialog.

## **Updating the WebManager information**

Update the information displayed in the WebManager by clicking the **Reload** button in the title view in the upper part of the WebManager.

#### Note:

The information in the WebManager is regularly updated and the latest status is not immediately displayed even if the status has changed. To display the latest information, click the **Reload** button after performing an operation.

To configure the automatic reload interval of the WebManager, from the shortcut menu, select **Properties**. In the properties dialog box, click the **WebManager** tab. Configure the **Reload Interval**.

Some objects may be displayed in gray when communications to the connecting destination is disabled or ExpressCluster is not working at the access destination.

# Starting the Builder from the WebManager

Click **Start Builder** to reboot the Builder in the title view on the upper part of the WebManager reboots the Builder. For details on the Builder, refer to Chapter 3, "Function of the Builder."

# Starting and/or stopping the cluster services from the WebManager


Click **Service** to display the following menus.

Menu	Description	
Suspend Cluster	Stop the service temporarily.	
Resume Cluster	Resume the suspended service.	
Start Cluster	Start the service.	
Stop Cluster	Stop the service.	
Restart Manager	Restart the WebManager service.	

# Changing the screen layout on the WebManager

The screen layout of the WebManager can be changed by clicking the buttons of the split bars or by dragging the bars. This is useful to display only a specific view. Display or hide the split bars by clicking the **Option** button in the title view.

The split bars divide the views in the WebManager.



To display or hide the split bars in the WebManager:

- 1. Start the WebManager. (http://FIP\_address\_for\_the\_WebManager\_group:port\_number (default value is 29003))
- **2.** In the title view, click the **Option** button.
- **3.** When using the split bars, select **Display split bar**. When not using split bars, click to clear the check box.
- 4. Click OK.

#### Note:

Change the layout by dragging the bars that divide views even if the function of the split bars is turned off.


# Checking the status of each object in the tree view of WebManager

You can see the status of the objects that configure the cluster on the WebManager by following the steps below.

- 1. Start the WebManager. (http://FIP\_address\_for\_the\_WebManager\_group:port\_number (default value is 29003))
- 2. On the left pane of the window, a tree is displayed. Check the status by looking at each icon and object color. The following is the brief overview of a tree.

#### Note:

The configurations of the tree depend on the versions and option products of ExpressCluster.



# The colors of the icons displayed in the WebManager tree view

The following table shows icons and their meanings:

No.	Icon		Status	Description
(1)	Cluster	Ø	Normal	All servers, group resources, and monitor resources are in a normal status.
			Warning	One or more servers, or group resources, or monitor resource has an error or is in a warning status.
			Error	All servers are down or in the error status.
(2)	All servers		Normal	All servers have been started.
		<u> </u>	Warning	One ore more servers is down or in the pending status.
			Unknown	No information is acquired.
(3)	Individual server		Online	The server is running normally.
			Suspension (Network Partition Unsolved)	The network partition cannot be solved, because the disk network partition resolution resource is in the error status.
		<b>×</b>	Suspension (Isolated)	The server has been rebooted after it was shut down a way other than Suspend Cluster or a cluster shutdown.
		<b>=</b>	Offline or Unknown	The server is not working, or no information is acquired.
(4)	4) Kernel-mode LAN heartbeat	<b>%</b>	Normal	The resource can communicate with all servers.
	resource		Warning	One or more servers in the cluster cannot be accessed.
		×	Error	The resource is not working normally.
		400	Unknown	No status is acquired.
		***	Not Used	The heartbeat resource is not registered.
(5)	(5) Disk network partition resolution resource		Normal	The resource can communicate with all servers.
			Warning	One or more servers in the cluster cannot be accessed.
		×	Error	The resource is not working normally.
			Unknown	No status is acquired.
			Not Used	The disk network partition resolution resource is not registered.

No.	Icon		Status	Description
(6)	COM network partition		Normal	The resource can communicate with all servers.
	resolution resource		Warning	One or more servers in the cluster cannot be accessed.
			Error	The resource is not working normally.
			Unknown	No status is acquired.
			Not Used	The network partition resolution resource is not registered.
(7)	PING network partition		Normal	The resource can communicate with all servers.
	resolution resource		Warning	One or more servers in the cluster cannot be accessed.
			Error	The resource is not working normally.
			Unknown	No status is acquired.
			Not Used	The PING network partition resolution resource is not registered.
(8)	Majority Network Partition		Normal	The resource can communicate with all servers.
	Resolution Resource		Warning	One or more servers in the cluster cannot be accessed.
			Error	The resource is not working normally.
			Unknown	No status is acquired.
			Not Used	The Majority Network Partition Resolution Resource is not registered.
(9)	All groups		Normal	All groups are running normally.
		<u> </u>	Warning	One or more groups are not running normally.
		×	Error	No groups are working normally.
			Unknown	No information is acquired.
(10)	Individual group		Online	The group has been started.
		X	Error	The group has an error.
		5	Offline or Unknown	The group is stopped, or no information is acquired.
(11)	Application resource	<b>=</b>	Online	The application resource has been started.
		×	Error	The application resource has an error.
		<b>3</b>	Offline or Unknown	The application resource is stopped, or no information is acquired.

No.	Icon		Status	Description
(12)	Floating IP resource	<b>**</b>	Online	The floating IP resource has been started.
		×	Error	The floating IP resource has an error.
		-	Offline or Unknown	The floating IP resource is stopped/ no information is acquired.
(13)	Mirror disk resource	<b>(P</b> )	Online	The mirror disk resource has been started.
		×	Error	The mirror disk resource has an error.
			Offline or Unknown	The mirror disk resource is stopped, or no information is acquired.
(14)	Registry synchronization		Online	The registry synchronization resource has been started.
	resource	×	Error	The registry synchronization resource has an error.
		H	Offline or Unknown	The registry synchronization resource is stopped, or no information is acquired.
(15)	Script resource		Online	The script resource has been started.
		X	Error	The script resource has an error.
			Offline or Unknown	The script resource is stopped, or no information is acquired.
(16)	Disk resource		Online	The disk resource has been started.
		X	Error	The disk resource has an error.
			Offline or Unknown	The disk resource is stopped, or no information is acquired.
(17)	Service resource		Online	The service resource has been started.
		X	Error	The service resource has an error.
			Offline or Unknown	The service resource is stopped, or no information is acquired.
(18)	Print spooler resource	<b>■</b>	Online	The print spooler resource has been started.
		X	Error	The print spooler resource has an error.
			Offline or Unknown	The print spooler resource is stopped, or no information is acquired.
(19)	Virtual computer name resource		Online	The virtual computer name resource has been started.
		×	Error	The virtual computer name resource has an error.

No.	Icon		Status	Description
		No.	Offline or Unknown	The virtual computer name resource is stopped, or no information is acquired.
(20)	Virtual IP resource		Online	The virtual IP resource has been started.
		×	Error	The virtual IP resource has an error.
		1	Offline or Unknown	The virtual IP resource is stopped, or no information is acquired.
(21)	CIFS resource		Online	The CIFS resource has been started.
		×	Error	The CIFS resource has an error.
		*	Offline or Unknown	The CIFS resource is stopped, or no information is acquired.
(22)	NAS resource	<b>(</b>	Online	The NAS resource has been started.
		$\mathbb{X}$	Error	The NAS resource has an error.
		밒	Offline or Unknown	The NAS resource is stopped, or no information is acquired.
(23)	Hybrid disk resource	<b>@</b>	Online	The hybrid disk resource has been started.
		X	Error	The hybrid disk resource has an error.
		밒	Offline or Unknown	The hybrid disk resource is stopped, or no information is acquired.
(24)	All monitor resources		Normal	All monitor resources are running normally.
		<u>€</u>	Warning	One or more monitor resources have an error, or monitoring is suspended on a server.
		×	Error	All monitor resources have errors.
			Unknown	No information is acquired.
(25)	Application monitor resource	Q	Normal	The application is running normally.
		<mark>∕</mark>	Warning	There are one or more servers with application problems, or monitoring is suspended on a server.
		×	Error	All servers have application errors.
		0	Unknown	No information is acquired.
(26)	Disk RW monitor resource		Normal	The disk is running normally.
		<b>%</b>	Warning	There are one or more servers with disk problems, or monitoring is suspended on a server.
		×	Error	All servers have disk errors.

No.	Icon		Status	Description
		Q	Unknown	No information is acquired.
(27)	Floating IP monitor resource		Normal	The floating IP address has no error.
		<del>ڳ</del>	Warning	One or more servers cannot communicate with the floating IP address, or monitoring is suspended on a server.
		×	Error	No servers can communicate with the floating IP address.
		0	Unknown	No information is acquired.
(28)	IP monitor resource	Q	Normal	The IP address of a target has no error.
			Warning	One or more servers cannot communicate with the IP address of the target, or monitoring is suspended on a server.
		×	Error	No servers can communicate with the IP address of the target.
		0	Unknown	No information is acquired.
(29)	Mirror connect monitor resource		Normal	The mirror connect is running normally.
		<b>&gt;</b>	Warning	One of the servers has mirror connect problems, or monitoring is suspended on a server.
		×	Error	A mirror connect error has occurred on both servers.
		0	Unknown	No information is acquired.
(30)	Mirror disk monitor resource		Normal	The mirror disk is running normally.
		<b>^</b>	Warning	Mirroring is now being recovered, or monitoring is suspended on a server.
		×	Error	The mirror disk has an error. Mirror recovery is needed.
		0	Unknown	No information is acquired.
(31)	NIC Link Up/Down monitor resource		Normal	The NIC of a target has no error.
		<b>&gt;</b>	Warning	One of servers has a problem with the NIC of the target, or monitoring is suspended on a server.
		×	Error	All servers have errors with the NIC of the target.
		0	Unknown	No information is acquired.
(32)	Multi target monitor resource		Normal	Multi target monitor resource is running normally.

No.	Icon		Status	Description
			Warning	Monitoring is suspended on a server, or one or more monitor resources registered in the multi target monitor resource have errors.
		×	Error	Multi target has an error.
		9	Unknown	No information is acquired.
(33)	Registry synchronization monitor resource		Normal	The registry synchronization is running normally.
	monitor resource	<b>^</b>	Warning	Monitoring is suspended on a server.
		×	Error	The registry synchronization has an error.
		9	Unknown	No information is acquired.
(34)	Disk TUR monitor resource	Q	Normal	The disk is running normally.
		<b>☆</b>	Warning	There are one or more servers with disk problems, or monitoring is suspended on a server.
		×	Error	All the servers have disk errors.
		0	Unknown	No information is acquired.
(35)	Service monitor resource		Normal	The service is running normally.
		<b>^</b>	Warning	Monitoring is suspended on a server.
		×	Error	The service has an error.
		0	Unknown	No information is acquired.
(36)	Print spooler monitor resource	(C)	Normal	The print spooler monitor is running normally.
		<b>^</b>	Warning	Monitoring is suspended on a server.
		×	Error	The print spooler has an error.
		0	Unknown	No information is acquired.
(37)	name monitor		Normal	The virtual computer name is running normally.
	resource	<b>^</b>	Warning	Monitoring is suspended on a server.
		×	Error	The virtual computer name has an error.
		0	Unknown	No information is acquired.
(38)	Virtual IP monitor		Normal	The virtual IP is running normally.

No.	Icon		Status	Description		
	resource	Ş	Warning	Monitoring is suspended on a server.		
		×	Error	The virtual IP has an error.		
		0	Unknown	No information is acquired.		
(39)	CIFS monitor resource		Normal	The CIFS is working normally.		
		<b>^</b>	Warning	Monitoring is suspended on a server.		
		×	Error	The CIFS has an error.		
		0	Unknown	No information is acquired.		
(40)	NAS monitor resource		Normal	The NAS is working normally.		
		<b>^</b>	Warning	Monitoring is suspended on a server.		
		×	Error	The NAS has an error.		
		0	Unknown	No information is acquired.		
(41)	Hybrid disk monitor resource		Normal	The Hybrid disk is working normally.		
		<b>^</b>	Warning	Mirroring is now being recovered, or monitoring is suspended on a server.		
		×	Error	The hybrid disk has an error. Mirror recovery is needed.		
		0	Unknown	No information is acquired.		
(42)	Hybrid disk TUR monitor resource	Q	Normal	The disk is working normally.		
		Warning		One of servers has a problem with the disk, or monitoring is suspended on a server.		
		×	Error	All the servers have disk errors.		
		0	Unknown	No information is acquired.		
(43)	Custom monitor resource	Q	Normal	No error is detected by monitor script.		
		<b>&gt;</b>	Warning	There is a server where monitoring is suspended, or an error has been detected in one of the servers.		
		×	Error	Monitor script has detected an error.		
		0	Unknown	No information is acquired.		
(44)	DB2 monitor resource		Normal	The DB2 is working normally.		
		<b>^</b>	Warning	Monitoring is suspended on a server.		

No.	Icon		Status	Description
		×	Error	The DB2 has an error.
		0	Unknown	No information is acquired.
(45)	FTP monitor resource		Normal	The FTP is running normally.
		<b>^</b>	Warning	Monitoring is suspended on a server.
		×	Error	The FTP has an error.
		0	Unknown	No information is acquired.
(46)	HTTP monitor resource		Normal	The HTTP is running normally.
		<b>^</b>	Warning	Monitoring is suspended on a server.
		×	Error	The HTTP has an error.
		0	Unknown	No information is acquired.
(47)	IMAP4 monitor resource	Q	Normal	The IMAP4 is running normally.
		<b>^</b>	Warning	Monitoring is suspended on a server.
		×	Error	The IMAP4 has an error.
		0	Unknown	No information is acquired.
(48)	ODBC monitor resource	Q	Normal	The ODBC is running normally.
		Ç	Warning	Monitoring is suspended on a server.
		×	Error	The ODBC has an error.
		0	Unknown	No information is acquired.
(49)	Oracle monitor resource	(C)	Normal	The Oracle monitor resource is running normally.
			Warning	Monitoring is suspended on a server.
		×	Error	The Oracle monitor resource has an error.
		0	Unknown	No information is acquired.
(50)	OracleAS monitor resource		Normal	The OracleAS monitor resource is running normally.
		<b>\$</b>	Warning	Monitoring is suspended on a server.
		×	Error	The OracleAS monitor resource has an error.
		0	Unknown	No information is acquired.

No.	Icon		Status	Description	
(51)	OfficeScan CL monitor resource	Q	Normal	OfficeScan client is running normally.	
			Warning	Monitoring is suspended on some server.	
		×	Error	OfficeScan client has an error.	
		0	Unknown	No information is acquired.	
(52)	OfficeScan SV monitor resource	Q	Normal	OfficeScan server is running normally.	
		Ş	Warning	Monitoring is suspended on some server.	
		×	Error	OfficeScan server has an error.	
		0	Unknown	No information is acquired.	
(53)	POP3 monitor resource	Ç	Normal	The POP3 monitor resource is running normally.	
		<b>^</b>	Warning	Monitoring is suspended on a server.	
		×	Error	The POP3 monitor resource has an error.	
		0	Unknown	No information is acquired.	
(54)	PostgreSQL monitor resource		Normal	The PostgreSQL is running normally.	
		<b>^</b>	Warning	Monitoring is suspended on a server.	
		×	Error	The PostgreSQL has an error.	
		0	Unknown	No information is acquired.	
(55)	SMTP monitor resource		Normal	The SMTP monitor is running smoothly.	
		<del>ڳ</del>	Warning	Monitoring is suspended on a server.	
		×	Error	The SMTP resource has an error.	
		0	Unknown	No information is acquired.	
(56)	SQL Server monitor resource	rce Normal		The SQL Server is running normally.	
		<b>^</b>	Warning	Monitoring is suspended on a server.	
		×	Error	The SQL Server has an error.	
		0	Unknown	No information is acquired.	
(57)	Tuxedo monitor		Normal	The Tuxedo is running normally.	

No.	Icon		Status	Description
	resource		Warning	Monitoring is suspended on a server.
			Error	The Tuxedo has an error.
		0	Unknown	No information is acquired.
(58)	Websphere monitor resource		Normal	The WebSphere is running normally.
			Warning	Monitoring is suspended on a server.
		×	Error	The WebSphere has an error.
		0	Unknown	No information is acquired.
(59)	Weblogic monitor resource	Q	Normal	The WebLogic is running normally.
			Warning	Monitoring is suspended on a server.
		×	Error	The WebLogic has an error.
		0	Unknown	No information is acquired.
(60)	WebOTX monitor resource	Q	Normal	The WebOTX is running normally.
		<b>^</b>	Warning	Monitoring is suspended on a server.
		×	Error	The WebOTX has an error.
		0	Unknown	No information is acquired.

### Operations from the WebManager

You can operate a cluster by right-clicking (1) Cluster, (3) Individual server or (9) All groups and choosing an operation.

#### Objects of the cluster

When you right-click the **cluster** object, the following shortcut menu is displayed.



#### ♦ Shut down

Shuts down all running servers. When you select **Shutdown**, the following dialog box is displayed for confirmation.



The server that cannot communicate with the server (all LAN heartbeat resources are stopped) connected to the WebManager does not shut down.

### ♦ Reboot

Reboots all running servers. When you select **Reboot**, the following dialog box is displayed for confirmation.



#### ◆ Service

If you select Service, Suspend Cluster, Resume Cluster, Start Cluster, Stop Cluster and Restart Manager are displayed on the shortcut menu.

### ◆ Switch Authorization

Change the authorization of the WebManager. For this operation, see "Switch authorization of the WebManager" on page 75.


### Server object

When you right-click the **servers** object, the following shortcut menu is displayed.




### ♦ Mirror Disk List

If you select this operation, the following dialog box of the mirror disk list is displayed, and the list of all mirror disk resources and hybrid disk resources is displayed.



### • Detail (Starts Mirror Disk Helper)


Starts the **Mirror Disk Helper** dialog box for the selected mirror disk resource/hybrid disk resource.



For information on using the Mirror Disk Helper, see "Mirror disk helper" on page 59.

### ◆ Error Mirror Disk List

Lists mirror disk resources and hybrid disk resources with an error in the dialog box.



If there is a mirror disk with an error listed below in the cluster, the above dialog box will be displayed automatically.


The description provides what you should do for the error.

Error type	Description
Mirror Error	Mirror recovery or forced mirror recovery is necessary. Run the Mirror Helper and perform mirror recovery.
Mirror Error (Single Server Run)	Only one server is running, and the latest data of a mirror disk is not completed. To continue the operation, run the Mirror Helper and execute mirror recovery. Be careful since the server that is currently running will be the latest data when the mirror recovery is executed.

When you select **Details**, the Mirror Disk Helper is activated.

### Individual server objects

When you right-click an individual server object, the following shortcut menu is displayed.



### ♦ Shut down

Shuts down the selected server. When you select this operation, the following dialog box is displayed for confirmation.



### ♦ Reboot

Reboots the selected server. When you select this operation, the following dialog box is displayed for confirmation.



#### ◆ Recover

Recovers the selected server. When you select this operation, the following dialog box is displayed for confirmation.



### ◆ Service

Starts and stop the selected service. If you select this operation, the following dialog box is displayed for confirmation.



### ◆ Reset Statistical Data

Resets the selected statistical data of the server. If you select this operation, the following dialog box is displayed for confirmation.



### ◆ CPU Frequency Settings

Configures the CPU frequency control function of the selected server.

• Highest Frequency
Sets the CPU frequency to the highest.



• Lowest Frequency
Lowers the frequency to turn it to power-saving mode.




Auto
 Restores the CPU frequency control to the control by ExpressCluster.



This function cannot be used when the checkbox of "Use CPU Frequency Control" is not selected in the power saving settings in cluster properties.

### Individual group objects

When you right-click an individual group object, the following shortcut menu is displayed.



◆ Start (enabled only when the group is stopped)

Starts up the selected group. The dialog box for choosing a server that starts up the selected group is displayed.



◆ Stop (enabled only when the group has been started up or when it has an error)

Stops the selected group. When you select this operation, the following dialog box is displayed for confirmation.




♦ Move (enabled only when the group has been started up)

Moves the selected group. The dialog box for choosing a server to which you want to move the selected group is displayed.



### Group resource objects (Except mirror disk resources/hybrid disk resources)

When you right-click a group resource object, the following shortcut menu is displayed.



◆ Start (enabled only when the group is stopped)

Starts up the selected group resource. When you selected this operation, the following dialog box is displayed for confirmation.




◆ Stop (enabled only when the group has been started up or when it has an error)

Stops the selected group resource. When you selected this operation, the following dialog box is displayed for confirmation.



### Objects of mirror disk resource and hybrid disk resource

When you right-click a mirror disk resource object, the following shortcut menu is displayed.



#### ◆ Details

Starts up the Mirror Disk Helper for the selected mirror disk resource/hybrid disk resource, and the following dialog box for the Mirror Disk Helper is displayed.



For information on using the Mirror Disk Helper, see "Mirror disk helper" on page 59.


### Monitor resource objects

When you right-click a monitor resource object, the following shortcut menu is displayed.




• Resume (enabled when the resource is stopped temporarily)

Resumes a selected monitor resource. The dialog box for choosing the server on which the selected monitor resource is resumed.



◆ Suspend (enabled when the resource is monitoring)

Resumes the selected monitor resource. The dialog box for choosing the server on which the selected monitor resource is stopped temporarily.



# Checking the cluster status by the WebManager list view

The detailed information on the selected object in the tree view of the WebManager can be displayed in the list view.

### To display information on the whole cluster

- **1.** Start the WebManager. (http://FIP\_address\_for\_the\_WebManager\_group:port\_number (default value is 29003))
- 2. In this tree view, click the object icon for the cluster. In the list view in the right pane of the window, Name and Comment are displayed.
- 3. In the following dialog box, click the **Details** button to display the following information.

Alert Service Mirror Disk Disk Aut	to Recovery Power Saving		
Heartbeat I/F Timeout Port Nu	ımber Recovery Delay Warning		
Properties	Value		
Server Sync Wait Time	300		
Heartbeat Timeout	30000		
Heartbeat Interval	3000		
Server Internal Timeout	180		
Timeout Ratio	1		

Server Sync Wait Time: Time to wait for the other servers to start up (in seconds)

Heartbeat Timeout: Heartbeat timeout (in milliseconds)

Heartbeat Interval: The interval for sending heartbeats (milliseconds)
Server Internal Timeout: Internal communication timeout (in seconds)

Timeout Ratio: Current timeout ratio

Alert Service Mirror Disk Disk Au	uto Recovery Power Saving			
Heartbeat I/F Timeout Port N	umber Recovery Delay Warning			
Properties	Value			
Server Internal Port Number	29001			
Data Transfer Port Number	29002			
Kernel Mode Heartbeat Port Number	29106			
Client Service Port Number	29007			
WebManager HTTP Port Number	29003			
Alert Sync Port Number	29003			
Disk Agent Port Number	29004			
Mirror Driver Port Number	29005			

Server Internal Port Number: Port number for internal communication

Data Transfer Port Number: Port number for data transfer Heartbeat Port Number: Port number for heartbeat

Kernel Mode Heartbeat Port Number: Port number for kernel-mode heartbeat Client Service Port Number: Port number for client service

WebManager HTTP Port Number:
Alert Sync Port Number:
Port number for WebManager
Port number for alert synchronization

Disk Agent Port Number Port number for disk agent

Mirror Driver Port Number Port number for mirror driver (Only when

Replicator/Replicator DR is used)

Alert Service Mirror Disk Disk Au	to Recovery Power Saving		
Heartbeat I/F Timeout Port No	ımber Recovery Delay Warning		
Properties	Value		
Max Reboot Count	0		
Max Reboot Count Reset Time	0		
Use Forced Stop	Off		
Forced Stop Action	BMC Power Off		
Forced Stop Timeout (sec)	3		

Max Reboot Count: Maximum reboots count

Max Reboot Count Reset Time Time to reset maximum reboot count (in seconds)
Use Forced Stop Whether or not to perform the forced stop function

Forced Stop Action Action of forced stop function

Forced Stop Timeout Wait time until activation of failover group starts after forced

stop has been performed (in seconds)

Alert Service Mirror D		uto Recove Iumber	Power Sa	aving Delay Warning
Propertie	S			Value
Heartbeat Delay Warning		80		
Monitor Delay Warning		80		
COM Delay Warning		80		

Heartbeat Delay Warning: Heartbeat delay warning (%) Monitor Delay Warning: Monitor delay warning (%)

COM Delay Warning COM communication delay warning (%)

Alert Service	Mirror Disk	Disk Au	to Recove	ry	Power Sa	ving	
Heartbeat I/F	Timeout	Port N	umber	F	Recovery	De	elay Warning
Properties						Valu	ie
Auto Recovery			On				

Auto Recovery: The setting whether server recovery is automatically

performed after cluster server is rebooted from "Suspension

(Isolated)."

Alert Service	Mirror Disk [	Disk Aut	o Recove	ry Power Sa	ving
Heartbeat I/F	Timeout	Port Nu	ımber	Recovery	Delay Warning
F				Value	
Server Down Notif		On			
Cast Method		Unicast			

Server Down Notification

When you set this to Enable, one server is allowed to tell the other servers that it is being shut down by the commands from WebManager or command line, so that a failover occurs independently of the heartbeat settings.

### Note:

Even if **Server Down Notification** is set to **On**, failover is performed after heartbeat time-out when shutdown is performed with a method other than WebManager or a command.

Cast Method This is the setting for the method to send a heartbeat

(uni-cast/broadcast). When the IP address of the heartbeat I/F

is IPv6. the broadcast cannot be used.

### Only when Replicator/Replicator DR is used:

Alert Service	Mirror Disk	Disk /	luto Recove	ry	Power Sa	ving	
Heartbeat I/F	Timeout	Port	Number		Recovery	D	elay Warning
Properties				Value			
Auto First Mirror	Construction		On				
Auto Mirror Reco	very		On				
Mirror Disk Disc	onnection Retry	Threshold	l 10				
Mirror Disk Disc	onnection Retry	Interval	3				
Mirror Disk Disc	onnection Final	Action	Disconne	ect f	orcefully		
Auto First Mirro	r Construction		Whet const			form	auto mirror initial
Auto Mirror Rec	overy:		Whet	her	or not to per	form	auto mirror recove
Mirror Disk Disc	connection Retry	y Thresholo	d Mirro	or di	sk disconne	ction	retry threshold
Mirror Disk Disconnection Retry Interval			Mirro	Mirror Disk Disconnection Retry Interval			
			(in se	con	ds)		
Mirror Disk Disconnection Final Action			The f	inal	action at mi	rror c	lisk disconnection
Alert Service	Mirror Disk	Disk (	Auto Recove	n/	Power Sa	vina	1

		_	to Recove		V
Heartbeat I/F	Timeout	Port Nu	ımber	Recovery	Delay Warning
Pro		Value			
Shared Disk Discor	nnection Retry	Thresho	10		
Shared Disk Disconnection Retry Interval			3		
Shared Disk Disconnection Final Action Disconnect forcefully					
Shared Disk Disconr	nection Retry T	hreshold	Share	d disk disconne	ction retry threshold
Shared Disk Disconnection Retry Interval			Shared disk disconnection retry interval (in		
			second	ds)	
Shared Disk Disconnection Final Action Shared disk disconnection final action					

Alert Service Mirror Disk Disk Auto Recovery Power Saving					
Port Nu	ımber	Recovery	Delay Warning		
Properties			Value		
E-mail Address					
Use Network Warning Light					
Use Chassis Identify					
	Off				
	Port Nu	Auto Recove Port Number  Off Off Off	Port Number Recovery Off Off		

E-mail Address
Use Network Warning
Use Chassis Identify
Enable Alert Setting

Alert mail address
Whether or not to use network warning light
Whether or not to use the chassis identify association function
Whether or not to enable setting

Alert Service	Mirror Disk	Disk .	Auto Recove	ery Power S	aving	
Heartbeat I/F	Timeout	Port	Number	Recovery	De	elay Warning
Properties					Valu	ie
Use CPU Frequency Control			On			

Use CPU Frequency Control

Whether or not to use CPU frequency control

## Checking the whole status of the server in the WebManager list view

**1.** Start the WebManager. (http://FIP\_address\_for\_the\_WebManager\_group:port\_number (default value is 29003))

2. In the list view, select the object icon In the right pane of the window, Server Name, Type (master server or other server), and Status.

## Checking the status of individual server in the WebManager list view

- **1.** Start the WebManager. (http://FIP\_address\_for\_the\_WebManager\_group:port\_number (default value is 29003))
- 2. If the object of a server is selected in the tree view, Server Name, Comment, Version, Product, Internal Version, Install Path, IP address and Status of the server, the Heartbeat Name and Status of heartbeat status and Network partition resolution resource name and Status of the network partition resolution resource status are displayed.

Server Name: server2	Details
Properties	Value
Name	server2
Comment	
Product	EXPRESSCLUSTER X 2.0 for Windows
Internal Version	10.00
Install Path	C:\Program Files\EXPRESSCLUSTER
IP Address	192.168.16.145
Status	Online

Heartbeat Name		Status
lankhb1	Normal	
lankhb2	Normal	

Network Partition Resolution Status	
Network Partition Resolution Name	Status
disknp1	Normal
comnp1	Normal

Server Name: Server name

Comment: Comment for the server
Product Name of the product
Internal Version: Internal version

Install Path: Install path of ExpressCluster IP Address: IP address of public LAN Status: Status of the server

Heartbeat Name: Heartbeat resource name Status: Heartbeat resource status

Network partition resolution name: Network partition resolution resource name Status

Network partition resolution resource status

**3.** Click **Details** to display the following in the dialog box.

Properties	Value
Network Warning Light IP Address	
BMC IP Address	
CPU Frequency Status	high

Network Warning Light IP Address IP address of network warning light

BMC IP address BMC IP address

**CPU Frequency Status** 


Current setting status of CPU frequency control

## Checking the status of the whole monitor in the WebManager list view

- **1.** Start the WebManager. (http://FIP\_address\_for\_the\_WebManager\_group:port\_number (default value is 29003))
- 2. In the tree view, select the object icon . The **Monitor Name** and **Status** are displayed in the list view.

### Checking alerts using the WebManager

You can view alerts in the bottom part of the WebManager.



For meanings of alert messages, see Chapter 12, "Error messages." For information about searching alert messages, see "Searching for an alert by using the WebManager" in this chapter.

### Alert view fields

The meaning of each of the fields in the alert view of the WebManager are the following.

(1) Alert type icon

Alert type	Description
(i)	Informational message
<u> </u>	Warning message
*	Error message

(2) Alrert received time

The time the alert was received. The time in the server to which the WebManager connects is applied.

(3) Alert sent time

The time the alert was sent from a server. The time in the alert sender server is used.

(4) Alert sender server

The name of a server that sent the alert.

(5) Alert sender module

The name of a module that sent the alert.

Module type	Category
pm	ExpressCluster in general
rc	Group/resource related
rm	Monitor resource related
nm	Heartbeat resource related
lankhb	Kernel mode LAN heartbeat resource
disknp	Disk network partition resolution resource
fip	Floating IP resource
vcom	Virtual computer resource
vip	Virtual IP resource
cifs	CIFS resource
diskw	Disk RW resource monitoring
mdw	Mirror disk monitor resource
sdw	Disk TUR monitoring
hdtw	Hybrid disk TUR monitor resource
diskagent	Disk agent related
sdfunc	Disk function related
mdadmn	Mirror disk related
hdadmn	Hybrid disk related
armcmd	Compatible commands
event	Event log
Icns	License related
logcmd	Message output command
ptun	Parameter tuning related
dn1000s	Network warning light alert related
ptun	Mail alert related

### (6) Event ID


The event ID number set to each alert.

### (7) Alert message

The alert messages.

### Alert view operation

By clicking an item on the bar showing name of each field, you can change the alert order.




Whenever you select an item, the  $\triangle$  or  $\nabla$  mark is displayed in each field.


Mark	Purpose
	Sorts alerts in the ascending order of the selected field.
V	Sorts alerts in the descending order of the selected field.

By default, alerts are displayed in the **Time** descending order.


When you right-click this bar, the following pop-up window is displayed so that you can select the items to be displayed. All items are selected by default.



When you double-click the displayed alert, the following window is displayed where you can check the detail of the alert,



When you right-click the alert, the following pop-up window is displayed where you can select the type of the alert to be displayed. All items are selected by default.




### Mirror disk helper


### Overview of the mirror disk helper

The Mirror Disk Helper is a tool to help the recovery of mirror disk/hybrid disk. It is used by starting up from the WebManager. The following shows the layout of the Mirror Disk Helper.

For mirror disk resource



For hybrid disk resource



The Mirror Disk Helper can be started by the mirror disk list or a mirror disk resource/hybrid disk resource of a group.

The following is the description of the each field of the Mirror Disk Helper.

(1) Resource name

Displays the name of the mirror disk resource/hybrid disk resource.

### (2) Execute

When you click **Execute**, mirror recovery is started as displayed in the following dialog box. If there is any difference between the mirror disks in both servers, the mirror recovery is started.



If there is no difference between the mirror disks in both servers, the following dialog box is displayed.




If you click **OK**, full copy of the mirror begins.

If auto mirror recovery is enabled, mirror recovery begins automatically. However, mirror recovery does not begin automatically if there is no difference between both servers, or if there are errors in mirror disks in both servers.

### (3) Detailed information

When you click **Details**, detailed information is displayed.

#### For mirror disk resource



Server Name: Server name

Diff Status: Difference status of the mirror disk device

Active: Active status of the mirror disk device on the server

Media Error: Media error of the mirror disk resource


Mirror Break Occurred at: Mirror break time

Last Updated: The time that the data was updated the last time

Diff Percent: Difference rate

NMP Size: The data partition size as recognized by OS.

Disk Size: The physical size of data partition.



### For hybrid disk resource

Server Group Name Server group name

Current Server Name

Name of the server that uploads and manages the disks in the

server group.

Diff Status: Difference status of the mirror disk device

Activation Status: Active status of the mirror disk device on the server

Mirror Break Occurred at: Mirror break time

Last Updated: The time that the data was updated the last time

Diff Percent Difference rate

Disk Size: The physical size of data partition

**Last Data Update Time** is displayed when only one of the servers is updated. **Mirror Break Time** is displayed when mirror connect is disconnected.

### (4) Mirroring disk status

The following table shows the mirroring disk status of servers:

You can select what to perform for the mirror disk by clicking the icon.


Icon	Mirroring disk status	Mirror color*
	Mirroring status is normal. The server is inactive.	Green
	Mirroring status is normal. The server is active.	Green
<b>⊕</b>	Mirror recovery or forced mirror recovery is underway. The server is inactive.	Yellow
<b>4</b>	Mirror recovery or forced mirror recovery is underway. The server is active.	Yellow
	There might be a difference, but it has not been determined which has the latest information. Mirror recovery is required.	Orange
	The server has an error. Mirror recovery is required.	Red
	The server is stopped or its status is unknown. Information on the server status cannot be acquired.	Gray
	Both systems are active.	Blue
	Cluster partition has an error.	Black

<sup>\*</sup> To see the mirror color, run the clpmdstat command.

### (5) Progress bar

When performing the mirror recovery, the progress bar shows an arrow from a source server with the latest data to a copy destination server.

How far the mirror recovery has progressed and expected time required for copying are displayed in the progress bar.



### (6) Current server (only hybrid disk resource)


Current server displays the current server that updates and manages the disks. You can check the status of each member server of the server group by clicking the drop-down arrow. The current server is represented in the bold font. The server represented in gray font is in the down state.

When performing mirror recovery or cancelling access restrictions, you can select a server from the list shown by clicking the drop-down arrow to change a current server.

### Recovering a mirror (forcefully)

1. Mirror recovery

If there is a difference between the mirror disks on both servers:




If there is a difference between the mirror disks on both servers, and one of the servers has an error, the progress bar direction is fixed. When you click **Execute**, mirror recovery starts.

When you click **Execute**, mirror recovery starts. If any group is active, the server with the active group becomes the source server. When it is possible to recover differences, only the difference is recovered. If it is impossible to recover differences, whole partition area is recovered.

### If there is no difference between the mirror disks on both servers:


If there is no difference, full copy of the mirror is performed.



If there is no difference between the mirror disks of both servers, and both servers are running normally, the progress bar is displayed. When you click **Execute**, mirror recovery starts.

### If the status of both servers is Error:

If both servers have errors, click **Details** to determine a source server. When you click **Details**, the following detailed information is displayed.





Check the **Last Data Update Time**, and choose a server with the latest data as the source server. Note that the time you see here is of the OS.

If you select an icon whose status is mirrored disk as the source, the progress bar is displayed. Click **Execute** to start mirror recovery.

2. Forced mirror recovery only for a single server

When one server has an error while the other is in the unknown status or stopped, the Mirror Disk Helper is displayed.






When you click the icon of the server with an error, the following is displayed:

When you click **Execute**, forced mirror recovery of only one server starts.

### **Stopping mirror recovery**

What is similar to the following is displayed during mirror recovery:



When you click the icon of the server where data will be copied to or from, the following is displayed:



When you click **Execute**, the following dialog box is displayed. If you click **OK**, mirror recovery stops. The server where data is copied from becomes normal status and copied to become error status:



### **Canceling access restriction**

Canceling the access restriction can be performed only when the status of server is error. When the status of one server is normal and other server is error, the following is displayed:





When you double-click the icon of the server with error, the following is displayed:

When you click Execute, access restriction is cancelled in the server with an error.

To perform mirror recovery, click the icon of the server where access restriction is cancelled, perform access restriction, and follow the procedures in "Recovering a mirror (forcefully)."

#### Note

When the Auto Mirror Recovery is enabled and one of the servers is operating normally, it is necessary to disable Auto Mirror Recovery in advance or suspend the mirror disk monitor resource or hybrid disk monitor resource so that Auto Mirror Recovery does not operate when the access restriction is cancelled in the server that is abnormal.

### Manually stopping and starting the WebManager

Once ExpressCluster is installed, the WebManager automatically starts and stops along with the operating system.

If you wish to stop and start the WebManager specifically, just stop or start the service for the WebManager from the Services console of Administrative Tools.

### When you do not want to use the WebManager

If you do not want to use the WebManager for security reasons, change the settings of **Services** of **Management Tool** of your OS or that of the Builder not to start the WebManager.

For the settings of **Services** of **Administrative Tool**, change the "**Startup Type**" of the "ExpressCluster Manager" service into "Manual".

The WebManager can be configured on the **WebManager** tab in **Cluster Properties** of the Builder. For information on how to configure and reflect the settings, see "**WebManager tab**" on page 129.

# Setting limitations on the connection and operation of the WebManager

The limitation in connection and operation of the WebManager can be configured in **Cluster Properties** in the Builder. For details, see Chapter 3, "Functions of the Builder."

### Type of limitation

There are two ways to set usage limitations:

- Limiting the access by using client IP addresses
- ◆ Limiting the operation by using a password

### Limiting the access by using client IP addresses

This function limits clients who can access the WebManager and operations on the WebManager by using client IP addresses.

Add IP addresses to **IP Addresses of the Accessible Clients** on the **WebManager** tab in the **Cluster Properties** of the Builder. See "WebManager tab" on page 129.

When setting the limitation of the connection of the WebManager, if you attempt to access to the WebManager from the IP address that is not added to **IP Addresses of the Accessible Clients**, the following error messages are displayed.

Example: when using the Internet Explorer



The following **Reference Only** message is displayed to the WebManager that is connected from the client registered to limit the operation.



If you limit operations, you cannot perform the following operations from the WebManager.


- Shutdown and shutdown reboot of a cluster
- ◆ Shutdown and shutdown reboot of servers
- ◆ Starting, stopping, and moving of groups
- Operation using the Mirror Disk Helper (only when the Replicator/Replicator DR is used)
- Starting up Builder

#### The limitation by using a password

This function limits viewing and operations on the WebManager by using a password.

To configure this limitation: in **Cluster Properties** of the Builder, click the **WebManager** tab and then **Control connection by using password**. See "WebManager tab" on page 129 for detailed information.

Once password limitation of the WebManager is set, the following authorization dialog box is displayed when trying to access the WebManager by setting a password.



You can log on to the WebManager by selecting **Operation Mode** or **Reference Only** in **Authorization** and entering a correct password.

- ♦ The authorization dialog box is not displayed when the password limitation is not configured (you can log on to the WebManager without authorization).
- You cannot log on to the WebManager if you enter a wrong password three consecutive times.

When you log on with a reference-only authorization, the following **Reference Only** message is displayed.



The following operations cannot be performed from the WebManager when operations are limited.

- ♦ Shutdown and shutdown reboot of a cluster
- Shutdown and shutdown reboot of servers
- ◆ Starting, stopping, and moving of groups
- Operation using the Mirror Disk Helper (only when the Replicator/Replicator DR is used)

For the information on switching the authorization after log on and/or log out, "Switch authorization of the WebManager" on page 75.

#### Combination of the IP address and password


The operational limitations when using both IP addresses and passwords are the following:

	Password limitation			
Client IP address limitation	Operable mode	Reference only	Unable to operate/view (authorization failed)	
Operable Mode	Operable mode	Reference only	Unavailable	
Reference Only	Reference only*	Reference only	Unavailable	
Cannot Access	Cannot access	Cannot access	Cannot access	

<sup>\*</sup> Authorization cannot be selected.

## Switch authorization of the WebManager

The chart below describes the flow of accessing the WebManager and switching authorization.



1. Login to the WebManager

The log on authorization dialog box is displayed when a password for operation mode or reference only is set. You can log on to the WebManager by selecting the authorization of either **Operation Mode** or **Reference Only** and entering the correct password.

- Switch the authorization from the reference only screen to the operation mode screen
   The dialog box for password authorization is displayed. You can log on by entering the correct password. When password limitation is not configured, log on without entering a password.
- Switch the authorization from the operation screen to the reference only screen
   Authorization can be switched without authentication. You can do so even when the
   password limitation is configured.
- 4. Login when a password for both operation mode and reference only is not set Log in by following the client IP limitation. If the client IP limitation is not configured, log on to the WebManager whose authorization is in the operation mode. In this case, you cannot switch the authorization to reference only.

## Operating a cluster by using the WebManager

#### Cluster shutdown and cluster shutdown reboot

For the information on performing cluster shutdown and cluster shutdown reboot from the WebManager, see "Objects of the cluster."

## Mirror disk resource and hybrid disk resource

For the information on how to use the mirror disks and Mirror Disk Helper from the WebManager, see "Individual server objects" "Objects of mirror disk resource/hybrid disk resource"

## **Recovering servers**

When **Off** is selected in **Auto Return** in **Auto Recovery** tab of the **Properties** in the Builder, if a server is shut down or rebooted without using Cluster Shutdown command, the server is started in the status of **Suspension** (**isolated**). A server in this status does not run as a part of a cluster system. Thus you need to return the server to the cluster system after you finished the necessary maintenance work to the server. For the information on how to return a server to a cluster by using WebManager, see "Individual server"

## Shutting down and rebooting an individual server

For the information on how to shut down and reboot an individual server from the WebManager, refer to "Individual server objects".

## Starting, stopping, and moving an individual group

For the information on how to start, stop and move an individual group from the WebManger, refer to "Individual group objects."

## Starting and stopping a group resource

For the information on how to start and stop a group resource from the WebManager, refer to "Group resource objects."

## Resuming and suspending a monitor resource

For the information on how to resume and suspend a monitor resource, refer to "Monitor resource objects."

## **Limitations of the WebManager**

- ◆ Information displayed by the WebManager does not always reflect the latest status. To acquire the latest information, click the **Reload** button.
- ◆ If a server fails while the WebManager is acquiring information, the information acquisition fails, which may result in the failure to show some objects.
  You can either wait until the next auto refresh starts or click the **Reload** button to acquire the latest information.
- ◆ The ExpressCluster logs cannot be collected from two or more WebManagers simultaneously.
- ◆ If you work on the WebManager when no connectivity is established, it may take a while to regain control.
- ♦ While the mouse pointer is the hourglass which indicates that the OS is processing something, moving the cursor outside the browser may return to the arrow icon even if the process is still underway.
- ◆ If a proxy server is used, configure the proxy server so that the port number of the WebManager can be relayed.
- When you update ExpressCluster, close the browser. Clear the cache of Java and restart the browser.
- While the pointer in the WebManager appears an hourglass and you click Start Builder multiple times, the Builder may freeze. Do not operate the WebManager while the pointer appears as an hourglass.

## Error messages on the WebManager

The following is a list of error messages displayed when using the WebManager.

Level	Message	Cause	Solution
Info	Alert Service is	The status of the alert	-
	already started.	service became normal.	
Error	Alert service is	Starting the alert service	Check the configuration
	inactive.	failed.	of alert-related modules.
Error	Could not start the	No status can be acquired	Try reloading the status
	group because necessary responses	because the ExpressCluster is now being started up.	later.
	have not been made.	is now being started up.	
Error	Could not connect to	Connecting the	Check if the destination
	the server.	WebManager to the	server is running.
		ExpressCluster server failed.	3
Error	Connection Timeout.	Internal timeout occurred.	Internal timeout may
			occur when a
			time-consuming task is
			performed. Check the
			status after the timeout and if there is no
			problem, operations can
			be continued.
Error	Connection is	The connection between the	Check if the connection
	terminated.	WebManager and the	destination server has
		ExpressCluster is	failed.
		disconnected.	
Error	Could not activate	Failed to start some	Solve the problem that
	some resources.	resources under the group.	caused the resource
			error.
			See the alert log for the detailed information on
			the error.
Error	Could not deactivate	Failed to stop some	Solve the problem that
	some resources.	resources under the group.	caused a resource error.
			For details on the error,
			see the alert log.
Error	Failed to collect logs	Failed to collect logs.	Retry log collection.
	from the server.	Some servers may have	If logs from a certain
		been shut down during the log collection. Some servers	server cannot be
		may not be able to be	collected, run the clplogcc command on
		accessed due to error.	the server to collect logs.
Error	Failed to connect to	Failed to connect to the	Check if the
	server({0} : {1}).	WebManager.	ExpressCluster Web
			Alert service is running
			on the server.
Error	Failed to find group	Failed to detect the server	The server status may
	online server.	whose group is online.	have changed during the
			operation. Reload the
Error	Failed to get data for	Failed to acquire the cluster	status. Check if ExpressCluster
L1101	the cluster tree view	configuration.	is running on the server
	from the server.	- comgaration.	by using a command.
Error	Failed to get the latest	1) The alertlog.alt file does	Temporarily store all
	alert log.	not exist or is corrupted.	the files under the
	-	2) The maximum number of	/installation_path/alert/lo
		the alert viewer records in	g on the server, and then
		the cluster configuration	restart the alert
		data is over the limitation.	synchronization service.
		(Up to 999)	2) Check the maximum

Level	Message	Cause	Solution
			number of the alert viewer records set in the Builder.
Error	Failed to get property from the server.	Failed to acquire a cluster property value.	Run a command on the server to check if ExpressCluster is running.
Error	Failed to search the alert logs.	Failed to open alert log files on a server.	Temporarily store the files under the /installation_path/alert/lo g on the server, and then restart the alert synchronization service.
Error	The response content is invalid.	Connection to the server is disconnected.	Check the server operating status and network connectivity.
Error	Failed to move group "Group Name" to server "Server Name".	Moving the group failed. [Group Name] group_name [Server Name] server_name	Solve the problem that failed to move the group. For the detailed information on the error, see the alert log.
Error	The group is already started.	The target group has already been started up. Other manager or command on the server may have performed operations to the same group.	Try reloading the group status later to update it, and then perform operations to the group.
Error	Group is already stopped.	The group which is the target of the operation has already been stopped. Other manager or command on the server may have performed operations to the same group.	
Error	Group is updating its status.	The status of the target group is changing. Other manager or command on the server may have performed operations to the same group.	
Error	Internal Error	An internal error of the WebManager occurred.	Perform reloading. If the same error occurs even after reloading, restart the ExpressCluster Web Alert service.
Error	Invalid configuration data.	Failed to acquire the cluster configuration data.	Check the information on the cluster configuration.
Error	Invalid group name.	An internal error of the WebManager occurred.	Perform reloading. If the error occurs even after reloading, restart the ExpressCluster Web Alert service.
Error	Invalid group name or server name.	An internal error of the WebManager occurred.	
Error	Invalid parameter.	An internal error of the WebManager occurred.	
Error	Invalid server name.	An internal error of the WebManager occurred.	_
Error	An error occurred in server or group operation.	Some operations failed.	Run a command to check the server status. If there is no problem, operations can be

Level	Message	Cause	Solution
			continued.
Error	Operatable group does not exist.	The operation to the group failed.	Solve the problem that caused the failure of the operation to the group. For the detailed information on the error, see the alert log.
Error	Enter the number of alert logs displayed on each page.	The number of the alert log filter result to be displayed (for example, the number of logs in a window) is not set.	Specify the number of the alert log filter result to be displayed.
Error	Enter the event ID.	The ID for alert log search is not set.	Specify the ID for alert log search.
Error	Enter the module name.	The name of the module for the alert log search is not set.	Specify the name of a module for the alert log search.
Error	Enter the number of searches.	The number of alert logs to be searched is not set.	Specify the number of alert logs to be searched for.
Error	Enter the page number.	The page to show the results of the alert log research is not set.	Specify the page to show the results of the alert log research.
Error	Enter the server name.	The name of a server for alert log search is not set.	Specify the name of the server to be searched for.
Error	The selected server is invalid.	The server specified as the destination for moving the group is invalid.	Wait for a while to perform reloading to update the group status, and then perform the operation to the group.
Error	Specified server is not active.	The server that initiated the operation is not active.	Wait for a while to perform reloading to update the group, and then perform the operation.
Warning	The cluster tree obtained from server may not be completed.	An error occurred while acquiring the server status.	Try reloading later.
Error	The number of alert logs per page you have entered is not in the specified range (1~{0}).	The specified number of alert log filter results displayed per page is out of the range.	Specify a value between 1 and 300.
Error	The value in "To" is incorrect.	The time specified for end of alert log search is invalid.	Set a correct time.
Error	Event ID entered is less than 1.	The ID set for alert log search is smaller than one.	Specify a value of 1 or greater.
Error	There are no groups that can be started.	Failed to start up a group.	Solve the problem that caused the failure of the operation to the group. For the detailed information on the error, see the alert log.
Error	There are no groups that can be stopped.	Failed to stop the group.	Solve the problem that caused the failure of the operation to the group. For details on the error, see the alert log.
Error	There are groups that failed to start.	Some operations failed.	Run a command to check the server status. If there is no problem,

Level Message		Cause	Solution
			operations can be continued.
Error	There are groups that failed to stop.	Some operations have failed.	Run a command to check the server status. If there is no problem, operations can be continued.
Warning	The number of searches entered is less than 1.	The ID set for alert log search is smaller than one.	Specify a value of 1 or greater.
Error	Page number entered is less than 1.	The number of pages specified for the alert log search is smaller than one.	Specify a value of 1 or greater.
Error	The page number entered is greater than the total page number.	The number of pages specified for alert log search is greater than the total page number.	Specify the number that is smaller than the total page number.
Warning	The properties got from server may not be completed.	Failed to acquire some information.	Try reloading later.
Error	There are servers that failed to stop.	There is a server that may have failed to shut down the cluster.	Check if the server is down. If it is not down, check that ExpressCluster is running.
Error	The value in "From" is incorrect. Enter the correct value.	The time set for start of alert log search is invalid.	Set a correct time.
Error	The value set in "From" is later than the value in "To".	The time set for start of the alert log search is later than the time set for end.	Set a correct time.
Info	The total number of pages has been changed. The server alert log will be updated.	The number of total pages of alert log filter results is updated.  New alerts may have been issued while the search results were being displayed.	To reflect added alerts to the search results, close the window displaying the search results and perform search again.
Error	Failed to get mirror disk list from server.	An internal error of the Disk Agent occurred. Communication from the WebManager server to the ExpressCluster Web Alert service failed. The process on the server timed out.	Make sure that the Disk Agent is working. If the Disk Agent is not started, reboot the server.
Error	Failed to get mirror status.	The Disk Agent failed to acquire mirror disk status. An internal error of the Disk Agent occurred. Communication from the ExpressCluster Web Alert service to the Disk Agent has failed. The process in the server timed out.	Check if the Disk Agent is active. If the Disk Agent is not started, reboot the server.
Error	Failed to recover the mirror.	An error occurred while performing mirror recovery.	Make sure that the Disk Agent is operating. If the Disk Agent is not started, restart the server.
Error	Detected disk error while recovering the mirror.	A disk error was detected during the mirror recovery.	Run the clpmdstatmirror command to check disk error status

Level	Message	Cause	Solution	
			on each server.	
Error	Failed to recover the mirror since mirror status has changed.	Mirror recovery failed because the mirror status is changed after the Mirror Disk Helper dialog box was displayed.	Close this error message dialog box, and the information will be updated.	
Confirmation	Data on two disks are identical. Are you sure to execute a mirror recovery?	The mirror disks on both servers have no difference. Do you want to continue mirror recovery?	-	
Confirmation	{0} is recovering now. Are you sure to stop?	Do you want to stop mirror recovery?	-	
Error	Failed to stop recovery.	Failed to stop the mirror recovery.	The server may be heavily loaded. Start up the Mirror Disk Helper again.	
Error	Failed to get recovery status.	Acquiring information on the progress of mirror recovery failed.	The server may be heavily loaded. Start up the Mirror Disk Helper again.	
Error	The local applet version does not match the server's. Close the browser and clear the applet cache.	A mismatch between the Java applet and the server occurred because the Java cache remains.	Exit the browser. Clear the cache of Java and restart the browser.	
Error	Failed to recover since NMP size of "{0}" is smaller than "{1}".	Data partition size of the source server is larger than that of the destination server when recovering a mirror. The recovery is stopped. Initial mirror may not have been configured properly.	Specify a server as a source whose data partition size is smaller.	
Error	Failed to get server list.	Failed to get a server list.	Check if there are many log collection operations. Retry later.	
Error	Server is collecting logs. Try again after log collection is completed.	The server is collecting logs.	Try again after other log collections are completed.	
Error	Failed to collect logs from the server.	An error occurred while collecting logs.	Check the result in dialog box showing the progress of log collection (See "Collecting logs (clplogcc command)").	
Error	Failed to Login (Internal error)	An internal error occurred when logging on to the WebManager.	Try logging on to the WebManager again. Start the ExpressCluster Web Alert service if the error still occurs.	
Error	Failed to login.	Incorrect password was entered three consecutive times.	Try logging on to the WebManager again with a correct password.	
Error	Incorrect password.			
Error	Authorization failed.			
Error	Authorization failed. (Internal error.)	An internal error occurred when accessing to the WebManager.	Try logging on to the WebManager again. Reboot the	

Level	Message	Cause	Solution
			ExpressCluster Web Alert service if the error still occurs.
Error	Failed to connect to the server.	Failed to communicate with the WebManager.	Check if the ExpressCluster Web Alert service is working on the server. Check if connecting to the server can be performed successfully.
Error	Failed to get the list of mirror disk error.	Disk Agent failed to get the information on the mirror disk. Internal error of the Disk Agent occurred. The access to the Disk Agent from the ExpressCluster Web Alert service failed. The processing timed out on the server.	Check if the Disk Agent is operating. If the Disk Agent is not operating, restart the server.
Error	Failed to get the data for the cluster tree view from the server.	Failed to get the cluster data of the destination server. Failed to get all cluster data in the cluster tree view.	Check if ExpressCluster is operating by running a command on the destination server Check if all cluster management IPs in the tree view are running normally.
Error	Another user is performing auto-search now. Try it again later.	Auto-search has already been performed from the other manager.	Retry auto-search later.
Error	Internal error.	An internal error of the WebManager has occurred.	Perform the auto-search again. If an error still occurs, restart the ExpressCluster Web Alert service.
Warning	Failed to obtain a part of the cookie data.	The cookie file that supports the IP address was corrupted.	Delete the cookie file and open the window again.
Warning	Could not save the cluster list because cookie is not allowed. Make cookie settings enabled to display the list of clusters, and then restart your browser.	Cookie is not allowed to be used by the browser.	Allow cookie by the browser.
Error	The specified cluster "{0}" has been registered.	The cluster with the same name already exists in the tree view of the cluster.	Use the cluster data that already exists in the tree view.
Info	The cluster "{0}" has been successfully registered.	The cluster has already been registered in the tree view.	-
Error	The cluster cannot be unregistered now because it is being updated to the latest data. Try again later.	The screen is updating by getting the latest data from the WebManager server.	Try again after updating the data is completed.
Error	Failed to find this cluster. Check that the IP address or port	The cluster has not been found by the P address and port number entered.	Check if the IP address and the port number are correct.

Level	Message	Cause	Solution
	number is correct, and that the cluster is started.		Check if the cluster you want to find is operating.
Confirmation	Are you sure to unregister "{0}"?	Are you sure to delete the selected cluster from the management window?	
Error	Specify the IP address.	The IP address is not set.	Check if the IP address is set.
Error	Specify the port number.	The port number is not set.	Check if the port number is set.
Error	The specified IP address is invalid.	The specified IP address is invalid.	Specify the valid IP address.
Error	The specified IP address range is invalid.	The specified start IP address is larger than the stop IP address.	Set the valid IP address range.
Error	Specify the value of 1 ~ 65535 to the port number.	The port number is out of the range.	Specify the value of 1 ~ 65535 to the port number.
Error	The specified port range is invalid.	The specified start port number is larger than the stop port number.	Set the valid port number range.

# Chapter 2 Functions of the Integrated WebManager


This chapter provides information on functions of the Java Applet version Integrated WebManager. Refer to "ExpressCluster® X Integrated WebManager Administrator's Guide" for the Java application version. Integrated WebManager.

#### This chapter covers:

•	What is the Integrated WebManager?	86
•	Access to the Integrated WebManager	86
•	The window of the Integrated WebManager	87
•	Error messages on the Integrated WebManager	92

## What is the Integrated WebManager?


The Integrated WebManager is a function that collectively manages and monitors multiple cluster systems through the network. The following diagram shows the overview of the Integrated WebManager.



There are two types of the Integrated WebManager: One is the Java applet version that operates on a Web browser, and the other is the Java application version that can be operated by installing on a management PC and executed on Java Runtime Environment (JRE). This guide describes the functions on Java applet version of Integrated WebManager. Refer to the "ExpressCluster® X Integrated WebManager Administrator's Guide" for the Java application version of Integrated WebManager.

## Access to the Integrated WebManager

You can access to the Integrated WebManager from a management PC or from an ExpressCluster-installed server by entering the following URL in the browser.



Specify the actual IP address of the ExpressCluster Server-installed server or the management IP.

## The window of the Integrated WebManager


This section provides information on the window of the Integrated WebManager.

#### Note:

The windows of the Integrated WebManager used in this explanation are based on the display in the English environment. The language displayed on the Integrated WebManager's windows depends on the language used in the operating system of the machine on which it is running.

## The main window of the WebManager

The window of the Integrated WebManager consists of three views.



#### Title view

The following operations can be performed by using two buttons.

- ◆ Register
- Reload
- ♦ Option (configures whether or not to substitute by the IP address of Public-LAN.)

#### Tree view

Information on the cluster or server selected here is displayed on the List view area.

#### List view

The information on the cluster and/or server selected in the tree view is displayed.

## How to verify the status of each object in the tree view of the Integrated WebManager

You can visually verify the status of each object that consists of a cluster on the Integrated WebManager. The following shows the status of each object.



- (1) Whole cluster
- (2) Cluster
- (3) Server

No.	Icon		Status	Description
(1)	Whole cluster	Ø	-	No status
(2)	Cluster		Normal	All servers have been started.
			Warning	One or more server is down or in the suspended status.
		×	Error	All servers are down or in the suspended status (isolated) .
			Unknown	No information is acquired.
(3)	(3) Server Online Warning		Online	The server is running normally.
			Warning	Some servers cannot communicate.
		_	Suspension (Network Partition Unsolved)	The network partition cannot be solved, because the disk network partition resolution resource is in the error status.
		×	Suspension (Isolated)	The server is shut down and rebooted. The cluster system did not stop or shut down the server.
		<b>=</b>	Offline or Unknown	The server is not working, or no information is acquired.


## The title view of the Integrated WebManager

You can perform two types of operation by clicking the buttons on the title view.



## How to register a cluster to the Integrated WebManager

In the title view on the top of the Integrated WebManager window, click **Register** to register a cluster to the Integrated WebManager. **Register Cluster** dialog box is displayed.



#### **Manual Setting**

Enter the management IP or the actual IP address of the cluster server and the port number of the WebManager to register the cluster to the Integrated WebManager.


#### IP address

Enter the management IP of the cluster or the actual IP address of the cluster server.

#### Port

Enter the port number of the WebManager (default value 29003).

Click OK. If an IP address and/or port number is registered successfully, a cluster icon is added to the tree view. If it is not registered successfully, no icon is added. Check if IP address and Port are specified correctly and if a cluster is started.



#### **Auto Search**

Detects clusters on the network and registers it to the Integrated WebManager automatically,.


#### **IP Address Range:**

The range where you want to search the IP addresses is specified by entering an IP address for both **Start:** and **End:**.

#### **Port Range:**

Enter the range of the port number that is a target of the search.

To start a search, click **OK.** When the search completes, the result will be displayed.



Select the cluster you wish to register to the Integrated WebManager and click **Register.** The cluster will be displayed in the tree view.



#### How to update the information on the Integrated WebManager

In the title view on the top of the Integrated WebManager window, click **Reload** to update the information displayed on the Integrated WebManager.

#### Noto:

Although what is changed on the Integrated WebManager is automatically updated, it does not always display the latest status because of the refresh interval configuration. To display the latest information, click the **Reload** button after performing an operation.

To configure the automatic reload interval of the WebManager, from the shortcut menu, select **Properties**. In the **Properties** dialog box, click the **WebManager** tab. Then click **Turning** and select **Screen Data Refresh Interval**.

Some objects may be displayed in gray when connection to the server that the objects belong has some error or ExpressCluster on the server is not working.

#### How to start up a WebManager from the Integrated WebManager

There are the following two ways to start up the WebManager from the Integrated WebManager.

#### Start the WebManager by using the management IP

From the tree view of the Integrated WebManager, right-click on a cluster you want its WebManager to start. From the menu displayed, select **Connect to Management IP.** 

#### Start the WebManager by using an actual IP address of a server

#### **♦** Using **Connect**

From the tree view of the Integrated WebManager, select a cluster or a cluster server you want its WebManager to start. From the list view, click Connect.

Using the right-click menu

From the tree view of the Integrated WebManager, right-click on a cluster you want its WebManager to start. From the menu displayed, select **Connect to** *XXX.XXX.XXX.XXX*, where *xxx*...represents the IP address of the actual IP address of the server.

## How to remove a cluster from the Integrated WebManager

#### Using Unregister

From the tree view of the Integrated WebManager, select the icon to remove. In the list view, click Unregister.

Clusters will be deleted in the order that is displayed on the tree view.

◆ Using the right-click menu

Select the cluster to be deleted from the tree view of the Integrated WebManager, and right-click. Select Unregister from the right-click menu.

## Error messages on the Integrated WebManager

The following is a list of error messages displayed when using the Integrated WebManager:

Level	Message	Cause	Solution
Error	Failed to get the data for the cluster tree view from the	Failed to get the cluster information of the destination server.	Check if ExpressCluster is operating in destination server by using the clpstat command.
21101	server.	Failed to get all cluster information in the cluster tree view.	Check if all cluster management IPs in the cluster tree are operating properly.
Error	Another user is performing auto-search now. Try it again later.	Other WebManager has already performed auto-search.	Perform auto-search after waiting for a while.
Error	Internal error.	Internal error has occurred in the WebManager.	Perform auto-search again.  If this error occurs again, restart the WebManager service.
Warnin g	Failed to obtain a part of the cookie data.	Cookie file corresponding to the IP address of the server connected to the browser is corrupted.	Delete the cookie file, close the browser, and then restart the browser.
Warnin g	Could not save the cluster list because cookie is not allowed. Make cookie settings enabled to display the list of clusters, and then restart your browser.	Use of cookie is prohibited by the browser.	Allow cookie on your browser.
Error	The specified cluster "{0}" has been registered.	Same cluster name already exists in the cluster tree view.	-
Info	The cluster "{0}" has been successfully registered.	Specified cluster is registered to the tree.	-
Error	The cluster cannot be unregistered now because it is being updated to the latest data. Try again later.	Getting the latest information from the WebManager Server.	Try again after the update is completed.
Error	Failed to find this cluster. Check that the IP address or port number is correct, and that the cluster is started.	The cluster was not found by the IP address and port number that you have entered.	Check if the IP address and port number is correct. Check if the cluster that you want to find is operating.
Confir mation	Are you sure to unregister "{0}"?	Are you sure to delete the selected cluster?	-
Error	Specify the IP address.	The IP address is not set.	Close the error dialog box and configure the IP address of the cluster.
Error	Specify the port number.	The port number is not set.	Close the error dialog box and set the port number of the cluster.
Error	The specified IP address is invalid.	The specified IP address is invalid.	Close the error dialog box and set the correct IP address.
Error	The specified IP address range is invalid.	The value of start IP address is larger than stop IP address.	Specify the correct IP address range.

Level	Message	Cause	Solution
Error	Specify the value of 1 - 65535 to the port number.	The value of port number is outside of the range.	Specify the value between 1 through 65535.
Error	The specified port range is invalid.	The value of start port number is larger than stop port number.	Specify the correct range of port number.

## **Chapter 3** Function of the Builder

This chapter provides information on functions of the ExpressCluster X Builder. This chapter covers:

•	Overview of the Builder	96
•	Details on the Builder screen	98
•	Pop-up menu	105
•		
•		
•		
•	Edit menu	115
•	Parameter details	118
•	Parameters list	172
•	Upper limits of registration	199

## Overview of the Builder

The ExpressCluster X Builder is a tool for creating and changing the cluster configuration data (config and/or script) for the ExpressCluster Ver3.0 or later.

#### Note:

"Host name" in this guide represents the short name that excludes the domain name from a frequently qualified domain name (FQDN).

The table below describes the icons in "Using the menu bar of the Builder" and "Parameter details."

These icons represent the operations required to reflect the changes of items to the cluster. The table below shows the priorities of required operations in the descending order (high (1) to low (6)) if you make changes in multiple items.

Icon	Priority	How to change	Refer to
ShutdownReboot	1	Shut down and reboot cluster	The Installation and Configuration Guide Chapter 8, "Preparing to operate a cluster system."
StopRestart	2	Stop and restart the cluster daemon	The Installation and Configuration Guide Chapter 8, "Preparing to operate a cluster system."
SuspendResume	3	Suspend and resume the cluster daemon	The Installation and Configuration Guide Chapter 8, "Preparing to operate a cluster system."
GroupStopRestart	4	Stop and resume the group	The Installation and Configuration Guide Chapter 8, "Preparing to operate a cluster system."
MStopRestart	5	Stop and resume the WebManager Stop and resume the alert log	The Reference Guide Chapter 1 "Function of the WebManager"
(No icon)	6	Upload only	The Installation and Configuration Guide Chapter 8, "Preparing to operate a cluster system."

To form a new cluster, refer to the Installation and Configuration Guide.

## Considerations for using the Builder

- ◆ The following products' cluster configuration data is not compatible.
  - The Builder except the ExpressCluster X 1.0/2.0/2.1 for Windows
  - The trekking tool of the ExpressCluster for Linux
  - The trekking tool of the ExpressCluster for Windows Value Edition
- ◆ If you close the Web browser (by clicking **Exit** from the menu or clicking **X** at the top right-hand corner of the window frame), the changes made will be discarded. Even when you changed the configuration data, no dialog box asks if you need to save the changes. To save the changes, click **File** from the menu bar on the Builder and then click **Save** before you exit.
- ♦ If you reload data on the Web browser (by selecting **Refresh** from the menu or clicking **Reload** on the toolbar), the changes made will be discarded. Even when you changed the configuration data, no dialog box asks if you need to save the changes. To save the changes, click **File** from the menu bar on the Builder and click **Save** before you reload.
- ◆ Do not specify a number smaller than 30 seconds for **Reload Interval** on the **WebManager** tab (See "WebManager tab" on page 129 for details). If you have to set a smaller number for this field than the default value, test thoroughly to see if it works properly before you start the operation.
  - ◆ In the environment where both Microsoft Windows Vista<sup>TM</sup> and Internet Explorer 7 are used, disable **Protected Mode** on the security setting of Internet Explorer 7.
- ◆ The JIS 2004 unique characters supported by Microsoft Windows Vista<sup>™</sup> are not supported. You cannot enter or view any character added by JIS 2004.

## **Limitations on using the Builder**


- ◆ If you change the screen resolution while the Builder is running, the Java VM stack trace (example: NullPointerException) may be logged on the Java console. The Builder can keep running.
- ♦ If you press **Esc** while a pull-down menu of your browser is displayed, the Java VM stack trace (example: NullPointerException) may be logged on the Java console. The Builder can keep running.
- ◆ In some cases, you cannot use the keyboard because the keyboard focus of the Builder becomes disabled (the focus changes to the Web browser). Click the Builder window and get the focus back to the Builder.
- ♦ When you are using the multi-display function, do not run the Builder on the secondary display. Otherwise, it may not work properly. For example, the screen is not displayed. Use the Builder on the primary display.
- ♦ On the **Alert Log** tab (see "Alert Log tab" on page 135), for **Max. Number to Save Alert Records**, if you set a number smaller than the current one, all alert logs will be deleted. Take into account the available disk space, and specify the number before you start the operation.

## **Details on the Builder screen**

This topic explains the Builder screen layout.

## Overview of the ExpressCluster X Builder

The screen layout of the Builder is displayed below.



The tree view on the left pane shows the cluster objects in the hierarchical order. If you select an object from the tree view, its subordinate objects are displayed in the table view on the right pane.

#### Tree view


The following objects are displayed in the tree view:

Hierarchy	Object	Contents	Table view when the object is selected
1	C.	Represents the cluster.	Displays cluster names.
2	Groups	Represents a set of groups in the clusters	Displays groups.
3		Represents each group.	Displays group names.
2	Monitors	Represents a set of monitor resources in the clusters	Displays monitors.
2	Servers	Represents a set of servers in the clusters	Displays servers.
3		Represents an individual server.	Displays server names.
2	Server Groups	Represents a set of server groups in the clusters	Displays server groups.
3		Represents an individual server group.	Displays server group names.

#### **Table view**


#### Table for cluster name selection

Displays objects in the root hierarchy.



## Table for group selection

Displays the failover priorities of the groups.




Column name	Overview
Name	Displays the group names in alphanumerical order.
Туре	Displays the group type.
Server names (The number of columns dynamically increases or decreases according to the number of servers)	Represents the startup order of groups on the servers displayed by column names.  The top priority is represented with "1."  This is blank if the startup priority is the same as that of the server. This is blank for the WebManager group.
Comment	Displays comments specified for the groups.

## Table for group name selection

#### Resources


Group resources in the selected group are listed.



Column name	Overview
Name	Displays group resource names in alphanumerical order.
Туре	Displays a group resource type.
Resource Information	Displays objects to be activated or deactivated for the group resource.
Comment	Displays comments specified for the group resource.


#### **Dependency List**

Dependency among group resources in a selected group is listed.



Column name	Overview
Depth	Represents the target activation order of group resources in the name cells.  If a group resource does not depend on any group resource, "0" is displayed.  Group resources are displayed in the depth order.
Name	Displays the group resource name.
Dependent Resource Name	Displays the group resource names that the group resources in the name cells depend on.  If a group resource does not depend on any group resource, "none" is displayed.  When following the default dependency, "" is displayed.  If there are multiple dependent resources, they are displayed in separate rows.
Туре	Displays the group resource type in Dependent Resource Name. When following the default dependency, the dependent type is displayed.

The levels of depth are illustrated below. Arrows (->) in the figure represent the group resource activation order.




The dependencies in this figure are listed below. These are not the default dependencies, but specified with resource names.

Depth	Name	Dependent Resource Name	Туре
0	disk1	none	•
0	disk2	none	-
1	fip1	disk1	disk resource
1	fip2	disk2	disk resource
2	script1	fip1	floating ip resource
-	-	fip2	floating ip resource

#### Table for monitor resource selection


Displays the list of monitor resources.



Column name	Overview
Name	Displays monitor resource names in alphanumerical order.
Туре	Displays the monitor resource type.
Monitored Destination	Displays the monitor resource to be monitored.
Comment	Displays comments specified for the monitor resource.

#### Table for server selection


Displays the list of servers.



Column name	Overview
Name	Displays server names in alphanumerical order.
Туре	If the server is specified as the master server, "Master" is displayed.
Comment	Displays comments specified for the server.

## Table for server name selection


Displays the list of groups allowed to start on the selected server.



Column name	Overview
Order	Displays the server priority. The groups in the name cells start on servers in this order.  "1" is displayed for the top priority.  This list is displayed in the descending order of priority.  This field is blank if the group does not have a specific startup order of servers (if it follows the servers' priorities). The WebManager group is not displayed.
Name	Displays the group name.
Comment	Displays comments specified for the group.

## Table for server group selection

Displays the list of server groups.




Column name	Overview
Name	Displays the server group name.
Server	Displays the names of servers in the server group.
Comment	Displays comments specified for the servers.

## Table for server group name selection

Displays the list of servers in the selected server group.

Section I Detailed functions of ExpressCluster



Column name	Overview
Order	Displays the server priority.
Name	Displays the names of servers in the server group.

## Pop-up menu

Pop-up menus are displayed by right-clicking a tree object or table row.

If select	Displayed menu	Refer to
<pre>f no_cluster_name</pre>	Cluster Generation Wizard	Creating a new cluster (on page 108)
	Remove Cluster	Removing an object (on page 116)
	Rename Server	Renaming an object(on page 117)
	Properties	Properties (on page 117)
Servers	Add Server	Adding an object (on page 116)
	Properties	Properties (on page 117)
server name	Remove Server	Removing an object (on page 116)
	Rename Server	Renaming an object (on page 117)
	Properties	Properties (on page 117)
Monitor Resources	Add monitor resource	Adding an object (on page 115)
Groups	Add Group	Adding an object (on page 115)
group_name	Add Resource	Adding an object (on page 115)
g.cap	Remove Group	Removing an object (on page 116)
	Rename Group	Renaming an object (on page117)
	Properties	Properties (on page 117)
group_resource_name	Remove Resource	Removing an object (on page 116)
	Rename Resource	Renaming an object (on page 117)
	Properties	Properties (on page 117)
monitor_resource_name	Remove Monitor Resource	Removing an object (on page 116)
	Rename Monitor Resource	Renaming an object (on page 117)
	Properties	Properties (on page 117)
Server Groups	Add server group	Adding an object (on page 115)
server_group_name	Remove server group	Removing an object (on page 116)
	Rename server group	Renaming an object (on page 117)
	Properties	Properties (on page 117)

## Using a tool bar of the Builder

The Builder provides a toolbar:



#### Note:

Drag and drop the left corner of the bar to move it.

If you click the three icons on the toolbar, you can perform the same operations as some functions of the pull-down menu displayed on the top of the screen.

Button	Function	Refer to
	Opens a file. This is the same as clicking <b>File</b> from the menu bar, and pointing to <b>Open</b> .	"Opening the configuration file" (on page 108)
	Saves a file. This is the same as clicking <b>File</b> from the menu bar and then selecting <b>Save</b>	"Saving the configuration file" (on page 109)
Ø	Displays the version information. This is the same as clicking <b>Help</b> from the menu bar and then selecting <b>Version Information</b> .	"Checking the version information of the Builder"(on page 117)


## Using the menu bar of the Builder

You can perform various operations by using the menu bar of the Builder. This topic explains the operations to be executed using the menu bar.

#### File menu

Select File to display the following menu.

Menu	Function	
New File	Creates a new cluster.	
Cluster Generation Wizard	Starts the cluster generation wizard.	
Open	Opens the configuration file.	
Save	Saves the configuration file.	
Download the Configuration File	Downloads the configuration file reflected to the cluster.	
Upload the Configuration File	Uploads the configuration file and reflect it to the cluster.	
Option	Starts the <b>Option</b> dialog box.	
Collect logs	Starts the <b>Collect logs</b> dialog box.	
Exit	Exits the Builder.	



## Creating a new cluster

Create a new cluster using the Builder.

#### Important:

If you create a new cluster, the cluster configuration data that has been edited will be discarded. Be sure to save the required data before you create a new cluster.

- 1. On the menu bar, click **File** and then click **Create New File**.
- **2.** If you made changes in the cluster configuration data, a dialog box asks if you want to save them before they are discarded. Click **Yes** to save the changes. A dialog where you can specify a folder to save the cluster configuration data is displayed. If you do not want to save the changes, click **No**. For how to save the data, see "Saving the configuration file" on page 109.
- 3. On the left pane of the screen on the tree view displayed, right-click the cluster icon and click **Cluster Generation Wizard**. Use the **Cluster Generation Wizard** to create a cluster.

For the **Cluster Generation Wizard**, refer to Chapter 5, "Creating the cluster configuration data" in the *Installation and Configuration Guide*.


## Opening the configuration file

Select **Open** to open the saved cluster configuration data. A tree view is displayed by the configuration file that has been read.

Select this to restart editing a temporary file saved while editing the configuration data.

#### How to use:

- 1. Click **Open** from the **File** menu.
- **2.** The **Open** dialog is displayed. Select an appropriate configuration file and click **Open**. The data of the configuration file is displayed in the Builder.



For File Name, select or type "clp.conf."

# Saving the configuration file


Click **Save** to save the cluster configuration data you are editing. This menu becomes available if you have created a cluster configuration data. Save the file as "clp.conf."

To save a cluster configuration data, the following conditions should be satisfied.

- ♦ The server exists.
- ♦ Kernel-mode LAN heartbeat resource exists.

#### How to use:

- 1. Select **Save** from the **File** menu.
- 2. The **Save** dialog is displayed. Select an appropriate place to save the configuration file and click **Save**.



For File Name, select or type "clp.conf."

#### Note:

When using Builder on the server on which ExpressCluster is operated, do not edit etc\clp.conf in the ExpressCluster installation path. Otherwise, messages regarding how to reflect the changes are not properly displayed, and/or ExpressCluster may not work properly. Save the file on a different directory temporarily.

When uploading is performed by using the clpcfctrl command, specify the directory where the file is saved by using the -x option.

# Downloading the configuration file

Download the cluster configuration data set to the connected server. Tree view is displayed according to the downloaded configuration file,

If any changes have been made in the data which is being edited, a dialog box that asks if you want to save the data is displayed.

Click **Yes** to save the changes. A dialog where you can specify a folder to save the cluster configuration data is displayed. For how to save the data, see "Saving the configuration file" on page 109.

If you do not need to save the changes, click **No**. The cluster configuration that is being edited is discarded and the configuration file is downloaded.

If you want to cancel downloading, click Cancel.

#### Note:

Do not create a folder or a file under the <ExpressCluster installation path>\scripts on the server. Downloading the configuration file may fail if you create a file or a folder.

# Uploading the configuration file

Upload the cluster configuration data that is being edited to the connected server. You can select this menu when you open a valid cluster configuration file.

The following conditions must be satisfied to upload the configuration file.

- ◆ A server exists.
- ◆ A LAN heartbeat resource of kernel mode exists.

### Note:

If this condition is not met, connecting to other server fails, so uploading the cluster configuration data fails. In this case, you can only upload the cluster configuration data to a server that can be connected to. For the details, see "Creating a cluster and backing up configuration data (clpcfctrl command)"in Chapter 4 "ExpressCluster command reference."

The following message is displayed while uploading the cluster configuration data. If the uploading the data fails, take an action according to the error message, and upload the data again.

Message	Solution
The upload is completed successfully.	-
The upload is completed successfully. To apply the changes you made, from the Service menu, restart the WebManager and then start the cluster.	-
The upload is completed successfully. To apply the changes you made, shutdown and the reboot the cluster. Shut down all servers when the cluster is stopped.	-

Message	Solution
The upload is completed successfully. To apply the changed you made, restart the WebManager from the Service menu.	-
There is the disk information that is not configured. Are you sure you want automatic configuration?	Some GUID information of the volume is not configured. If you select <b>Yes</b> , automatic configuration is performed by determining the current GUID information from the derive letter.
There is the HBA information that is not configured. Are you sure you want automatic configuration?	The HBA information is not configured for the server where the information of HBA for accessing the shared disk was configured at the time of the installation. If you select <b>Yes</b> , the information configured at the time of the installation is inherited.
There is difference between the disk information in the configuration information and the disk information in the server.  Are you sure you want automatic modification?	The combination between the GUID information of the volume and the drive letter does not match with the one on the actual servers. If you select <b>Yes</b> , automatic configuration is performed by determining the current GUID information from the derive letter.
The upload was stopped. To upload the configuration file, suspend the cluster from the Service menu.	Since the cluster has not been stopped, uploading the cluster configuration data has been cancelled. Stop the cluster first, and then upload the data again.
The upload was stopped. To upload the configuration file, stop the groups to which you made changes.	Since the cluster has not been suspended, uploading the cluster configuration data has been cancelled. Suspend the cluster first, and then upload the data again.
The upload was stopped. To upload the configuration file, stop the resources to which you made changes.	Since the group whose settings have been changed has not been stopped, uploading the cluster configuration data has been cancelled. Stop the group whose settings have been changed, or the group to which the resource whose settings have been changed belongs, and then upload the data again.
The upload was stopped. Applying the cluster configuration file failed in one or more servers.	Since the resource whose settings have been changed has not been stopped, uploading the cluster configuration data has been cancelled. Stop the resource whose settings have been changed, and then upload the data again.
The upload was stopped. Applying the cluster configuration file failed in one or more servers.	Since there is a server that failed to send the cluster configuration data, uploading the cluster configuration data has been cancelled. Upload the data again.
The upload was stopped. There is one ore more servers that cannot be connected to. To apply cluster configuration information forcibly, run the clpcfctrl command on the server.	Since there is a server that cannot be connected to exist in the cluster, uploading the cluster configuration data has been cancelled. Make sure that all the servers in the cluster have been started, and then upload the cluster configuration data.  Even if a server that cannot be connected to exists in the cluster, to upload the cluster configuration data forcibly, refer to "Creating a cluster and backing up configuration data (clpcfctrl command)" in Chapter 4 "ExpressCluster command reference."
An error occurred when applying data to the cluster. Cfctrl (%0)	Since an error has occurred while performing processing, uploading the cluster configuration data has been cancelled. Upload the data again.

### **Related Information:**

If a server that cannot be connected to exists in the cluster, the cluster configuration data cannot be uploaded from the Builder. In this case, by running the clpcfctrl command, you can forcibly upload the cluster configuration data only on the server that can be connected to.

Follow the steps below to forcibly upload the cluster configuration data.

(1) Save the cluster configuration data to an appropriate directory of the local disk from the Builder.


Example) Save the configuration data to C:\config


- (2) Save the cluster configuration data that you have saved on a server in the cluster. Example) Save the data in C:\config that you have saved in step (1) in the C:\tmp directory on a server in the cluster.
- (3) Run the following command on the server where the cluster configuration data has been saved.

 ${\tt clpcfctrl --push -x ``Directory where the cluster configuration \ data} \\ {\tt has been saved" --force}$ 

Example) Run the following command on the server where step (2) has been performed. clpcfctrl --push -x "C:\tmp" --force

# **Changing communication settings**





### **Communication Timeout (0 to 999)**

This is the time-out value when accessing a server.

# Changing log level settings of Builder

Select **Option** and select **Log** to change the log level of Builder.



### Log Level

Configure the level of internal logs that Builder produces during operating.

ERROR

Select this to read only error-level logs.

WARNING

Select this to read warning-level and error-level logs.

INFORMATION

Select this to read information-level, warning-level, and error-level logs.

TRACE1,2,3


Select this to read logs of internal trace, and those from the information, warning and error levels. The greater the number is, more detailed the trace is.

### **Output on JAVA Console**

Click this to configure whether or not to report logs to the JAVA console.

# **Collecting Builder logs**

Select Collect Logs to collect the Builder logs.



Specify the destination to store logs, and select Save.

# **Exiting from the Builder**

Exit from the Builder by selecting Exit. Do not exit from your Web browser.


If any change was made in the cluster configuration data, a dialog box asks if you want to save the changes.

Select **Yes** to save the changes. The dialog box where you can specify a folder to save the file is displayed. For how to save the file, refer to "Saving the configuration file" on page 109. Select **No** if you do not need to save the changes. Exit from the Builder discarding the changes you made in the cluster configuration data.

# **Edit menu**

To open the **Edit** menu: on the menu bar, click **Edit**.

Menu	Function
Add	Adds the object.
Remove	Deletes the selected object.
Rename	Changes the name of the selected object.
Properties	Displays the properties of the selected object.
Add Management Group	Adds the management group.



# Adding an object

Displays the wizard for adding a server, group, group resource or monitor resource. For details, see Chapter 5, "Creating the cluster configuration data" in the *Installation and Configuration Guide*.

What you can add varies depending on what you select as shown below.

If select	Object to be added	How to change
Groups	Group	SuspendResume
group_name	Group resource	SuspendResume GroupStopRestart
Monitors	Monitor resource	SuspendResume
Servers	Server	SuspendResume
Server Groups	server group	SuspendResume

### Note:

If **Auto Failback** is set to **Failback Attribute** in **Group Properties**, a mirror disk resource/hybrid disk resource cannot be added. Set **Failback Attribute** to **Manual Failback** and add a mirror disk resource and hybrid disk resource.

# Removing an object

Displays a dialog box that asks if you want to remove the selected cluster, server, group, group resource or monitor resource. Select **Yes** for removing and **No** for not removing it.

To remove a cluster, select **New File** from the **File** menu.

You cannot remove an object if any of the following conditions is met:

If select	Conditions	How to change
Cluster Name	None	
Server Name	- There is no other server The server is the only server where the group can start up.	SuspendResume
Group Name	- A recovery target of monitor resource <sup>1</sup> Has group resources.	SuspendResume GroupStopRestart
Group Resource Name	<ul> <li>A recovery target of monitor resource<sup>1</sup>.</li> <li>A target object in the monitoring timing of monitor resource<sup>1</sup>.</li> <li>To be monitored by the mirror disk monitor resource<sup>1</sup>.</li> <li>A mirror disk resource that uses the mirror connect to be monitored by the mirror disk connect monitor resource<sup>1</sup>.</li> <li>Other group resources in the same group depend on it.</li> </ul>	SuspendResume GroupStopRestart
Monitor Resource Name	- No condition for those other than mirror disk monitor resource Auto Mirror Recovery is selected on the Mirror Disk tab of Cluster Properties for mirror disk monitor resource.	SuspendResume
Server Group Name	- The server group is registered as the server group of failover group.	SuspendResume

ExpressCluster X 2.1 for Windows Reference Guide

<sup>&</sup>lt;sup>1</sup> A message asks if you want to delete the specified object's monitor resources. If you select **Yes** (delete), the specified object's monitor resources will be deleted, and the object will be deleted.

# Renaming an object

Displays a dialog box for renaming the selected cluster, server, group, group resource or monitor resource.



The following are restrictions for each of the objects.

If select	Naming rules	How to change
Group Name	-Only alphanumeric characters, hyphen (-), underscore (_) and space are allowed for names.	SuspendResume GroupStopRestart
Group Resource Name	-Up to 63 characters (63 bytes) -Names cannot start or end with a hyphen (-) or space.	SuspendResume GroupStopRestart
Cluster Name Monitor Resource Name	() or opace.	SuspendResume
Server Name	-There are naming rules that are the same as the host name of TCP/IP that can be set by the OS. It should be completely the same as the name set to the server.  - Up to 63 characters (63 bytes)  - Neither hyphen (-) nor space can be the first or last letter in names.  - A name consisting of only numbers is not allowed.  -Do not use "localhost" as a server name.	When changing a server name, you have to be careful. For the procedure of change, see Chapter 10, "The system maintenance information" in the Reference Guide.
Server Group Name	The naming conventions the same as the host name of TCP/IP that can be set by the OS.  Up to 31 characters (31 bytes)  Neither hyphen (-) nor space can be used for the first and last letters in names.  A name consisting only of numbers is not acceptable.	

Names should be unique (case-insensitive) by categories such as cluster, server, server group, group, group resource and monitor resource.

# **Properties**

Displays properties of a selected cluster, server, group, group resource, or monitor resource. For details, see "Parameter details" on page 118.

# Checking the version information of the Builder

To check the version information of the Builder, click the Help icon on the toolbar, or click **Help** in the menu bar and select **Version Information**.

EXPRESSCLUSTER and Builder versions are displayed.

Section I Detailed functions of ExpressCluster


# Parameter details

# **Cluster properties**

In Cluster Properties, you can view and change the cluster's settings.

### Info tab

You can view the cluster name, and enter or change a comment for this cluster.



### Name

The cluster name is displayed. You cannot change the name here.

### Comment


You can enter a comment for the cluster. Only alphanumeric characters are allowed.


### Language SuspendResume MStopRestart

Select a language for cluster from the following. Set the language (locale) of OS on which the WebManager runs.


- ♦ English
- ◆ Japanese

## Heartbeat I/F tab





Heartbeat interfaces used by ExpressCluster are listed in **Heartbeat I/F Priority**. Heartbeat interfaces that are not in use are listed in **Available I/F**. Types of heartbeat devices are as follows:



- (1) Interconnect for LAN heartbeat (kernel mode)
- (2) Public LAN heartbeat (kernel mode)

Heartbeat devices types are displayed on this tab as follows:

Heartbeat device type	Туре	How to display in Available I/F <sup>2</sup>
Interconnect for LAN heartbeat (kernel mode)	KLAN	Add to "Interconnect LAN I/F tab."
Public LAN heartbeat		
(kernel mode)		

- ◆ If one or more servers are defined, you have to define at least one LAN interface in **Heartbeat I/F Priority**. It is recommended to specify two or more LAN interfaces.
- ◆ The priority order of the LAN heartbeat for interconnect should be set higher than that of public LAN heartbeat. You can adjust the order by using the **Up** and **Down** buttons after adding the priority order of the LAN heartbeat for interconnect to the **Heartbeat I/F Priority**.
- ◆ Two or more kernel mode LAN heartbeat resources and shared kernel mode LAN heartbeat resources for interconnect and public are recommended to be specified.


Numbers you see in I/F No. cells are those you specified on each tab in Server Properties. Section I Detailed functions of ExpressCluster

## Add SuspendResume

Use **Add** to add a heartbeat interface. Select a heartbeat interface from **Available I/F**, click **Add**, and then it will be added in **Heartbeat I/F Priority**.

# Remove SuspendResume

Use **Remove** to remove a heartbeat interface. Select a heartbeat interface from **Heartbeat I/F Priority**, click **Remove**, and then it will be added in **Available I/F**.



## Up & Down SuspendResume

Use **Up** and **Down** to change the priority of the selected heartbeat interface. Select a heartbeat interface from **Heartbeat I/F Priority**, click **Up** or **Down**, and then the selected row moves accordingly.

### **Server Down Notification**

When a server stops successfully (including shutdown and reboot), it is notified to other servers in the cluster. You can perform failover faster by notifying it in advance.

When failing to deactivate groups when a server stops (including shutdown and reboot), or when other abnormalities occur, other servers are not notified of it regardless of the settings of failed server notification.

When selected:

Server down will be notified.

♦ When cleared:

Server down will not be notified.

## Broadcast and Unicast SuspendResume

Select the communication method of a heartbeat from the following.

♦ Broadcast


Communicate in broad cast method. However, it cannot be used with IP v6.

### ♦ Unicast

Communicate in unicast method

# **Network Partition Resolution I/F tab**

Change the setting of the network partition interface. The network partition resolution interface used for ExpressCluster is displayed on the NP.




### **Tuning**

This tab is used to tune the network partition I/F. Click **Tuning** to display the **NP Resolution Tuning Properties** dialog box.


### Ping tab

The detailed setting about the ping method is displayed. The ping NP used for ExpressCluster is displayed on the **Ping NP**.



### **Edit**

This operation is used to edit the detailed setting of the ping NP. Select the Ping NP that you want to edit from the **Ping NP**, and select **Edit**.



♦ Interval (2 to 999) SuspendResume

This value indicates an interval to issue the ping command.

♦ Timeout (1 to 999) SuspendResume

This value indicates the time-out of the ping command.

♦ Retry Count (1 to 999) SuspendResume

This value indicates the times to reissue the ping command.


<sup>\*</sup>Set each value according to the following requirements.

Requirement 1: Heartbeat Timeout > Interval x Retry Count + Timeout

Requirement 2: Interval > Timeout


### Disk tab

The detailed setting about the Disk method is displayed. The Disk NP used for ExpressCluster is displayed on the **Ping NP**.



### **Edit**

This operation is used to edit the detailed setting of the Disk NP. Select the Disk NP that you want to edit from the **Ping NP**, and select **Edit**.




- ◆ IO Wait Time (1 to 9999) SuspendResume
  This is the time to wait for IO of a disk.
- ◆ Interval (1 to 999) SuspendResume
  This is the interval to perform monitoring.
- ◆ Timeout (5 to 999) SuspendResume Section I Detailed functions of ExpressCluster

This is the time-out to perform monitoring.

Retry Count (0 to 999) SuspendResume
 This is the count to retry monitoring.

# **Master Server tab**


Define the priorities of servers on this tab. All registered servers are listed here. Master server is the server that contains the master of the cluster configuration data. This is the top priority server.




Up & Down SuspendResume

Use this to change the priority of a selected server. Select a server name whose priority you want to change from **Server Priority**, click **Up** or **Down**, and then the selected row moves accordingly.

# Timeout tab





### Server Sync Wait Time (0 to 99)

For the time specified here, the server will wait at startup until other servers are started.

### Heartbeat

- ◆ Interval (1 to 99) SuspendResume
  Interval of heartbeats
- ◆ Timeout (2 to 9999) SuspendResume

A server is determined to be failed if there is no response for the time specified here.

• This time-out should be longer than the interval.

### Server Internal Timeout (1 to 9999) SuspendResume


The time-out to be used in the ExpressCluster Server internal communications

### **Initialize**

Used for initializing the value to the default value. Click the **Initialize** button to initialize all the items to the default value.

### Port No. tab





### **TCP**

No TCP port numbers can be overlapped. When the Replicator/Replicator DR is used, they should not be overlapped with any mirror data port number of any mirror disk resources and hybrid disk resource.

- ◆ Server Internal Port Number (1 to 65535³) SuspendResume MStopRestart

  This port number is used for internal communication.
- ◆ Data Transfer Port Number (1 to 65535³) ShutdownReboot

This port number is used for transactions such as reflecting and backing up the cluster configuration data, sending and receiving the license data and running commands.

♦ WebManager HTTP Port Number (1 to 65535³) MStopRestart

This port number is used for a browser to communicate with the ExpressCluster Server.

- ◆ **Disk Agent Port Number** (1 to 65535 <sup>3)</sup> **ShutdownReboot** This port number is used for a disk agent port number.
- ♦ Mirror Driver Port Number (1 to 65535 ³) ShutdownReboot This port number is used for a mirror driver.

### **UDP**

No UDP port numbers can be overlapped.

- ♦ Kernel Mode Heartbeat Port Number (1 to 65535³) SuspendResume
  This port number is used for kernel mode heartbeat.
- ◆ Alert Sync Port Number (1 to 65535³) MStopRestart

This port number is used for synchronizing alert messages among servers.

<sup>&</sup>lt;sup>3</sup> It is strongly recommended not to use well-known ports, especially reserved ports from 1 to 1023.
ExpressCluster X 2.1 for Windows Reference Guide

#### TCP/UDP


◆ Client Service Port Number (1 to 65535 ³) ShutdownReboo This port number is used for client service.

#### **Initialize**

This is used for initializing the value to the default value. Click the **Initialize** button to initialize all the items to the default value.

# Recovery tab

Make settings on cluster recovery.



#### **Reboot Limitation**

You can specify the **Reboot OS** or **Shut down OS** as the final action at abnormality detection for group resources and monitor resources. If either of them is selected, reboot may be repeated infinitely. By setting the reboot limit, you can prevent repeated reboots.

◆ Max Reboot Count (0 to 99) SuspendResume

Specify how many times the operating system can reboot. The number specified here is separately counted for group resource and monitor resource.

♦ Max Reboot Count Reset Time (0 to 999) SuspendResume

When the max reboot count is specified, if the operation keeps running normally for the time specified here, the reboot count is reset. The time specified here is separately counted for group resource and monitor resource.

### Note:

If **Max Reboot Count** is set to 1 or greater, set **Max Reboot Count Reset Time** also to 1 or greater. If the time to reset the maximum reboot count is set to zero (0), the number of reboot will be unavailable, thus, shutdown/reboot are executed every time at failure detection regardless of the maximum reboot count.

### **Use Forced Stop**

Use this to select whether or not to enable the forced stop.

On

If selected, the forced stop function is enabled.

When you use the forced stop function, configure the information in the **BMC** tab of server property as well.

Off

If selected, the forced stop function is disabled.

### **Forced Stop Action**

Specify an action of the forced stop.

BMC Reset

Use this to perform hardware reset of the server by using the hwreset command or the ipmitool command.

BMC Power off

Use this to power off the server by using the hwreset command. The OS may be shut down depending on how the **Power Options** of OS is configured. For further information, see *Notes on the forced stop* in the Chapter 10 "Other monitor settings.".

BMC Power Cycle

Use this to perform the Power Cycle (powering on/off) by using the hwreset command. The OS may be shut down depending on how the ACPI of OS is configured. For further information, see *Notes on the forced stop* in the Chapter 10 "Other monitor settings."


BMC NMI


Use this to generate NMI by using the hwreset command. The behavior after NMI is generated depends on the OS settings.

### Forced Stop Timeout (0 to 999)

Configure the timeout value when performing Forced Stop. When one of the above commands is executed, activation of the failover group starts after the time specified elapsed.

# WebManager tab





### **Enable WebManager Server**

**MStopRestart** 

Enables the WebManager Server.


- ♦ When selected: the WebManager server is enabled.
- ♦ When cleared: the WebManager server is disabled.

Accessible number of clients (1 to 999) MStopRestart

Specify the number of client machines that can be connected.

### Control connection by using password

Click the Settings button to open the WebManager Password dialog box.



### **♦** Password for Operation

Set a password to connect to the WebManager in the operation mode. Click **Change** to display the **Change Password** dialog box.

### **♦** Password for Reference

Set a password to connect to the WebManager in the reference mode. Click **Change** to display the **Change Password** dialog box.



Old Password (Within 255 bytes)

Enter the current password. If the password is not set, leave it blank.

• New Password (Within 255 bytes):

Enter a new password. When deleting the old password, leave it blank.

• **Password Confirmation** (Within 255 bytes)

Enter the password again which you entered in **New Password**.

### Control connection by using client IP address

**MStopRestart** 

If selected, accesses are controlled by client IP addresses.

♦ When selected:


Add, Remove and Edit buttons are enabled.

♦ When cleared:

Add, Remove and Edit buttons are disabled.

### Add MStopRestart

Use **Add** to add an IP address in **IP Addresses of the Accessible Clients**. By clicking **Add**, the **IP Address Settings** dialog box is displayed to enter an IP address. Newly added IP addresses have the rights for the operation.



◆ IP **Address** (within 80 bytes)

Specify a client IP address that can be connected.

• IP address: 10.0.0.21

Network address: 10.0.1.0/24

# Remove MStopRestart

Use **Remove** to remove an IP address from **IP Addresses of the Accessible Clients**. Select an IP address you want to remove in **IP Addresses of the Accessible Clients** and click **Remove**.

### Edit MStopRestart

Use **Edit** to edit an IP address. Select an IP address you want to edit in **IP Addresses of the Accessible Clients** and click **Edit**. A dialog box where the specified IP address is preset is displayed. The rights for operating the edited IP addresses remain the same.

### Control connection by using client IP address MStopRestart

Sets the operation rights for IP addresses that are registered in **IP Addresses of the Accessible Clients**.

♦ When selected:


A client can operate a cluster and display its status.

♦ When cleared:

A client can only view the status of a cluster.

#### **Tuning Properties**

Use **Tuning** to tune the WebManager. Click **Tuning** to open the **WebManager Tuning Properties** dialog box.



◆ Client Session Timeout (1 to 999) MStopRestart

Specify the client session time-out. A time-out is determined if the time specified here elapses after the last communication between the WebManager Server and the WebManager.

♦ Max. Number of Alert Records on Viewer (1 to 999) MStopRestart

Specify the maximum number of alert viewer records to display on the Alert Viewer of the WebManager.

◆ Screen data update interval (0 to 999) MStopRestart

Specify the screen data update interval. At this time interval, the WebManager screen is refreshed.

♦ Mirror agent timeout (1 to 999) MStopRestar

Specify the mirror agent time-out. A time-out is determined if the time specified here elapses till the mirror disk information is acquired.

### ♦ How to update client data MStopRestart

You can select the method to update the screen data of the WebManager from the following.

- Polling
   The screen data is updated regularly.
- Real Time
   The screen data is updated on the real time.

# ◆ Time Limit For Keeping Log Files (60 – 43200) MStopRestart

Time limit determines when the log collection information temporarily saved on the server will be deleted. When the time specified here has elapsed, the log collection information will be deleted unless you save the file when the dialog box asking you if you save the log collection information is displayed.


**♦** Initialize

Click **Initialize** to reset all settings on this dialog to default.

# **♦** The Number Of Clusters That It Searches For At A Time

Configure the number of clusters to acquire the information at a time when the cluster information is uploaded.

# Integrated WebManager tab




The Number of Logics when Searching Clusters (1 to 100) MStopRestart

Set the number of logics when the Integrated WebManager searches for cluster.

The Number Of Clusters That It Searches For At A Time (1~20) MStopRestart Set the number of clusters by which information collection is made at a time.

# **Alert Log tab**





# Enable Alert Service MStopRestart

Select this to start ExpressCluster Web Alert service for the server.

- ♦ When selected:
  - ExpressCluster Web Alert service is enabled.
- ♦ When cleared:

ExpressCluster Web Alert service is disabled.

### Max. Number to Save Alert Records (1 to 99999) MStopRestart

Specify the maximum number of alert records that can be retained. ExpressCluster Web Alert service for server can retain alert messages up to this number.

## Alert Sync: Method MStopRestart

This communication mode is used for Alert Log synchronization. Only unicast is available in **Method** list box for this version.

### Alert Sync: Communication Timeout (1 to 300) MStopRestart


Specify a communication time-out. A communication time-out is determined if the time specified here elapses after the last communication between ExpressCluster Web Alert service and servers.

### **Initialize**

Click Initialize to reset all settings on this tab to default.

# **Delay Warning tab**

Configure the settings for Delay Warning on this tab. See "Delay warning of monitor resources" in Chapter 7, "Monitor resource details" for more information.



## Heartbeat Delay Warning (1 to 99) SuspendResume

Set a percentage of heartbeat time-out at which the heartbeat delay warning is issued. If the time for the percentage passes without any heartbeat response, the warning will be produced in an alert log.

### Monitor Delay Warning (1 to 99) SuspendResume

Set a percentage of monitor time-out at which the monitor delay warning is issued. If the time for the percentage passes without any monitor response, the warning will be produced in an alert log.


### COM Delay Warning (1 to 99) SuspendResume


Set a percentage of COM I/F delay warning. If the time for the percentage passes without any COM response, the warning will be produced in an alert log.

#### Note:

If you specify 0% for the delay warning, an alert log is shown in every heartbeat interval and monitor interval. Setting 0% allows you to see the time spent for monitoring. This will be helpful particularly in a test operation. Make sure not to set low values such as 0% in the production environment.

# Disk tab





### Retry interval when failing to disconnect a disk (1 to 10)



Set the interval time required to retry disconnecting, when disconnecting a shared disk has failed.

### Retry count when failing to disconnect a disk (0 to 180) MStopRestart

Set the count to retry disconnecting when disconnecting a shared disk has failed.

♦ Infinite

Select this to retry disconnecting a disk infinitely.

Specifying the retry count

Select this to specify the count to retry to disconnect a disk.

### Final action when failing to disconnect a disk MStopRestart

If the count to disconnect a shared disk again is specified, set the action that will be taken in the case that disconnecting is failed for the specified count

Disconnecting forcibly

Select this to disconnect a disk forcibly.

Not disconnect forcibly


Select this not to disconnect a disk forcibly.

### Initialize

This operation is used to return the value to the default value. Click **Initialize** to set the default values to all items.

# Mirror disk tab

Configure the setting for a mirror disk.



#### **Auto Mirror Initial Construction**

Specify whether to perform the mirror initial construction automatically when the newly created mirror disk resource is activated for the first time.

When selected

Mirror initial construction is performed automatically.

♦ When cleared

Auto mirror initial construction is not performed

### **Auto Mirror Recovery**

An automatic mirror recovery is performed when any difference occurs in the data of mirror disks between both servers. There is a case that mirror recovery cannot be performed automatically even if it is selected. For the detail information, see "Automatically recovering from mirroring" in Chapter 11, "Trouble Shooting."

♦ When selected

Mirror recovery is performed automatically.

♦ When cleared

Mirror recovery is not performed automatically.

### Retry interval when failing to disconnect a disk (1 to 10)

Set the interval time required to retry disconnecting, when disconnecting a mirror disk has failed.

### Retry count when failing to disconnect a disk (0 to 180)

Set the count to retry disconnecting when disconnecting a mirror disk has failed.

◆ Infinite

Select this to retry disconnecting a disk infinitely.

◆ Specifying the retry count

Select this to specify the count to retry to disconnect a disk.

### Final action when failing to disconnect a disk

If a retry count is set for mirror disk disconnection, set the action when that will be taken in the case that disconnection still fails after the specified retry count exceeds.

♦ Disconnecting forcibly

Select this to disconnect a disk forcibly

Not disconnect forcibly


Select this not to disconnect a disk forcibly.

### **Initialize**

This operation is used to return the value to the default value. Click **Initialize** to set the defaults value to all items.


# **Account tab**

Register and/or delete the user account that is used in the ARMLOAD compatible command. You can set up to sixteen user accounts for one cluster system. The accounts that have already set on the all cluster servers are the target to be registered. The user accounts that are currently registered on the **Account** are displayed.



### Add

Use **Add** to add a user account on the Account List. Click **Add** to display the dialog box where an account is entered.



### ◆ User Name

Enter a user account name to be registered. When specifying an account of a domain, enter, for example, "Domain Name\Account Name."

### ◆ Password

Enter a password of the user account to be registered.

### Remove


Use **Remove** to remove a user account from the Account List. Select a user account you want to remove from the Account List and click Remove.

#### **Edit**

Use **Edit** to edit a user account. Select a user account you want to edit from the **Account** and click **Edit**. The Entry of Account dialog box where the selected account is preset is displayed.

# **Auto Recovery tab**

Configure whether to perform "Auto Recovery" when a cluster server is restarted after server failure has occurred.




### **Auto Return**

- ◆ On
  - Select this to perform the auto recovery.
- Off

Select this not to perform the auto recovery.


# RIP (Legacy) tab

With the virtual IP resource configured with the Builder in the older version (X1.0), configure the IP address of the public LAN that sends RIP. As to the version X2.1, you do not have to configure this fir mo of cases because it is configured at the properties of virtual IP resource. When connecting to the ExpressCluster Server from a remote LAN by using a virtual IP address, RIP must be sent to the public LAN which a router is connected to. The broadcast address of the RIP which is set on the cluster is displayed on the **Network Address**.



### Add

Use **Add** to add a network address to the **Network Address**. Selecting **Add** displays a dialog box to enter a network address.



◆ Network Address

Enter a network address to be registered.

#### ♦ Net Mask

Enter a network mask to be registered.

#### Remove

Use **Remove** to remove a network address from the **Network Address**. Select a network address you want to remove and click **Remove**.

### Edit


Use **Edit** to edit a network address. Select a network you want to edit from the **Network Address** and click **Edit**. The entry of network address dialog box where a network address is preset is displayed.

# Alert service tab

Configure the alert service, chassis identify, and network warning light.

### Note:

To use the mail alert function and network warning light, ExpressCluster X Alert Service 2.1 for Windows is required.



### **Enable Alert Setting**

Configures whether or not to modify the default value of the alert settings. To modify the settings, click Edit to configure the destination address.

If you clear the checkbox, the destination address you have modified returns to the default settings temporarily.

For the default settings of the destination address, see the *messages reported by eventlog and alert* in the Chapter 13 "Error messages."

E-mail Address (Within 255 bytes)

Enter the mail address of alert destination. To specify multiple mail addresses, separate each of them by semi-colon ";".

### Subject (Within 127 bytes)

Enter the mail subject.

### Mail Method

Configure the mail method. In this version, SMTP is the only option in this

#### ◆ SMTP

Sends the alert by communicating with directly the SMTP server.

### **Use Chassis Identify**


Configure whether or not to use the chassis identify function.

### **Use Network Warning Light**

Configure whether or not to use the warning light (dedicated product) controlled by network. The IP address of warning light is entered on the server property.


### **Change Alert Destination**

Select **Edit** to display the dialog box where you can change alert destination.



### Add

Add the alert ID of the destination which you want to customize. Click **Add** to open the dialog box for entering the message.



### Category

Select a main category of module types.

### Module Type (within 31 bytes)

Select the name of the module type for which you want to change the destination address.

### **Event ID**

Enter the message ID of the module type for which you want to change the destination. For information on the message IDs, refer to *messages reported by eventlog and alert* in the Chapter 13 "Error messages."

### **Destination**

Select a message destination from the following options.


- WebManager Alertlog
   This sends messages to the alert view of the WebManager.
- Alert Extension

This executes the specified function by using the alert extension function. Modify the extension settings by using the **Add** button and/or the **Edit** button. (The command must be specified within four lines.)

- Mail Report
   Uses the mail report function.
- Event Log (Disable only)
   Disables the settings for the OS to report logs to the event log. You cannot configure the settings to report messages that are not reported to event logs.)

### Add

Add a command of the alert extension function. Click **Add** button to display the dialog box for entering a command.



### Command (Within 511 bytes)

Enter any command you want to use.

Keyword

If you specify %%MSG%%, the message of the target event ID is inserted. You cannot specify multiple %%MSG%% for one command. Configure the command within 511 bytes including the description of %%MSG%%. If you set %%MSG%% as an argument for a command, you need to add backslash (\) and double quotation (") like below.

<any command you want to use> \"%%MSG%%\"

### Remove


Click this to remove a command of the alert extension function. Select the command, and then, click **Remove**.

### Edit

Click this to modify a command of the alert extension function. Select the command, and then, click **Edit**.

### **SMTP Settings**

Click this to display the SMTP Settings dialog box which is used for the mail alert.



# Mail Charaset (within 127 bytes)

Configure the character set of the e-mails sent for mail report.

## Send Mail Timeout (1 – 999)

Configure the timeout value for the communication with SMTP server.

## **Subject Encode**


Configure whether or not to encode the subject of e-mails.

# **SMTP Server List**

Use this button to display a SMTP server that has been configured. Only one SMTP server can be configured in this version.

### Add

Use this button to add a SMTP server. Click **Add** to open the **Enter the SMTP Server** dialog box.



### SMTP Server (within 255 bytes)

Configure the IP address of the SMTP server.

### **SMTP Port** (1 – 65535)

Configure the port number of the SMTP server.

# Sender Address (within 255 bytes)

Configure the address from which mail report is sent.

#### **Enable SMTP Authentication**

Configure whether or not to enable SMTP authentication.

### Method

Select a method of SMTP authentication.

# User Name (within 255 bytes)

Configure the user name used for SMTP authentication.

# Password (within 255 bytes)

Configure the password used for SMTP authentication.

### Remove


Select this to remove the SMTP server.

### **Edit**

Use this button to modify the settings of SMTP server.

# Power saving tab

Configure whether or not to use the function to turn it to power-saving mode by controlling the CPU frequency of the standby server.



### **Use CPU Frequency Control**

Select the checkbox when you use CPU frequency control. If you uncheck the checkbox, CPU frequency control is disabled.

### **Initialize**

This operation is used to return the value to the default value. Click **Initialize** to set the defaults value.

#### **Related Information:**

When CPU frequency control is used, the CPU frequency of the server where a failover group is activated is set to high, and that of the server where a failover group is stopped is set to low.

When CPU frequency control is performed by a command or WebManager, the settings changed by the command or WebManager are given higher priority regardless of whether the failover group is started or stopped. Note that the settings changed by the command or WebManager is discarded after the cluster is stopped/started or suspended/resumed, so that CPU frequency is controlled by the cluster.

### Note:

For using CPU frequency control, it is required that the frequency is changeable in BIOS settings and the CPU supports the frequency control by Windows OS power management function.

### Note:

If you disable CPU frequency control function with CPU frequency changed, the CPU frequency does not return to the state before changing.

In this case, return the CPU frequency to the defined value by the following way.

Windows Server 2003:

Execute the following command at a command prompt.

# powercfg /X "Always On" /processor-throttle-ac none

The character string to be specified with /X option is the name selected in the current setting of [Power Options] -> [Power Schemes] in [Control Panel].

Windows Server 2008:

Select [Balanced] in [Power Options] -> [Select a power plan] in [Control Panel].

# Server Properties

On the **Server Properties** dialog box, add, remove or edit interfaces such as IP address and device that are used on each server in a cluster. Configure the settings for the same number of interfaces (hereinafter referred to as I/F) on each server. I/F No. represents the registration order by the Builder. This is irrelevant to the number set by the OS.

From the aspect of network environment, IP addresses have the following restrictions:

• One server cannot have two or more IP addresses that belong to the same network address. Likewise, containment is not allowed as follows.

• IP address: 10.1.1.10, Subnet mask: 255.255.0.0

• IP address: 10.1.2.10, Subnet mask: 255.255.255.0

# Interface of each server

If two or more servers are defined, the Builder gives the same number of interfaces for each server. Click **OK** or **Apply**. The Builder confirms the number of interfaces, and works as follows:

### When an interface was added:

The Builder automatically adds the interface of the same type and number to the other servers. On the other servers, the settings are all blank.

# When an interface was removed:

The following message is displayed for confirmation. If you removed a public LAN interface on a server, you see the following message. If you removed another type of interface, you see the corresponding message.



♦ When **Yes** is selected:


The interface of the same type and the last number will automatically be removed from the other servers so that all servers have the same number of interfaces.

◆ When **No** is selected:

The interface of the same type and the last number will not be removed from the other servers. On the server where you have removed an interface, its I/F No. will not be removed, but set to blank.

# Info tab

You can display the server name, and register and make a change to a comment on this tab.



#### Name

The selected server name is displayed. You cannot change the name here.


#### Comment

You can specify a comment for the server. Only alphanumeric characters are allowed.

# Interconnect LAN I/F tab

You can add, remove and edit an interconnect LAN interface to be used for interconnect LAN heartbeat. Registered I/F No. and IP addresses are listed in **Interconnect LAN I/F**.

You have to specify more than one interconnect LAN interface.




# Note:

- ♦ When the Replicator/Replicator DR is used, see also "Mirror connect I/F tab ~ for Replicator/Replicator DR ~-." If there are two or more interconnect LAN interfaces, it is required to take into account the IP address to be used for mirror connect interface and specify the interconnect LAN interface.
- ◆ You must follow the steps below to remove the interconnect LAN I/F after setting the heartbeat I/F.
  - 1. Remove all heartbeat I/Fs in the cluster properties.
  - 2. Remove the interconnect LAN I/F in the server properties.
  - 3. Reset the heartbeat I/F in the cluster properties.

## Add SuspendResume

Use Add to add an interface. Click Add to open the IP Address Settings dialog box.



◆ IP Address (within 80 bytes)
Enter an IP that is actually used for interconnect LAN.

# Remove SuspendResume

Use **Remove** to remove an interface. Select an interface you want to remove from the interface list and click **Remove**. You cannot remove the I/F No. specified for the heartbeat interface. To remove it, change the heartbeat interface settings first.

#### **Edit**

Use **Edit** to edit an IP address. Select an interface you want to edit from the interface list, and click **Edit**. The **IP Address Settings** dialog box where the selected IP address is preset is displayed.

### Note:

Be careful when you change an IP address of the server. For how to change the IP addresses, see Chapter 10, "The system maintenance information."

### Note:


Do not specify address in IPv6 format for Windows Server 2003 environment.

# Up & Down SuspendResume

Use **Up** and **Down** to change I/F No. Select an interface from the interface list and click **Up** or **Down**. The selected row moves accordingly.

# Public LAN I/F tab

You can add, remove and edit a public LAN interface. Registered I/F No. and IP addresses are listed in **Public LAN I/F**. For details of heartbeat, see Chapter 8, "Heartbeat resources."



# Add SuspendResume

Use Add to add an interface. Click Add to open the IP Address Settings dialog box.



◆ **IP Address** (within 80 bytes)

Enter an IP that is actually used for public LAN.

Remove SuspendResume

Use **Remove** to remove an interface. Select an interface you want to remove from the interface list and click **Remove**.

#### **Edit**

Use **Edit** to remove an IP address. Select an interface you want to edit from the interface list and click **Edit**. The **IP Address Settings** dialog box where the selected IP address is preset is displayed.

### Note:


Be careful when you change an IP address of the server. For how to change the IP addresses, see Chapter 10, "The system maintenance information."

# Up & Down SuspendResume

Use **Up** and **Down** to change I/F No. Select an interface from the interface list and click **Up** or **Down**. The selected row moves accordingly.


# COM I/F tab

You can add, remove and edit a COM interface to be used for the network partition resolution by COM method. Registered I/F No. and devices are listed in **COM I/F**. This is used for 2-node cluster. For details of network partition resolution, see Chapter 9 "Details on network partition resolution resolution resources."



# Add SuspendResume

Use **Add** to add an interface. Click **Add** to open the **Enter the device name** dialog box. The default device name is preset.



◆ **Port Name** (up to 1023 bytes)

Enter an actual device name for the COM port. You cannot register a port name that is registered in **COM I/F**.

### Remove SuspendResume

Use **Remove** to remove an interface. Select the interface that you want to remove from the interface list and click **Remove**.

# Edit SuspendResume

Use **Edit** to edit a device. Select a device you want to edit from the interface list and click **Edit**. The **Enter the device name** dialog box where the name of selected COM device is preset is displayed.


# Up & Down SuspendResume

Use **Up** and **Down** to change the I/F number. Select an interface from the interface list and click **Up** or **Down**. The selected row moves accordingly.

# Disk I/F tab


You can add, remove and edit a disk interface to be used for network partition resolution by the disk method. The interface numbers, mount points, and GUIDs currently registered in **Disk I/F** are listed.

For details of network partition resolution, see Chapter 9, "Network partition resolution resources."



# Add SuspendResume

Use Add to add an interface. Select Add to open the Selection of partition dialog box.



### **♦** Select From List

Select the partition device (partition for a disk heartbeat) to be used for the network partition resolution in the Disk method form the list. You can get the list of partitions by clicking **Connect**.

#### **♦** Direct entry

Select **Direct entry** to change the mouse point which is allocated to the selected partition.

### Important:

For the partition for a disk heartbeat, specify a filtering-set unformatted partition on the shared disk connected to HBA. Do not specify the partition set for disk heartbeat for a disk resource partition, cluster partition of a mirror disk resource and the data partition. Otherwise, data on the shared disk may be corrupted.

### ◆ Remove SuspendResume

Select **Remove** to delete the interface. Select the interface to delete from the I/F list, and click **Remove**.

# ◆ Edit SuspendResume


Select **Edit** to edit the device. Select the interface to edit from the I/F list, and click **Edit.** The **Selection of partition** dialog where the selected device name has been entered is displayed.

# ◆ Up & Down SuspendResume

Select **Up** or **Down** to change the interface number. Select the interface to change from the I/F list and click **Up** or **Down**. The selected line moves.


# Ping I/F tab

You can add, remove and edit the IP address to be used for the network partition resolution in the Ping method. The currently registered interface number, whether to use any interface number and the IP address to be used are displayed on the Ping I/F List. Configure whether to use with the check box within the **Ping I/F**.



# Add SuspendResume

Use Add to add an interface. Click Add to open the Selection of Ping NP dialog box.



### ♦ Group

Register a group of the Ping method. If multiple groups are registered and one of the groups detects an error, it is determined that the interface has an error.

#### **♦** IP Addresses

Register the IP address to be grouped in one of the groups with the Ping method. The IP address of the group selected in the **Group** is displayed. If multiple groups are registered and one of the groups detects an error, it is determined that the group has an error.

### Remove SuspendResume


Use **Remove** to remove an interface. Select an interface you want to remove from the I/F list and click **Remove**.

# Edit SuspendResume

Use **Edit** to edit an IP address. Select an interface you want to edit from the I/F list and click **Edit**. The **Selection of Ping NP** dialog box where the selected IP address is presser is displayed.

# Majority I/F tab

Configure whether to use the network partition resolution with the majority method. The interface numbers that is currently registered in the and whether to use those numbers are displayed on the majority I/F list. Whether to use an interface can be configured in the check box within the Majority I/F list



# Add SuspendResume


Use Add to add an interface. Click Add to add an interface.

# Remove SuspendResume


Use **Remove** to delete an interface. Select an interface you want to remove from **Majority I/F** and click **Remove**.

# Mirror connect I/F tab ~ for Replicator/Replicator DR ~

You can add, remove and edit a mirror connect interface. The I/F number and the IP addresses currently registered in **Mirror Connect I/F** are listed. You have to specify a mirror connect interface.




- ◆ Specify the IP address of LAN heartbeat for interconnect.
- ◆ If there are two or more LAN heartbeats for interconnect, specify an IP address of the second or later LAN heartbeat for interconnect.



### Add SuspendResume

Use Add to add an interface. Click Add to open the IP Address Settings dialog box.



## ◆ **IP Address** (within 80 bytes)

Enter an actual IP to be used for mirror connect.

### Remove SuspendResume

Use **Remove** to remove an interface. Select an interface you want to remove from the interface list and click **Remove**.

You cannot remove an I/F number that is set for the mirror disk resource or hybrid disk resource. To remove such an I/F number, change its mirror connect interface setting of mirror disk resource or hybrid disk resource.

### **Edit**

Use **Edit** to edit an IP address. Select an interface you want to edit from the interface list and click **Edit**. The **IP Address Settings** dialog box where the selected IP address is preset is displayed.


## Note:


Be careful when you change a server IP address. For how to change an IP address, see Chapter 10, "The system maintenance information."

# Up & Down SuspendResume

Use **Up** and **Down** to change an I/F number. Select an interface from the interface list and click **Up** or **Down**. The selected row moves accordingly.

## **HBA** tab





### **♦** HBAs to be managed by the cluster system

ShutdownReboot

Set the access to the shared disk. If the check box is selected, access to all disks connected to the HBA is controlled when starting the OS next time. To protect data, it is required to select the check box of the HBA to which the shared disk is connected.

If the HBA list is not displayed, it can be displayed by clicking the **Connect** button.

### Important:

- Do not connect the shared disk to any HBA whose check box is not selected. Even
  though the check box is selected, do not connect to the shared disk when the OS is not
  started again after configuring the settings. Data on the shared disk may be corrupted.
- Do not select the checkboxes other than those of HBAs to which the shared disk is connected. If access to the system partition on which the OS has been installed is restricted, the OS may not be started.
- Do not select the checkboxes of HBA that connects the mirroring target internal disk if you use mirror disk resource. Starting mirror disk resource fails.

## ◆ Partition excluded from cluster management SuspendResume

When a disk other than the shared disk is connected to the HBA set in **HBAs to be** managed by the cluster system, register the partitions on the disk. The access to the partitions registered with this list is not restricted.

#### Important:

In principle, do not register the partitions on the shared disk that can be accessed from multiple servers. Data on the shared disk may be corrupted.

### Connect

Select this to get the HBA data by connecting to the server.

#### Add


Add a partition that should not be restricted in its access in **Partition excluded from cluster management**.

### Remove

Remove the selected partition from Partition excluded from cluster management.


# Warning light tab

Set an IP address of warning light (specified by NEC) controlled by network.



# $\mathbf{Add}$

Use this button to add an IP address of warning light. Click **Add** to open the **IP Address Settings** dialog box.



◆ IP Address (within 80 bytes)

Enter an IP address of the warning light.

### Note:

One warning light is required per one server. Do not set an IP address of the same warning light to multiple servers.

◆ User Name

Enter the user name of the execution account on the server used for controlling the warning light.

◆ Password

Enter the password of the execution account on the server used for controlling the warning light.

### Note:


For Windows Server 2008, enter Administrator for user name, Administrator for password. For Windows Server 2003, you can omit the user name and password.

### **Edit**

Use **Edit** to change an IP address. Click **Edit** and the **IP Address Settings** dialog box is displayed.


# **BMC** tab

Configure a LAN port for managing BMC when using the forced stop and the chassis identify. Configure one for each server.



### Add

Use this button to newly configure new settings. Click **Add** to open the **IP Address Settings** dialog box.



♦ IP Address (within 80 bytes)

Enter the IP address set for the LAN port for managing BMC.

◆ User Name (within 255 bytes)

Enter the name of a user with administrator privilege from the user names configured in BMC.

If you do not enter anything, do not configure the argument of user name when the hwreset command or the alarms command is executed.

• Password (within 255 bytes)

Enter the password of user configured above.

For information on user name of BMC and how to configure the password, refer to the manual of the server.

### Remove

Use this button to remove the settings. Select the target setting, and then, click **Remove**.

### Edit

Use this button to modify the settings. Select the target setting, and then, click **Edit**. The **IP Address Settings** dialog box is displayed.

# **Parameters list**

Parameters you can specify in the Builder and their default values are listed below.

"How to change [1]-[6]" represents the way you reflect changes of parameters on servers. Applicable method is marked with "O." For details of [1]-[6], see "Overview of the Builder" on page 96.

Pa	arameters	Default	How	to cha	nae		
				2 3	4	5	6
Clus	ter Properties						
	fo Tab						
Na	ame	-		0		I	
C	omment	-					0
La	anguage	English		0		0	
Н	eartbeat I/F Tab	T ,					
	rder (Up, Down)	1 -		0			
	ype (Add, Remove)	-		0			
	erver Down Notification	On					0
	roadcast/Unicast	Unicast		0	1		
	etwork Partition Resolution I/F Tab	0					
	NP Resolution						
	Tuning Properties						
	Ping Tab						
	Interval	5 seconds		ТОТ		П	
	Timeout	3 seconds		0			
	Retry Count	3 seconds	++	0	+		
	Disk Tab	0 00001100					
	IO Wait Time	80 seconds	1 1	ΤΟΙ		T	
	Interval	60 seconds		0			
	Timeout	300 seconds		0			
	Retry count	zero		0			
M	aster Server Tab	Zeio					
	rder (Up, Down)	The order you added servers	1 1	101		0	
T:	meout Tab	The order you added servers				<u> </u>	
	erver Sync Wait Time	5 minutes					0
	eartbeat Interval	3 seconds		0			0
	eartbeat Timeout	30 seconds					
	earroear Timeour erver Internal Timeout	180 seconds		0			
		180 seconds		0			
	ort No. Tab	1,00004	1				
	erver Internal Port Number	29001	$\perp$	0		0	
	ata Transfer Port Number	29002	0			_	
	ebManager HTTP Port Number	29003				0	
	sk Agent Port Number	29004	0				
	irror Driver Port Number	29005	0				
	ernel Mode Heartbeat Port Number	29106		0			
	ert Sync Port Number	29003				0	
	lient Service Port Number	29007	0				
	ecovery Tab						
	ax Reboot Count	zero		0			
	ax Reboot Count Reset Time	0 minute		0			
	se Forced Stop	Off					0
	orced Stop Action	BMC power off					0
	orced Stop Timeout	3 sec					0
	lert Service Tab						
	nable Alert Service	Off					0
	ail Address						0
	ubject	-					0
	ail Method	SMTP					0
U	se Chassis Identify	Off	0				
	se Network Warning Light	Off		0			
		•					

Parameters	Default	Но	How to char		nae		
		1	2	3	4	5	6
Alert Destination Tab							
Messages (Add, Remove, Edit)	-						
Message Tab							
Category	Process						
Module Type	apisv						
Event ID	-						
Destination WebManager Alert Log	On						
Destination Mail Report	On						
Destination Alert Extension	Off						
Command (Add, Remove, Edit)	-						
SMTP setting							
Mail Charaset	-						
Send Mail Timeout	30 sec						
Subject Encode	Off						
SMTP Server (Up, Down)	-						
SMTP Server List (Add, Remove)	-						<del>                                     </del>
Enter the SMTP Server							
SMTP Server	1	1		1	1		
SMTP Server SMTP Port	25						<u> </u>
Sender Address	25						<u> </u>
Enable SMTP Authentication							<u> </u>
	Off LOGIN						<u> </u>
Method	LOGIN						<u> </u>
User name	-						<u> </u>
WebManager Tab	-						Щ_
	Lon	1		1	1	_	
Enable WebManager Server Accessible number of clients	On 64					0	<u> </u>
Control connection by using client IP address	Off					0	<u> </u>
IP Addresses of the Accessible Clients	Oil					0	<u> </u>
(Add, Remove, Edit)	-					0	
Operation	On					0	<del> </del>
Web Manager Password	011			<u> </u>			Щ
Password for Operation	I -	1		1	1		0
Password for Reference	-						0
WebManager Tuning Properties	1 -						
Behavior Tab							
Client Session Timeout	30 seconds			I		0	
Max. Number of Alert Records on the	300						<del></del>
Viewer	300					0	
Screen Data Refresh Interval	90 seconds					0	<del></del>
Mirror Agent Timeout	150 seconds					0	<del></del>
Client Data Update Method	Real Time					ō	
Time Limit For Keeping Log Files	600 seconds					Ō	
Integrated WebManager Tab	000 30001103						
The Number of Logics when Searching Clusters	10					0	
The Number Of Clusters That It Searches For At	10					_	
A Time	'					0	
Alert Log Tab							
Enable Alert Service	On					0	
Max. Number to Save Alert Records	10000					0	
Alert Sync Method	Unicast (fixed)					0	
Alert Sync Communication Timeout	30 seconds					ō	
Delay Warning Tab							
Heartbeat Delay Warning	On 80%			0			
Monitor Delay Warning	On 80%			0			
COM Delay Warning	On 80%		<del>                                     </del>	0			
Disk Tab	0.1.0070						
Retry Interval At Disk Disconnection Failure	3 seconds						О
Retry Count At Disk Disconnection Failure	Specify the count						0
Metry Count At Disk Disconnection Failule	Opecity the count						U

Parameters	Default	Но	How to change		nga	ie .				
	Delauit	1	2	3	4	5	6			
Set Retry Count At Disk Disconnection Failure	10 times		_		-		0			
Final Action At Disk Disconnection Failure	Enforced Disconnection						Ō			
Mirror Disk Tab		L L								
Auto Mirror Initial Construction	On						0			
Auto Mirror Recovery	On						Ō			
Retry Interval At Disk Disconnection Failure	3 seconds						0			
Retry Count At Disk Disconnection Failure	Specify the count						O			
Set Retry Count At Disk Disconnection Failure	10 times						Ō			
Final Action At Disk Disconnection Failure	Enforced Disconnection						Ō			
Account Tab							Ť			
Account List (Add, Remove, Edit)	T -		l l				0			
Auto Recovery Tab			<u> </u>				Ŭ			
Auto Return	On		1				О			
RIP Tab (Legacy)	311						Ŭ			
List of Network Address (Add, Remove, Edit)	1 -		I				О			
Power Saving Tab							$\vdash$			
Use CPU Frequency Control	Off		l l				О			
Ose Cr O r requericy Control	Oli									
Add Server		1	l	0		0				
Remove Server				0		0	<u> </u>			
Server Properties				0		0				
Info Tab										
Name	-		0							
Comment	-						0			
Interconnect LAN I/F Tab	1.7									
I/F Number (Add, Remove)	The order you added I/Fs			0						
IP Address (Edit) <sup>4</sup>	-									
IP Address (Up, Down)	-			0						
Public LAN I/F Tab										
I/F Number (Add, Remove)	The order you added I/Fs			0						
IP Address (Edit) <sup>4</sup>	-									
IP Address (Up, Down)	-			0						
COM I/F Tab										
I/F Number (Add, Remove)	The order you added I/Fs			0						
Device (Edit, Up, Down)	-			0						
Disk I/F Tab										
I/F Number (Add, Remove)	The order you added I/Fs			0						
Mount Point (Edit, Up, Down)	-			0						
GUID (Edit, Up, Down)	-			0						
Ping I/F Tab										
I/F Number (Add, Remove)	The order you added I/Fs			0						
Use	On-			0						
IP Address (Edit, Up, Down)				0						
Majority I/F Tab			<u> </u>							
I/F Number (Add, Remove)	The order you added I/Fs		1	0						
Use Majority Resolution	On-		-	0						
Mirror Connect I/F Tab	1									
I/F Number (Add, Remove)	The order you added I/Fs	10	1							
IP Address (Edit) <sup>4</sup>	-	0	<del>                                     </del>							
Warning Light Tab			<u> </u>				<b>—</b>			
I/F Number (Add, Remove)	The order you added I/Fs									
	The order you added I/FS			0			├			
IP Address (Edit, Up, Down)	<u> </u>		<u> </u>	U			_			
BMC Tab	The Onderson III	1								
Number (Add, Remove)	The Order you added		<u> </u>	0			<u> </u>			
IP Address (Edit)	-			0			<u> </u>			
User Name	-			0						

\_

<sup>&</sup>lt;sup>4</sup> Be careful when you change the host name or IP address of a server. For how to change the host name or IP address, see Section III of this guide.

Parameters	Default	L	w to	cha	ngo		
r arameters	Delauit	1	2	3	4	5	6
Password	-		_	Ö	-		
HBA Tab							
HBAs to be managed by the cluster system	-	О					
Partitions to be managed by the cluster system	-			0			
j j			I		l l		
Add Server Group				0			
Remove Server Group			0				
Server Group Properties							
Info Tab							
Name	failover		0				
Comment	-						0
Server Group Tab	T			•			
Order (Up, Down)	The order you added to "Servers		0				1
	that can run the Group."						L
Add	-		0				<u> </u>
Remove	-		0				L
Add Group			I	0	1		
Remove Group			1	0	0		
Group Properties							
Info Tab							
Name	1-		Г	0	0		
Comment	-			_			0
Startup Server Tab							$\vdash$
Order (Up, Down)	The order you added to "Servers		l				
order (op, zemi)	that can run the Group."			0			1
Name (Add, Remove)	-			0			
Attribute Tab							
Startup Attribute	Auto Startup			0			
Failover Exclusive Attribute	Off			0			
Failover Attribute	Auto Failover			0			
Failback Attribute	Manual Failback			0			
Logical Service Tab							
Logical Service Name (Add, Remove)	-						0
Server Group Tab							
Add, Remove, Up, Down	The order you added to "Servers		0				
	that can run the Group."						<u> </u>
Add Group Resource				0			<u> </u>
Remove Group Resource				0	0		
Group Resource Common Properties Info Tab							
Name	Default value per each resource			О	0		
Comment	Delault value per each resource			0	U		0
Application Resource Properties							$\cup$
Dependency Tab							
Follow the default dependence	l On						
1 onew the delatit dependence	• floating ip resources						1
	• virtual IP resources						1
	<ul> <li>virtual computer name</li> </ul>						ł
	disk resources			0	0		ł
	mirror disk resources						ł
	print spooler resources						i
	registry synchronization						
	CIFS resources						
Domandant Passurasa (Add. Darrasus)	NAS resource		<u> </u>				<u> </u>
Dependent Resources (Add, Remove)	<u> </u> -			0	0		
Settings Tab Retry Count	Zoro						
Failover Target Server	Stable operation server		-	0			<b>-</b>
I allover rarget Server	Stable operation server			U			

	eters	Default	Hov 1	v to c	cha 3		_	F
Foilove	er Threshold	Cot as many as the number of	1	2	3	4	5	+
Fallove	rinresnoid	Set as many as the number of the servers			0			
Set Nu	umber	the servers	-		0			+
	action at Activation Failure Detection	No Operation (Not activate next	-		0			+
i illai A	ction at Activation Failure Detection	resources)		1	0			
Evecut	te Script before Final Action	Off		_				$^{+}$
	Count at Deactivation Failure	zero		_	0			$^{+}$
	Action at Deactivation Failure	Stop the cluster service and shut			_			$^{+}$
i iliai A	ction at Deactivation Failure	down OS.		1	0			
Execut	te Script before Final Action	Off		-				$^{+}$
Details		1 011						4
	ent Type	Resident				0		Ŧ
Start P		-	++			0		+
Stop P		-	+ +	-		U		$^{+}$
	oplication Resource Tuning	-						_
	operties							
FIG	Parameter Tab							-
	Start Script Synchronous, Asynchronous	Cynobronous		_	1			Ŧ
	Start Script Synchronous, Asynchronous  Start Script Timeout	Synchronous 1800 seconds						+
			$\vdash$	-+				4
	Stop Script Synchronous, Asynchronous	Synchronous 1800 seconds	$\longmapsto$	$\dashv$				4
	Stop Script Timeout		$\sqcup$					4
	Target VCOM Resource Name	-				0		4
	Allow to Interact with Desktop	Off				0		
	Start Tab	_						
	Current Directory	-						
	Option Parameter	-						
	Window Size	Hide						
	Exec User Domain	-				0		
	Exec User Account	-				0		Ī
	Exec User Password	-				0		Ī
	Execute from the Command Prompt	Off						Ī
	Stop Tab							
	Current Directory	-						T
	Option Parameter	-						T
	Window Size	Hide						T
	Exec User Domain	-						Ť
	Exec User Account	-						Ť
	Exec User Password	-						t
	Execute from the Command Prompt	Off		_				t
oating	IP Resource Properties							İ
Depen	dency Tab							-
	the default dependence	On (No default is set)			0	0		Ī
	dent Resources (Add, Remove)	-	+		ŏ	Ō		t
Setting								
	Count at Activation Failure	5 times			0			Ť
	er Target Server	Stable Operation Server			Ö			t
	er Threshold	Set as many as the number of	+					t
i anove	/ 1111001101G	the servers			0			
Specify	y the count	5517515	+	-+	$\overline{}$			$\dagger$
	•	-			0			
Final A	action at Activation Failure Detection	No Operation (Not activate next			0			Ī
		resources)			۷			
Execut	te Script before Final Action	Off						Ť
Retry C	Count at Deactivation Failure	zero			0			1
Final A	action at Deactivation Failure	Stop the cluster service and shut		$\neg$	$\overline{}$			t
		down OS.			0			
F	te Script before Final Action	Off	+	$\dashv$				t
Execut	- T-L							1
Details	s lad							
Details IP Add		T -	П			0		T

Paramete	ers	Default	Но	w to	Cha	nge		
. aramet		Joidan	1	2	3	4	5	6
F	Run ping	On						С
r	ping Interval	1 second						С
	ping Timeout	1000 milliseconds						С
l r	ping Retry Count	5 times						С
	ping Forced FIP Activation	Off						С
	Resource Properties							
Depende								
Follow th	e default dependence	On (No default is set)			0	0		
	ent Resources (Add, Remove)	-			Ō	0		
Settings								
Retry Co	unt at Activation Failure	zero	l	l	О			
Failover	Target Server	Stable operation server			Ō			-
	Threshold	Set as many as the number of						
		the servers			0			
Specify th		-			0			
Final Acti	ion at Activation Failure Detection	No Operation (Not activate next resources)			0			
Execute	Script before Final Action	Off						C
Retry Co	ount at Deactivation Failure	zero	<b> </b>		0			È
	ion at Deactivation Failure	Stop the cluster service and shut	-	-				⊢
		down OS.			0			
	Script before Final Action	Off						(
Details T								
Mirror Dis		1			0	0		
Data Part	tition Drive Letter	-			0	0		
Cluster P	Partition Drive Letter	-			0	0		
Cluster P	Partition Offset Index	0			0	0		
Servers t	that can run the group (Add, Remove)	-	0					
	tition (Edit)	-			0	0		
	Partition (Edit)	-			ō	0		
	or Disk Resource Tuning Properties		<u> </u>					
	Mirror Tab							_
	Execute the initial mirror construction	l On	ı	l	0	0		
	Mirror Connect Timeout	20 seconds			0	0		
		2048 [KB]			0	0		
	Request Queue Maximum Size							
	Mode	Synchronous			0	0		
	Kernel Queue Size	2048 [KB]			0	0		
	Application Queue Size	2048 [KB]			0	0		
	Thread Timeout	30 seconds			0	0		L
	Communication Band Limit	Unlimited	L	L	0	0		1
	History Files Store Folder	-			0	0		
	History Files Size Limit	Unlimited			0	0		Г
egion, e,	nchronization Resource Properties							
Depende	ency Tab							
Depende	ency Tab	On						ļ
Depende	ency Tab  ee default dependence	_						
Depende	ency Tab	floating ip resources						
Depende	ency Tab	<ul><li>floating ip resources</li><li>virtual IP resources</li></ul>			0	0		
Depende	ency Tab	<ul><li>floating ip resources</li><li>virtual IP resources</li><li>virtual computer name</li></ul>			0	0		
Depende	ency Tab	<ul> <li>floating ip resources</li> <li>virtual IP resources</li> <li>virtual computer name</li> <li>disk resources</li> </ul>			0	0		
Depende	ency Tab	<ul> <li>floating ip resources</li> <li>virtual IP resources</li> <li>virtual computer name</li> <li>disk resources</li> <li>mirror disk resources</li> </ul>			0	0		
Depende Follow the	ency Tab	<ul> <li>floating ip resources</li> <li>virtual IP resources</li> <li>virtual computer name</li> <li>disk resources</li> </ul>			0	0		
Depende Follow the	ency Tab ue default dependence ent Resources (Add, Remove)	<ul> <li>floating ip resources</li> <li>virtual IP resources</li> <li>virtual computer name</li> <li>disk resources</li> <li>mirror disk resources</li> </ul>						
Depende Settings	ency Tab ue default dependence ent Resources (Add, Remove)	<ul> <li>floating ip resources</li> <li>virtual IP resources</li> <li>virtual computer name</li> <li>disk resources</li> <li>mirror disk resources</li> </ul>						
Depende  Follow the  Depende  Settings  Retry Con	ency Tab ue default dependence ent Resources (Add, Remove) a Tab unt at Activation Failure	floating ip resources     virtual IP resources     virtual computer name     disk resources     mirror disk resources     print spooler resources     zero			0			
Depende  Depende  Settings  Retry Cor  Failover	ency Tab  le default dependence  ent Resources (Add, Remove)  a Tab  unt at Activation Failure Target Server	floating ip resources     virtual IP resources     virtual computer name     disk resources     mirror disk resources     print spooler resources     zero  Stable operation server			0			
Depende Follow the Depende Settings Retry Cor Failover	ency Tab ue default dependence ent Resources (Add, Remove) a Tab unt at Activation Failure	• floating ip resources     • virtual IP resources     • virtual computer name     • disk resources     • mirror disk resources     • print spooler resources     -      zero     Stable operation server     Set as many as the number of			0			
Depende  Follow the Depende  Settings  Retry Correction Failover  Failover	ency Tab  te default dependence  ent Resources (Add, Remove)  Tab  tunt at Activation Failure  Target Server  Threshold	floating ip resources     virtual IP resources     virtual computer name     disk resources     mirror disk resources     print spooler resources     zero  Stable operation server			0 0 0			
Depende  Follow the Depende  Settings  Retry Cor  Failover  Failover  Specify the Specify	ency Tab  te default dependence  ent Resources (Add, Remove)  Tab  tunt at Activation Failure  Target Server  Threshold	• floating ip resources     • virtual IP resources     • virtual computer name     • disk resources     • mirror disk resources     • print spooler resources     -      zero     Stable operation server     Set as many as the number of			0			

Parameters	Default	Но	w to				
		1	2	3	4	5	6
Execute Script before Final Action	Off						0
Retry Count at Deactivation Failure	zero			0			
Final Action at Deactivation Failure	Stop the cluster service and shut down OS.			0			
Execute Script before Final Action	Off						0
Details Tab	] 011						U
Registry List (Add, Remove)	1 1			0	0	l l	Π
Registry Synchronization Resource Tuning							
Parameter Tab	rioperties						
Delivery Interval	1 second			0		Ι	
Script Resource Properties	i second						
Dependency Tab							
	0.5					Г	1
Follow the default dependence	On						
	floating ip resources						
	virtual IP resources						
	virtual computer name						
	disk resources			_	_		
	mirror disk resources			0	0		
	• print spooler resources						
	<ul> <li>registry synchronization</li> </ul>						
	resource						
	CIFS resource						
	NAS resource						
Dependent Resources (Add, Remove)	-			0	0		
Settings tab							
Retry Count	zero			0			
Failover Target Server	Stable operation server			0			
Failover Threshold	Set as many as the number of			_			
	the servers			0			
Specify the count	1 -			0			
Final Action at Activation Failure Detection	No Operation (Not activate next			_			├
I iliai Action at Activation I aliule Detection	resources)			0			
Execute Script before Final Action	Off						0
Retry Count at Deactivation Failure	zero			0			-
Final Action at Deactivation Failure				0			<u> </u>
Final Action at Deactivation Failure	Stop the cluster service and shut down OS.			0			
Execute Script before Final Action	Off						0
Details Tab							
Script (Add, Remove, Edit)	-						О
Script Resource Tuning Properties							
Parameter Tab							
Start Script Synchronous, Asynchronous	Synchronous						0
Start Script Timeout	1800 seconds				1	<b> </b>	ō
Stop Script Synchronous, Asynchronous	Synchronous				1		0
Stop Script Synchronous, Asynchronous  Stop Script Timeout	1800 seconds	-	-		<b> </b>	<del>                                     </del>	0
Target VCOM Resource Name	1000 Seconds					1	0
	Off	-	-		<u> </u>	<del>                                     </del>	
Allow to Interact with Desktop	Off						0
Disk Resource Tuning Properties							
Dependency Tab	On (No data 10)					1	
Follow the default dependence	On (No default is set)			0	0		
Dependent Resources (Add, Remove)	-			0	0		
Settings Tab							
Failover Target Server	Stable operation server			0			
Failover Threshold	Set as many as the number of			0			
	the servers						
Specify the count	-			0	1		
Final Action at Activation Failure Detection	No Operation (Not activate next				1	<b> </b>	
and a second of	resources)			0			
Execute Script before Final Action	Off	<del>                                     </del>	<del>                                     </del>		<b> </b>	<del>                                     </del>	0
				0	<u> </u>		
Retry Count at Deactivation Failure	zero						

	Parameters	Default	Но	w to	cha	ngo	_	
	r ai ainetei s	Delault	1	2	3	4	5	6
	Final Action at Deactivation Failure	Stop the cluster service and shut	•	_		•		
		down OS.			0			
	Execute Script before Final Action	Off						0
	Details Tab							
	Drive Letter				0	0		
	Servers that can run the group (Add, Remove)				0	0		
	GUID (Edit)				0	0		
S	ervice Resource Properties							
	Dependency Tab							
	Follow the default dependence	On			0	0		
		floating IP resources						
		virtual IP resources						
		virtual computer name						
		resources  • disk resources						
		mirror disk resources						
		• print spooler resources						
		• registry synchronization						
		CIFS resources						
		NAS resource						
,	Dependent Resources (Add, Remove)	-			0	0		
	Settings Tab							
	Retry Count at Activation Failure	zero			0			1
	Failover Target Server	Stable operation server			0			
	Failover Threshold	Set as many as the number of			0			
	Tallovoi Tilloonola	the servers						
	Specify the count	-			0			
	Final Action at Activation Failure Detection	No Operation (Not activate next						
	Timar Addition at Addition Famor Decodion	resources)			0			
	Execute Script before Final Action	Off						0
	Retry Count at Deactivation Failure	zero			0			
	Final Action at Deactivation Failure	Stop the cluster service and shut						
	Tillal Action at Deactivation Fallare	down OS.			0			
	Execute Script before Final Action	Off						0
	Details Tab							
	Service Name					0		1
	Service Resource Tuning Properties							l
	Parameter Tab							
	Start Script Synchronous, Asynchronous	Synchronous		Γ				0
	Start Script Timeout	1800 seconds						0
	Stop Script Synchronous, Asynchronous	Synchronous						0
	Stop Script Timeout	1800 seconds						0
	Target VCOM Resource Name	-		1		0		$\vdash$
	Service Tab							l
	Start Parameters	-				0		
	Do not assume it as an error when the	Off		1				
	service is already started					0		
Р	rint Spooler Resource Properties							
	Dependency Tab							
	Follow the default dependence	On			0	0		
	•	disk resources						
		mirror disk resources						
		NAS resource						
	Dependent Resources (Add, Remove)	-			0	0		
	Settings Tab							
	Retry Count at Activation Failure	zero			0			
	Failover Target Server	Stable operation server			0			
	Failover Threshold	Set as many as the number of			0			
		the servers						
	Specify the count	-			0			

Parameters	Default	Но	w to	cha	inge		
		1	2	3	4	5	6
Final Action at Activation Failure Detection	No Operation (Not activate next resources)			0			
Execute Script before Final Action	Off						0
Retry Count at Deactivation Failure	zero			0			_
Final Action at Deactivation Failure	Stop the cluster service and shut			$\vdash$			
	down OS.			0			
Execute Script before Final Action	Off						0
Details Tab							
Printer Name	-			0			
Partition	-			0			
Spool Directory	-			0			
Virtual Computer Name Resource Properties							
Dependency Tab							
Follow the default dependence	On			0	0		
	floating IP resources						
	virtual IP resources						
Dependent Resources (Add, Remove)	-			0	0		
Settings Tab			<u> </u>				
Retry Count at Activation Failure	5 times			О			
Failover Target Server	Stable operation server			ō			
Failover Threshold	Set as many as the number of			0			
	the servers						
Specify the count	-			0			
Final Action at Activation Failure Detection	No Operation (Not activate next resources)			0			
Execute Script before Final Action	Off						0
Retry Count at Deactivation Failure	zero			0			
Final Action at Deactivation Failure	Stop the cluster service and shut						-
	down OS.			0			
Execute Script before Final Action	Off						0
Details Tab							
Virtual Computer Name	-			0	0		
Target FIP Resource Name	-			0	0		
Virtual Computer Name Resource Tuning							
Properties							
Parameter Tab							
Dynamic Registration to DNS	Off			0	0		
Associated IP address	FIP			0	0		
Virtual IP Resource Properties							
Dependency Tab							
Follow the default dependence	On (No default is set)			О	0		
Dependent Resources (Add, Remove)	-			0	0		
Settings Tab			ı				
Retry Count at Activation Failure	5 times		Π	0	Π		
Failover Target Server	Stable operation server			0			
Failover Threshold	Set as many as the number of			0			
	the servers						
Specify the count	-			0			
Final Action at Activation Failure Detection	No Operation (Not activate next resources)			0			
Execute Script before Final Action	Off						0
Retry Count at Deactivation Failure	zero		1	0			Ť
Final Action at Deactivation Failure	Stop the cluster service and shut down OS.			0			
Execute Script before Final Action	Off		-				0
Details Tab			<u> </u>				
IP Address	-				0		
Net Mask		-	<b> </b>	<u> </u>	0		
	-		<u> </u>	ļ	_		<u> </u>
Destination IP Address	-				0		<u> </u>
Source IP Address	<u> </u>		L	<u> </u>	0		<u> </u>
	Franco Chroton V O 4 for Windo						

	Danama dana	Default		1 -	-1			
	Parameters	Default	1 1	w to	cna 3	inge 4	5	6
	Send Interval	30 seconds		2	3	0	J	0
	Use Routing Protocol	RIPver1				0		-
	Virtual IP Resource Tuning Properties	IXII VEI I						
	Parameter Tab							
	Run ping		Π					О
		On						
	Interval	1 second						0
	timeout	1000 milliseconds						0
	Retry Count	5 times						0
	Forced VIP Activation	Off						0
	RIP Tab							
	Next Hop IP Address	-				0		
	Motrio					_		<u> </u>
	Metric	3				0		
	Port Number	520				0		
	RIPng Tab	<u> </u>						
	Metric	1				0		
	Port Number	521		-		0		-
CIF	S Resource Properties	V2 1				0		
CIF								
	Dependency Tab	On						
	Follow the default dependence	On • disk resources				_		
		disk resources     mirror disk resources			0	0		
	Department Description (Add Demarks)	• militor disk resources			_	_		
	Dependent Resources (Add, Remove)				0	0		
	Settings Tab	7						
	Retry Count at Activation Failure	Zero			0			
	Failover Target Server	Stable operation server			0			<u> </u>
	Failover Threshold	Set as many as the number of			0			
		the servers			_			
	Specify the count	-			0			
	Final Action at Activation Failure Detection	No Operation (Not activate next			0			
		resources)			_			
	Execute Script before Final Action	Off						0
	Retry Count at Deactivation Failure	zero			0			
	Final Action at Deactivation Failure	Stop the cluster service and shut			0			
		down OS.			Ŭ			
	Execute Script before Final Action	Off						0
	Details Tab							
	Auto-saving of	Off				0		
	shared configuration of drive							
	Target drive	-				0		
	Shared configuration file	-				0		
	Shared Name	-				0		
	Folder	-				0		
	Comment	-				0		
	CIFS Resource Tuning Properties							
	Cache Tab							
	Cache Enable	Off				0		
	Cache Setting	Automatic cache				0		
	User Tab							
	User Count Limit	Unlimited				0		
	Access Permission	everyone read				0		
		-						
NA	S Resource Properties							
	-							
	Dependency Tab Follow the default dependence	On						
	Follow the detault dependence	On • Floating IP resource			0	0		
		Virtual IP resource				U		
		VIII.Ual IF 1650UICE	<u> </u>	<u> </u>				

Pa	arameters	Default	Ho	w to	cha	nge		
			1	2	3	4	5	6
De	ependent Resources (Add, Remove)				0	0		
Se	ettings Tab							
	etry Count at Activation Failure	zero			0			
Fa	ailover Target Server	Stable operation server			0			
Fa	ailover Threshold	Set as many as the number of			0			
		the servers						
	pecify the count	-			0			
Fi	nal Action at Activation Failure Detection	No Operation (Not activate next			0			
<del> </del>		resources)						$\sqsubseteq$
	Recute Script before Final Action	Off						0
	etry Count at Deactivation Failure nal Action at Deactivation Failure	Zero			0			<u> </u>
FII	nai Action at Deactivation Failure	Stop the cluster service and shut down OS.			0			
	kecute Script before Final Action	Off						0
	etails Tab	011						
	ive	T -		Ι	Ι	0		
	older	-				0		
	ser name	-				0		
	assword	-				0		
	NAS Resource Tuning Properties							
	Disconnection Tab							
	Retry Count	3				0		
	Retry Interval	5				0		
Hybr	id Disk Resource Properties							
	ependency Tab							
	bllow the default dependence	On (No default is set)		I	0	О		
	ependent Resources (Add, Remove)	On (No default is set)			0	0		
	ettings Tab							
	etry Count at Activation Failure	0 times		Ι	О	l		
	allover Target Server	Stable Operation Server			0			
	allover Threshold	Set as many as the number of			0			
Ι, ,	and von Trindonoid	the servers			~			
Sr	pecify the count	-			0			
	nal Action at Activation Failure Detection	No Operation (Not activate next						
		resources)			0			
Ex	cecute Script before Final Action	Off						0
	etry Count at Deactivation Failure	zero			0			
	nal Action at Deactivation Failure	Stop the cluster service and shut						
		down OS.			0			
Ex	cecute Script before Final Action	Off						0
De	etails Tab							
	ybrid disk number	1			0	0		
	ata partition drive letter	-			0	0		
	uster partition driver letter	<u>-</u>			0			
CI	uster partition offset index	0			0	0		
	Hybrid Disk Resource Tuning							
	Properties							
	Mirror Tab							
	Execute the initial mirror construction	On			0	0		
	Mirror Connect Timeout	20 seconds			0	0		
	Request Queue Maximum Size	2048 KB			0	_		
	Mode Kornel Queue Size	Synchronous		-	0	0		
	Kernel Queue Size	2048 KB		-	0	0		
	Application Queue Size Thread Timeout	2048 KB			0	0		<b></b>
		30 seconds		-	00			<u> </u>
	Communication Band Limit	Unlimited		-	0	_		<u> </u>
	History Files Store Folder	- I Inlimited		-	0	0		<u> </u>
A cl al	History Files Size Limit  Monitor Resource	Unlimited			0	0		<u> </u>
					0			<u> </u>
Kem	ove Monitor Resource	Funnanchistan V 2.4 fan Winder		<u> </u>	0			L

Parameters	Default	How to			
			3		5
onitor Resource Properties					
Info Tab					
Name	-		0		
Comment	-				
oplication Monitor Resource Properties					
Monitor Tab					
Interval	60 seconds		0		
Timeout	60 seconds		0		
Retry Count	1 time		0		
Wait Time to Start Monitoring	0 second		0		
Monitor Timing	Active (fixed)		0		
Target Resource	-		0		
Error Detection Server					
Error Detection Server	All Servers		О		T
Servers that can run the Group (Add,	-		0		
Remove)					
Error Detection Tab					
Recovery Target	T -		О	T	T
Reactivation Threshold	3 times (if the recovery target is		0	<del>-  </del>	$\dashv$
	other than clusters)				
Failover Target Server	Stable operation server		0		$\dashv$
Failover Threshold	Set as many as the number of		0		_
Tallover Trifeshold	the servers				
Specify the count	-		0		-
Final Action	No Operation		0		_
Execute Script before Final Action	Off				
	Oli		$\perp$		
sk RW Monitor Resource Properties					
Monitor Tab					
Interval	30 seconds		0		
Timeout	300 seconds		0		
Retry Count	zero		0		
Wait Time to Start Monitoring	0 second		0		
Monitor Timing	Active (fixed)		0		
Target Resource	-		0		
Error Detection Server					
Error Detection Server	All Servers		0		
Servers that can run the Group (Add,	-		0		
Remove)					
Error Detection Tab					
Recovery Target	-		0		
Reactivation Threshold	zero (if the recovery target is		0		
	other than clusters)				
Failover Target Server	Stable Operation Server		0		
Failover Threshold	Set as many as the number of		0		
	the servers				
Specify the count	-		0	<u> </u>	$\dashv$
Final Action	No Operation		Ō		$\dashv$
Execute Script before Final Action	Off				$\dashv$
Parameter Tab					
File Name	I -		ТОТ	T	_
I/O size	2000000 [byte]	+ +	0	+	
Action on Stall			0		4
ACTION ON STAIL	Generate an Intentional Stop				
esting ID Meniter Pessures Drawarties	EIIUI				
oating IP Monitor Resource Properties					
Monitor Tab					
Interval	60 seconds		0		ļ
	60 seconds		0		
Timeout		1 1			
Timeout Retry Count	1 time		0		
Timeout			00		1

Parameters	Default		w to				
Target December		1	2	3	4	5	6
Target Resource Error Detection Server	] -			0			
Error Detection Server	All Servers		П	0			
Servers that can run the Group (Add,				0			
Remove)							l
Error Detection Tab			11				
Recovery Target	T -			0			
Reactivation Threshold	3 times (if the recovery target is			0			_
	other than clusters)						l
Failover Target Server	Stable operation server			0			
Failover Threshold	Set as many as the number of			0			
	the servers						
Specify the count	-			0			
Final Action	No Operation			0			<u> </u>
Execute Script before Final Action	Off						~
Parameter Tab							
Monitor NIC Link Up/Down	Off-						_
Monitor Resource Properties							
Monitor Tab							
Interval	60 seconds			0			L
Timeout	60 seconds			0			<u> </u>
Retry Count	1 time			0			<u> </u>
Wait Time to Start Monitoring	0 second			0			<u> </u>
Monitor Timing	Active (fixed)			0			<u> </u>
Target Resource	-			0			_
Error Detection Server	411.0						
Error Detection Server	All Servers			0			<u> </u>
Servers that can run the Group (Add,	-			0			l
Remove) Error Detection Tab							_
	-		1 1	$\overline{}$			
Recovery Target Reactivation Threshold	3 times (if the recovery target is			0			_
Reactivation Threshold	other than clusters)						l
Failover Target Server	Stable operation server		-	0			_
Failover Threshold	Set as many as the number of			0			
Tallover Titleshold	the servers						l
Specify the count	-			0			Г
Final Action	No Operation			0			
Execute Script before Final Action	Off						
Parameter Tab	Oll						_
IP Address (ADD, Remove, Edit)	T _		1 1				
Ping Timeout	1000 milliseconds		-				H
rror Connect Monitor Resource Properties	1000 miniseconds						_
Monitor Tab							_
Interval	60 seconds		1 1	0			F
Timeout	60 seconds			Ö			
Retry Count	zero			0			_
Wait Time to Start Monitoring	0 second			0			_
Monitor Timing	Active (fixed)			0			_
Target Resource	-		+ +	Ö			_
Error Detection Server							
Error Detection Server	All Servers		1	0			f
				Ö			_
	1						l
Servers that can run the Group (Add,			1 1				
Servers that can run the Group (Add, Remove)  Error Detection Tab	1-			0			
Servers that can run the Group (Add, Remove)  Error Detection Tab  Recovery Target							_
Servers that can run the Group (Add, Remove)  Error Detection Tab  Recovery Target  Reactivation Threshold	zero			0			
Servers that can run the Group (Add, Remove)  Error Detection Tab  Recovery Target							

Parameters	Default	How to				
		1 2	3	4	5	6
Final Action	No Operation		0			
Execute Script before Final Action	Off					О
Parameter Tab						
Mirror Disk Resource	-		0			
rror Disk Monitor Resource Properties						
Monitor Tab	I 00					
Interval	30 seconds 999 seconds		0			
Timeout Petry Count			0			
Retry Count World Time to Start Manitoring	zero		0			
Wait Time to Start Monitoring	0 second		0			
Monitor Timing Target Resource	Active (fixed)		0			
Error Detection Server	-		U			
Error Detection Server	All Servers			1		
	All Servers		0			_
Servers that can run the Group (Add,	-		0			i i
Remove) Error Detection Tab						
	T -		0			
Recovery Target Reactivation Threshold			0			
Failover Target Server	Stable operation conver		0			
Failover Target Server Failover Threshold	Stable operation server  Set as many as the number of		0			
raiiuvei IIIIesiiuiu	the servers		١٠			ì
Specify the count	tne servers		0			
Final Action	No Operation		0			
Execute Script before Final Action	Off		U			C
	Oil					_
Parameter Tab						
Mirror Disk Resource	-		0			_
C Link Up/Down Monitor Resource Properties  Monitor Tab						
	I 00	1 1				
Interval	60 seconds		0			
Timeout	60 seconds		_			
Retry Count	1 [time]		0			
Wait Time to Start Monitoring	0 second		0			
Monitor Timing	Always		0			
Target Resource	-		0			_
Error Detection Server	LAUG					
Error Detection Server	All Servers		0			
Servers that can run the Group (Add,	-		0			ì
Remove)						
Error Detection Tab	T	1 1				
Recovery Target	- 2 times -		0			
Reactivation Threshold	3 times		0			
Failover Target Server	Stable operation server		0			
Failover Threshold	Set as many as the number of		0			i
On a site of the annual to	the servers					
Specify the count	- No Operation		0			
Final Action	No Operation		0			_
Execute Script before Final Action	Off					С
Parameter Tab						_
Individually Set Up Servers (Add, Remove, Edit)	-					С
ulti Target Monitor Resource Properties						
Monitor Tab						
Interval	60 seconds		0			
Timeout	60 seconds		0			
Retry Count	1 time		0			
Wait Time to Start Monitoring	0 second		0			
Monitor Timing	Always		0			
Target Resource	-		0			_
Error Detection Server			_			
Error Detection Server	All Servers		0	T		_

Parameters	Default	Но	w to	cha	ngo		
r didilicters	Delauit	1	2	3	4	5	6
Servers that can run the Group (Add,	-	•		0		<b>.</b>	
Remove)				0			İ
Error Detection Tab							
Recovery Target	I -	l		0	l		
Reactivation Threshold	3 times			0			
Failover Target Server	Stable operation server			0			
Failover Threshold	Set as many as the number of			0			-
	the servers						
Set Number	-			0			
Final Action	No Operation			0			
Execute Script before Final Action	Off						0
Parameter Tab							
Monitor Resource List (Add, Remove)	-			0			
Registry synchronous Monitor Resource							
Properties							
Monitor Tab							
Interval	60 seconds			0			
Timeout	60 seconds			0			
Retry Count	1 time	<b> </b>		Ō	<b> </b>		
Wait Time to Start Monitoring	0 second	l -		0	l -		
Monitor Timing	Active	<b> </b>		0	<b> </b>		$\vdash$
Target Resource	-			0			<b>-</b>
Error Detection Server	-			U			
	I All Coming		I 1	_			
Error Detection Server	All Servers			0			
Servers that can run the Group (Add,	-			0			İ
Remove)							
Error Detection Tab							
Recovery Target	-			0			
Reactivation Threshold	3 times			0			
Failover Target Server	Stable operation server			0			
Failover Threshold	Set as many as the number of the servers			0			
Specify the count	-			0			
Final Action	No Operation			0			
Execute Script before Final Action	Off						0
Disk TUR Monitor Resource Properties							Ŭ
Monitor Tab							
Interval	60 seconds			0			
	** *********			0			
Timeout	300 seconds						
Retry Count	zero			0			
Wait Time to Start Monitoring	0 second			0			
Monitor Timing	Always			0			<u> </u>
Target Resource	-			0			<u> </u>
Error Detection Server							
Error Detection Server	All Servers			0			
Servers that can run the Group (Add,	-			0			
Remove)							l
Error Detection Tab							
Recovery Target	-			0			
Reactivation Threshold	zero			0			
Failover Target Server	Stable operation server			0			
Failover Threshold	Set as many as the number of the servers			0			
Specify the count	-	<b> </b>		0	<b> </b>		<del>                                     </del>
Final Action	No Operation			0			$\vdash$
Execute Script before Final Action	Off			)			_
	Oil	L			L		0
Parameter Tab							
Disk Resource	-			0			<u>L</u>
Service Monitor Resource Properties							
Monitor Tab							
							-

	Parameters	Default	Но	w to	cha	nge		
	T dramotors	Boladit	1	2	3	4	5	6
П	Interval	60 seconds			0			
i t	Timeout	60 seconds			0			
ÌΙ	Retry Count	1 time			0			
i t	Wait Time to Start Monitoring	0 second			0			
i t	Monitor Timing	Active (fixed)			0			
i t	Target Resource	-			0			
i t	Error Detection Server							
	Error Detection Server	All Servers			0			
	Servers that can run the Group (Add,	-			0			
	Remove)							
_	Error Detection Tab							
	Recovery Target	-			0			<u> </u>
1	Reactivation Threshold	3 times			0			
	Failover Target Server	Stable operation server			0			<u> </u>
	Failover Threshold	Set as many as the number of			0			
	0 '' 1	the servers						<u> </u>
	Specify the count	-			0			<u> </u>
	Final Action	No Operation			0			Ļ
	Execute Script before Final Action	Off	<u> </u>					0
Pr	int Spooler Monitor Resource Properties							
	Monitor Tab							
	Interval	60 seconds			0			
	Timeout	60 seconds			0			
	Retry Count	1 time			0			
	Wait Time to Start Monitoring	0 second			0			
	Monitor Timing	Active (fixed)			0			
	Target Resource	1			0			
	Error Detection Server							
	Error Detection Server	All Servers			0			
	Servers that can run the Group (Add,	-			0			
	Remove)							
	Error Detection Tab							
	Recovery Target	-			0			
	Reactivation Threshold	3 times			0			
	Failover Target Server	Stable operation server			0			
	Failover Threshold	Set as many as the number of			0			
		the servers						
	Specify the count	-			0			
	Final Action	No Operation			0			
	Execute Script before Final Action	Off						0
	rtual Computer Name Monitor Resource					1		
Pr	operties							
	Monitor Tab							
	Interval	60 seconds			0			<u> </u>
	Timeout	60 seconds			0			
	Retry Count	1 time			0			
	Wait Time to Start Monitoring	0 second			0			
	Monitor Timing	Active (fixed)			0			
	Target Resource	-			0			
	Error Detection Server							
	Error Detection Server	All Servers			0			
	Servers that can run the Group (Add,	-			0			
	Remove)							<u> </u>
	Error Detection Tab							
	Recovery Target	-			0			<u> </u>
	Reactivation Threshold	zero			0			
-	Failover Target Server	Stable operation server			0			
					0	T		1
	Failover Threshold	Set as many as the number of			U			
	Failover Threshold  Specify the count	Set as many as the number of the servers			0			

Parameters	Default	Но	w to	cha	inge		
		1	2	3	4	5	6
Final Action	No Operation			0			
Execute Script before Final Action	Off						0
Virtual IP Monitor Resource Properties							
Monitor Tab							
Interval	60 seconds			0			
Timeout	60 seconds			0			
Retry Count	1 time			0			
Wait Time to Start Monitoring	0 second			0			
Monitor Timing	Active (fixed)			0			
Target Resource	-			0			
Error Detection Server							
Error Detection Server	All Servers			0			<u> </u>
Servers that can run the Group (Add,	-			0			l
Remove)							
Error Detection Tab							
Recovery Target	-			0			
Reactivation Threshold	3 times			0			
Failover Target Server	Stable operation server			0			<u> </u>
Failover Threshold	Set as many as the number of			0			l
	the servers						<u> </u>
Specify the count	-			0			
Final Action	No Operation			0			
Execute Script before Final Action	Off						0
CIFS Monitor Resource Properties							
Monitor Tab							
Interval	60 seconds			0			
Timeout	60 seconds			0			
Retry Count	1 time			0			
Wait Time to Start Monitoring	0 second			0			
Monitor Timing	Active (fixed)			0			
Target Resource	-			0			
Error Detection Server							
Error Detection Server	All Servers			0			
Servers that can run the Group (Add,	-			0			
Remove)							
Error Detection Tab							
Recovery Target	-			0			
Reactivation Threshold	3 times			0			
Failover Target Server	Stable operation server			0			
Failover Threshold	Set as many as the number of the servers			0			
Specify the count	-			0			
Final Action	No Operation			0			
Execute Script before Final Action	Off						0
Parameter Tab							
Access Check	No operation			0			
Path	-			0			
Check	Read			0			
NAS Monitor Resource Properties							
Monitor Tab							
Interval	60 seconds			0			
Timeout	60 seconds			0			
Retry Count	1 time			0			
Wait Time to Start Monitoring	0 second			0			
Monitor Timing	Active (fixed)			0			
Target Resource	-			Ō			
Error Detection Server							
Error Detection Server	All Servers			0			
Servers that can run the Group (Add,	-			0			
Remove)				ັ			l
	Franco Cluster V 2 4 for Windo	<u> </u>	<u> </u>	l	<u> </u>		

Parameters	Default				16
Error Detection Tab			<b>J</b>	T   J	
Recovery Target	l -		О		Т
Reactivation Threshold	3 times				
					+
Failover Threshold			Ō		+
1					
Specify the count	-		0		+
Final Action	No Operation		_		+
					10
Interval	30 coconds				Т
11 11					+
					+
					+
					4
	Active (fixed)				
	-		O		
	All Servers				
	-		0		
Error Detection Tab					
Recovery Target	-		0		
Reactivation Threshold	zero		0		T
Failover Target Server	Stable operation server		0		T
Failover Threshold					1
- Cameron Timesmena					
Specify the count	-		0		+
	No Operation		_		+
					<del>                                     </del>
·	Oli				10
	1				
	-				
Hybrid Disk TUR Monitor Resource Properties					
	1				
Interval			_		
Timeout	I .		_		
Retry Count	1   2   3   4   5   6				
Wait Time to Start Monitoring	1				
Monitor Timing	Active		0		Ī
Target Resource	-		0		1
Error Detection Server	All Servers		0		T
	-		0		1
	L				
	I -				$\overline{}$
			_		+
			_	_	+-
					+
Fallover Threshold			0		
Specify the count	uic Sciveis			_	+-
	No Operation			_	+
			U	_	+_
	Off				0
Parameter Tab					
Hybrid Disk Resource	-		0		
Custom Monitor Resource Properties					
Monitor Tab					
Interval	60 seconds		0		
Timeout				_	1
Retry Count				_	+
	1				

Parameters	Default	Но	w to	cha	inge		
		1	2	3	4	5	6
Wait Time to Start Monitoring	0 second			0			
Monitor Timing	Always			0			
Target Resource	-			0			
Error Detection Server							
Error Detection Server	All Servers			0			
Servers that can run the Group (Add,	-			0			
Remove)							
Error Detection Tab							
Recovery Target	-			0			
Reactivation Threshold	zero			0			
Failover Target Server	Stable operation server			0			
Failover Threshold	Set as many as the number of			0			
	the servers						
Specify the count	-			0			
Final Action	Stop cluster service and			0			
	shutdown OS						
Execute Script before Final Action	Off						0
Parameter Tab							
Monitor Script Path Type	Script created with this product			0			
Monitor Script Type	Synchronous			0			
Normal Return Value of Monitor Script	0			0			
DB2 Monitor Resource Properties							
Monitor Tab							
Interval	60 seconds			0			
Timeout	120 seconds			0			
Retry Count	2 times			0			
Wait Time to Start Monitoring	0 second			0			
Monitor Timing	Active (fixed)			0			
Target Resource	Stop the cluster service and shut			0			
Target Resource	down OS.			O			
Error Detection Server	down OS.						
	All Servers			0			
Error Detection Server	- All Servers			00			
Servers that can run the Group (Add,	-			O			
Remove)							
Error Detection Tab		1					
Recovery Target	-			0			
Reactivation Threshold	zero			0			
Failover Target Server	Stable operation server			0			
Failover Threshold	Set as many as the number of			0			
	the servers			_			
Specify the count	-			0			
Final Action	No Operation			0			
Execute Script before Final Action	Off						0
Parameter Tab							
Database Name	-			0			
Instance Name	DB2			0			
Password	-			0			
Monitor Table Name	DB2WATCH			0			
FTP Monitor Resource Properties							
Monitor Tab							
Interval	30 seconds			0			
Timeout	60 seconds			0			
Retry Count	3 times			0			
Wait Time to Start Monitoring	0 second			0			
Monitor Timing	Active (fixed)			0			
Target Resource	-			0			
Error Detection Server							
Error Detection Server	All Servers	1		0			
Servers that can run the Group (Add,	-			0			
Remove)							
15	<u>I</u>	l	ш		L		

Parameters	Default	Но	w to	cha	nge		
		1		3		5	6
Error Detection Tab							
Recovery Target	-			0			
Reactivation Threshold	zero			0			
Failover Target Server	Stable operation server			0			
Failover Threshold	Set as many as the number of			0			
	the servers						
Specify the count	-			0			
Final Action	No Operation			0			
Execute Script before Final Action	Off						С
Parameter Tab							<u> </u>
IP Address	127.0.0.1			0			
Port No	21			Ô			
User Name	<u>-</u>			Ō			
Password	-			0			
TP Monitor Resource Properties							<u> </u>
Monitor Tab							
Interval	30 seconds			0			Ι
Timeout	60 seconds		<b> </b>	0			_
Retry Count	3 times			0			_
Wait Time to Start Monitoring	0 second	-	1	00			
Monitor Timing	Active (fixed)			0			
Target Resource	-			0			
Error Detection Server				_			
Error Detection Server	All Servers			0			
Servers that can run the Group (Add,	-			0			
Remove)							
Error Detection Tab							
Recovery Target	-			0			
Reactivation Threshold	zero			0			
Failover Target Folder	Stable operation server			0			
Failover Threshold	Set as many as the number of			0			
	the servers						
Specify the count	-			0			
Final Action	No Operation			0			
Execute Script before Final Action	Off						C
Parameter Tab							
Connecting Destination	127.0.0.1			0			
Port Number	80			0			
Monitor URL	-			0			
Protocol	HTTP			0			
AP4 Monitor Resource Properties							
Monitor Tab							
Interval	30 seconds			0			
Timeout	60 seconds			0			
Retry Count	3 times	<del>                                     </del>		0			
Wait Time to Start Monitoring	0 second	-	1	0			_
Monitor Timing	Active (fixed)			0			
Target Resource	Active (lived)	-	1	00			_
Error Detection Server	<u> </u>			J			_
	All Contoro						
Error Detection Server	All Servers		<b>.</b>	0			
Servers that can run the Group (Add,	-			0			
Remove)							L
Error Detection Tab							
Recovery Target	-			0			
Reactivation Threshold	zero			0			L
Failover Target Server	Stable operation server			0			L
Failover Threshold	Set as many as the number of the servers			0			
Specify the count	=			0			-
Specify the count				_			

Parameters	Default		w to				
		1	2	3	4	5	1
Francis Occint before Final Action	shutdown OS						Ļ
Execute Script before Final Action	Off						_ (
Parameter Tab							
IP Address	127.0.0.1			0			L
Port Number	143			0			Ļ
User Name	-			0			Ļ
Password	-			0			Ļ
Certification Method	AUTHENTICATELOGIN			0			L
DBC Monitor Resource Properties							
Monitor Tab							
Interval	60 seconds			0			L
Timeout	120 seconds			0			
Retry Count	2 times			0			
Wait Time to Start Monitoring	0 second			0			
Monitor Timing	Active (fixed)			0			
Target Resource	-			0			
Error Detection Server							
Error Detection Server	All Servers			0			Γ
Servers that can run the Group (Add,	-			0			T
Remove)							
Error Detection Tab							Ť
Recovery Target	-			0			T
Reactivation Threshold	zero			0			t
Failover Target Server	Stable operation server			Ō			t
Failover Threshold	Set as many as the number of			Ō			t
Tallovoi Tilloonola	the servers						
Specify the count	-			0			t
Final Action	Stop cluster service and			0			t
I IIIdi Action	shutdown OS						
Execute Script before Final Action	Off						Ŧ
Parameter Tab	Oil						
			1				_
IP Address	-			0			Ļ
User Name	-			0			L
Password	-			0			L
Monitor Table Name	ODBCWATCH			0			L
racle Monitor Resource Properties							
Monitor Tab							
Interval	60 seconds			0			
Timeout	120 seconds			0			Ī
Retry Count	2 times			0			
Wait Time to Start Monitoring	0 second			0			Γ
Monitor Timing	Active (fixed)			0			T
Target Resource	-			0			T
Error Detection Server	•						İ
Error Detection Server	All Servers			0			T
Servers that can run the Group (Add,	-		1	0			t
Remove)							
	·						۲
Error Detection Tab							Ŧ
Error Detection Tab Recovery Target	-			0			
Recovery Target							ŀ
Recovery Target Reactivation Threshold	zero			0			ļ
Recovery Target Reactivation Threshold Failover Target Server	zero Stable operation server			00			<u> </u>
Recovery Target Reactivation Threshold	zero Stable operation server Set as many as the number of			0			<u> </u>
Recovery Target Reactivation Threshold Failover Target Server Failover Threshold	zero Stable operation server Set as many as the number of the servers			0 0			
Recovery Target Reactivation Threshold Failover Target Server Failover Threshold Specify the count	zero Stable operation server Set as many as the number of the servers -			0 0			\ - - -
Recovery Target Reactivation Threshold Failover Target Server Failover Threshold	zero Stable operation server Set as many as the number of the servers - Stop cluster service and			0 0			  -  -  -
Recovery Target Reactivation Threshold Failover Target Server Failover Threshold  Specify the count Final Action	zero Stable operation server Set as many as the number of the servers - Stop cluster service and shutdown OS			0 0			\-\-\-\-\-\-\-\-\-\-\-\-\-\-\-\-\-\-\-
Recovery Target Reactivation Threshold Failover Target Server Failover Threshold  Specify the count Final Action  Execute Script before Final Action	zero Stable operation server Set as many as the number of the servers - Stop cluster service and			0 0			
Recovery Target Reactivation Threshold Failover Target Server Failover Threshold  Specify the count Final Action	zero Stable operation server Set as many as the number of the servers - Stop cluster service and shutdown OS			0 0			

Parameters	Default	How to change		nge	IP.		
i didilictors	Delault	1	2	3	nge 4	5	6
Password	-		_	0			-
OS Authentication	Off			Ō			
SYSDBA/DEFAULT	SYSDBA			O			
Monitor Table Name	ORAWATCH			0			
Character Set	(Following the setting of the			0			
	application)						
fficeScan CL Monitor Resource Properties							
Monitor Tab							
Interval	60 seconds			0			
Timeout	120 seconds			0			
Retry Count	1 time			0			
Wait Time to Start Monitoring	0 seconds			0			
Monitor Timing	Always (fixed)			0			
Target Resource				0			
Error Detection Server	-			<u> </u>			
Error Detection Server	All Carrier			0			
	All Servers						
Servers that can run the Group (Add, Remove)	-			0			
Error Detection Tab							
Recovery Target	-			0			
Reactivation Threshold	0 times			0			
Failover Destination Server	Stable operation server			0			
Failover Threshold	Set in accordance with the			0			
	number of the servers						
Specify the count	-			0			
Final Action	No Operation			0			
Execute Script before Final Action	Off						C
fficeScan SV Monitor Resource Properties							
Monitor Tab							
Interval	30 seconds			0			
Timeouth	60 seconds			0			
Retry Count	3 times			0			
Wait Time to Start Monitoring	0 seconds			0			
Monitor Timing	Active (fixed)			0			
Target Resource	-			0			
Error Detection Server							
Error Detection Server	All Servers			0			
Servers that can run the Group (Add,	-			0			
Remove)							
Error Detection Tab							
Recovery Target	-			0			
Reactivation Threshold	0 times			0			
Failover Destination Server	Stable operation server			0			
Failover Threshold	Set in accordance with the number of the servers			0			
Specify the count	-			0			
Final Action	Stop cluster service and			0			
	shutdown OS						С
Execute Script before Final Action	Off						_
Execute Script before Final Action  OP3 Monitor Resource Properties	Off						
Execute Script before Final Action  OP3 Monitor Resource Properties  Monitor Tab	Off						
OP3 Monitor Resource Properties	Off 30 seconds			0			
OP3 Monitor Resource Properties  Monitor Tab  Interval	30 seconds			0			
OP3 Monitor Resource Properties  Monitor Tab  Interval  Timeout	30 seconds 60 seconds			0			
OP3 Monitor Resource Properties  Monitor Tab  Interval  Timeout  Retry Count	30 seconds						
OP3 Monitor Resource Properties  Monitor Tab  Interval  Timeout	30 seconds 60 seconds 3 times			0			

Parameters	Default	Но	w to		nge		
		1	2	3	4	5	6
Error Detection Server							
Error Detection Server	All Servers			0			
Servers that can run the Group (Add,	-			0			
Remove)							
Error Detection Tab							
Recovery Target	-			0			
Reactivation Threshold	zero			0			
Failover Target Server	Stable operation server			0			
Failover Threshold	Set as many as the number of			0			
	the servers						
Specify the count	-			0			
Final Action	Stop the cluster service and			0			
Francis Corint hafana Final Action	shutdown OS						L
Execute Script before Final Action	Off						C
Parameter Tab							
IP Address	127.0.0.1			0			
Port Number	110			0			
User Name	-			0			
Password	-			0			
Certification Method	APOP			0			
PostgreSQL Monitor Resource Properties							
Monitor Tab							
Interval	60 seconds			0			
Timeout	120 seconds			0			
Retry Count	2 times			0			
Wait Time to Start Monitoring	0 second			0			
Monitor Timing	Active (fixed)			0			
Target Resource	-			0			
Error Detection Server							
Error Detection Server	All Servers			0			
Servers that can run the Group (Add,	-			0			
Remove)							
Error Detection Tab							
Recovery Target	-			0			
Reactivation Threshold	zero			0			
Failover Target Server	Stable operation server			0			
Failover Threshold	Set as many as the number of			0			
	the servers						
Specify the count	-			0			
Final Action	Stop the cluster service and			0			
	shutdown OS						
Execute Script before Final Action	Off						C
Parameter Tab							
Database Name	-			0			
IP Address	127.0.0.1			0			
Port Number	5432			0			
User Name	postgres			0			
Password	-			0			
Monitor Table Name	PSQLWATCH			0			
SMTP Monitor Resource Properties							
Monitor Tab							
Interval	30 seconds			0			
Timeout	60 seconds			0			
Retry Count	3 times			0			
Wait Time to Start Monitoring	0 second			0			T
Monitor Timing	Active (fixed)			Ō			T
Target Resource	-			Ō			T
Error Detection Server							
Error Detection Server	All Servers			0			
-				Ō			

Parameters	Default		w to				
		1	2	3	4	5	6
Remove)							
Error Detection Tab			1				
Recovery Target	-			0			
Reactivation Threshold	zero			0			
Failover Target Server	Stable operation server			0			
Failover Threshold	Set as many as the number of			0			
On a life than a sourt	the servers						
Specify the count	- Otan the shorten condition and						
Final Action	Stop the cluster service and			O			
For and Ordinal hadana Final Artisa	shutdown OS						_
Execute Script before Final Action	Off						0
Parameter Tab	1						
IP Address	127.0.0.1						
Port Number	25			_			
User Name	-						
Password	-			_			
Certification Method	CRAM-MD5			0			
Email Address	-			0			
QL Server Monitor Resource Properties							
Monitor Tab							
Interval	60 seconds			0			
Timeout	120 seconds			0			
Retry Count	2 times			0			
Wait Time to Start Monitoring	0 second						
Monitor Timing	Active (fixed)						
Target Resource	-						
Error Detection Server							<u> </u>
Error Detection Server	All Servers			0			Г
Servers that can run the Group (Add,	-						
Remove)							
Error Detection Tab							<u> </u>
Recovery Target	1-						Ι
Reactivation Threshold	zero						
Failover Target Server							
Failover Threshold	Stable operation server						
Fallover Threshold	Set as many as the number of the servers			O			
On a life than a sunt	the servers						
Specify the count	-						
Final Action	Stop the cluster service and			O			
	shutdown OS						
Execute Script before Final Action	Off						C
Parameter Tab							
Database Name	-			0			L
Instance Name	MSSQLSERVER			0			L
User Name	SA			0			
Password	-			0			
Monitor Table Name	SQLWATCH			0			
uxedo Monitor Resource Properties							
axedo Monitor Nesource Froperties							
Monitor Tab							
Monitor Tab  Interval	60 seconds			0			
Monitor Tab	60 seconds 120 seconds			0			
Monitor Tab Interval Timeout							
Monitor Tab Interval Timeout Retry Count	120 seconds 2 times			00			
Monitor Tab Interval Timeout Retry Count Wait Time to Start Monitoring	120 seconds 2 times 0 second			000			
Monitor Tab Interval Timeout Retry Count Wait Time to Start Monitoring Monitor Timing	120 seconds 2 times			0000			
Monitor Tab Interval Timeout Retry Count Wait Time to Start Monitoring Monitor Timing Target Resource	120 seconds 2 times 0 second			000			
Monitor Tab Interval Timeout Retry Count Wait Time to Start Monitoring Monitor Timing Target Resource Error Detection Server	120 seconds 2 times 0 second Active (fixed)			0000			
Monitor Tab Interval Timeout Retry Count Wait Time to Start Monitoring Monitor Timing Target Resource Error Detection Server Error Detection Server	120 seconds 2 times 0 second Active (fixed) -			00000			
Monitor Tab  Interval Timeout Retry Count Wait Time to Start Monitoring Monitor Timing Target Resource Error Detection Server Error Detection Server Servers that can run the Group (Add,	120 seconds 2 times 0 second Active (fixed)						
Monitor Tab Interval Timeout Retry Count Wait Time to Start Monitoring Monitor Timing Target Resource Error Detection Server Error Detection Server Servers that can run the Group (Add, Remove)	120 seconds 2 times 0 second Active (fixed) -			00000			
Monitor Tab Interval Timeout Retry Count Wait Time to Start Monitoring Monitor Timing Target Resource Error Detection Server Error Detection Server Servers that can run the Group (Add,	120 seconds 2 times 0 second Active (fixed) -			00000			

Reactivation Threshold zero Failover Threshold Set as many as the number of failover Threshold Set as many as the number of the servers  Specify the count Final Action Stop the cluster service and shutdown OS Execute Script before Final Action Off Parameter Tab Application Server Name BBL O O Config File Websphere Monitor Resource Properties Monitor Tab Interval 120 seconds Timeout 120 seconds Timeout 120 seconds Timeout 120 seconds Timeout 120 seconds Timeout 120 seconds Timeout 130 second O O Monitor Timing Active (fixed) O O Error Detection Server Error Detection Server Error Detection Server  Error Detection Tab Recovery Target Reactivation Threshold Set as many as the number of O Failover Threshold Set as many as the number of O Failover Threshold Set as many as the number of O Failover Threshold Set on Server O Specify the count Final Action Server Name Server O Specify the Count Final Action Server Name Server O Specify the Count Final Action Server Name Server O Specify the Count Final Action Server Name Server O Parameter Tab Application Server Name Server O P	Parameters	Default	Но	w to	cha	nge	
Reactivation Threshold Set as many as the number of the servers Specify the count - Final Action Stop the cluster service and shutdown OS Specify the count - Final Action Stop the cluster service and shutdown OS Stop the cluster service and s							6
Failover Threshold the servers  Specify the count  Final Action	Reactivation Threshold	zero					
the servers   Specify the count   - Final Action   - Stop the cluster service and shutdown OS   - Stop the cl		Set as many as the number of			0		
Final Action  Execute Script before Final Action  Off  Parameter Tab  Application Server Name  Config File  Descript Monitor Resource Properties  Monitor Tab  Interval  Timeout  Exercite Script Before Final Action  BBL  DO  DO  Config File  DO							
Final Action  Execute Script before Final Action  Parameter Tab  Application Server Name  Config File  Config	Specify the count	-			0		
Sevente Script before Final Action	Final Action	Stop the cluster service and			0		
Parameter Tab							
Parameter Tab	Execute Script before Final Action	Off					0
Application Server Name   BBL							l
Config File	Application Server Name	BBL			0		Π
Monitor Tab   Interval   60 seconds   0   Interval   120 seconds   0   Netry Count   120 seconds   0   Netry Count   2 times   0   Netry Count   Netry Cou	Config File						
Monitor Tab	Websphere Monitor Resource Properties				Ť		
Interval Timeout Timeo	Monitor Tab						
Timeout		60 seconds			0		1
Retry Count							
Wait Time to Start Monitoring							
Monitor Timing							
Target Resource							
Error Detection Server		` '					
Error Detection Server   Servers that can run the Group (Add, Remove)   Colorador							l
Servers that can run the Group (Add,   Remove)		All Convers	1	l 1	_		1
Remove   Remove   Recovery Target					_		
Error Detection Tab Recovery Target Reactivation Threshold Recovery Target Reactivation Threshold Recovery Target Reactivation Threshold Recovery Target Reactivation Threshold Set as many as the number of the servers Specify the count Final Action Stop the cluster service and shutdown OS Execute Script before Final Action Off Parameter Tab  Application Server Name Profile Name Gefault User Name C:\Program Files\IBM\WebSphere\AppServer  Weblogic Monitor Resource Properties  Monitor Tab Interval Interval Retry Count Wait Time to Start Monitoring Monitor Timing Active (fixed) Target Resource Ferror Detection Server  Error Detection Server  Error Detection Server  Reactivation Threshold Recovery Target Resource Servers that can run the Group (Add, - Remove) Recovery Target Reactivation Threshold Set as many as the number of the servers Specify the count - O		-			O		
Recovery Target   -   Reactivation Threshold   zero   O							<u> </u>
Reactivation Threshold Failover Threshold Set as many as the number of the servers Specify the count Final Action Stop the cluster service and shutdown OS Execute Script before Final Action Off Parameter Tab Application Server Name Profile Name User Name				1	_		1
Failover Threshold  Set as many as the number of the servers  Specify the count  Final Action  Stop the cluster service and shutdown OS  Execute Script before Final Action  Off  Parameter Tab  Application Server Name  Profile Name  User Name  Password  Install Path  C:\Program  Files\IBM\WebSphere\AppServer  Weblogic Monitor Resource Properties  Monitor Tab  Interval  Interval  Interval  Interval  Files Oseconds  Oo  Retry Count  Wait Time to Start Monitoring  Monitor Timing  Active (fixed)  Target Resource  Error Detection Server  Servers that can run the Group (Add, - Remove)  Error Detection Tab  Recovery Target  Reactivation Threshold  Failover Threshold  Set as many as the number of the servers  Oo  Oo  Oo  Oo  Oo  Oo  Oo  Oo  Oo  O							
Specify the count							
Specify the count	Fallover Inreshold				O		
Final Action  Execute Script before Final Action  Off  Parameter Tab  Application Server Name Profile Name User Name Password Install Path C:\Program Files\\BM\\WebSphere\AppServer  Monitor Tab Interval Timeout Retry Count Wait Time to Start Monitoring Active (fixed) Target Resource Fror Detection Server Servers that can run the Group (Add, Pailover) Recovery Target Recovery Target Reactivation Threshold Failover Threshold Failover Threshold Fassword C:\Program Files\\BM\\WebSphere\AppServer C:\Program Files\\BM\\WebSphere\AppServer C:\Program Files\\BM\\WebSphere\AppServer C:\Program Files\\BM\\WebSphere\AppServer C:\Program Files\\BM\\WebSphere\AppServer C:\Program Files\\BM\\WebSphere\AppServer C:\Program Files\\BM\\WebSphere\AppServer C:\Program Files\\BM\\WebSphere\AppServer C:\Program Files\\BM\\WebSphere\AppServer C:\Program Files\\BM\\WebSphere\AppServer C:\Program C:\Program Files\\BM\\WebSphere\AppServer C:\Program C:\Program Files\\BM\\WebSphere\AppServer C:\Program C:\Program Files\\BM\\WebSphere\AppServer C:\Program C:\Program Files\\BM\\WebSphere\AppServer C:\Program C:\Program Files\\BM\\WebSphere\AppServer C:\Program C:\P		the servers					
Execute Script before Final Action		-					
Execute Script before Final Action	Final Action				O		
Parameter Tab							
Application Server Name		Off					0
Profile Name							
User Name	Application Server Name				-		
Password		default			_		
Install Path   C:\Program   Files\IBM\WebSphere\AppServer		-					
Files\\BM\\WebSphere\AppServer		-			0		
Meblogic Monitor Resource Properties   Monitor Tab	Install Path				0		
Monitor Tab		Files\IBM\WebSphere\AppServer					
Interval   120 seconds   0							
Timeout	Monitor Tab						
Retry Count	Interval	60 seconds			0		
Wait Time to Start Monitoring	Timeout	120 seconds			0		
Monitor Timing Target Resource		2 times			0		
Monitor Timing Target Resource							
Target Resource - O		Active (fixed)			0		
Error Detection Server  Error Detection Server  Servers that can run the Group (Add, Remove)  Error Detection Tab  Recovery Target Reactivation Threshold Failover Threshold Set as many as the number of the servers  Specify the count  - O		-					
Error Detection Server All Servers O Servers that can run the Group (Add, Remove)  Error Detection Tab  Recovery Target - O Reactivation Threshold zero O Failover Threshold Set as many as the number of the servers Specify the count - O	Error Detection Server						l
Servers that can run the Group (Add, - Remove)  Error Detection Tab  Recovery Target - O  Reactivation Threshold zero O  Failover Threshold Set as many as the number of the servers Specify the count - O		All Servers			0		
Remove)  Error Detection Tab  Recovery Target Reactivation Threshold Failover Threshold Set as many as the number of the servers Specify the count  - O							
Error Detection Tab  Recovery Target Reactivation Threshold Failover Threshold Set as many as the number of the servers Specify the count  - O					_		
Recovery Target - O Parameter - O Parameter - Parameter - Parameter - Parameter - O Parameter - O Parameter - O Parameter - Parameter - O P Parameter - O P Parameter - O P Parameter - O P P P P P P P P P P P P P P P P P P	Error Detection Tab						
Reactivation Threshold zero O Set as many as the number of the servers O Specify the count - O Set as many as the number of the servers O Set as many as t		-			0		
Failover Threshold  Set as many as the number of the servers  Specify the count  O							1
Specify the count - O			<del>                                     </del>				 <b> </b>
Specify the count - O	- Landvoi Hillouriola				_		
	Specify the count	-			$\overline{}$		1
Final Action   Stop the cilieter earlied and	Final Action	Stop the cluster service and			0		1
shutdown OS	I mai / totion				9		
Execute Script before Final Action Off	Execute Script before Final Action						0
Parameter Tab				Щ			L
r aranicus ray	r ai ailietei Tau						

Parameters	Default	Но	How to cha				
		1	2	3	4		
IP Address	127.0.0.1			0			
Port	7002			0			
Account Shadow	Off			0			
On Config File	-			0			
On Key File	-			0			
Off User Name	weblogic			0			T
Off Password	-			0			t
Authority Method	DemoTrust			0			<u> </u>
Key Store File	-			-			H
Install Path	C:\bea\weblogic92						+
bOTX Monitor Resource Properties	C. Weblegiesz	<u> </u>					<u>                                       </u>
Monitor Tab							_
Interval	60 seconds	ı	1				Т
Timeout	120 seconds						ł
							ļ
Retry Count	1 times						L
Wait Time to Start Monitoring	0 second			_			
Monitor Timing	Active (fixed)			0			
Target Resource	-		2   3   0   0   0   0   0   0   0   0   0				
Error Detection Server			2 3 0 0 0 0 0				
Error Detection Server	All Servers			0			Ī
Servers that can run the Group (Add,	-			0			t
Remove)							
Error Detection Tab							
Recovery Target	1-	Π		0			T
Reactivation Threshold	zero						ł
Failover Threshold	Set as many as the number of						ł
railovei Tillesiloid	the servers			U			l
Charify the count	the servers						ļ
Specify the count	-						ļ
Final Action	Stop the cluster service and			O			
	shutdown OS						ļ
Execute Script before Final Action	Off						
Parameter Tab							
Connecting Destination	localhost						l
Port Number	6212						Ī
User Name	-			0			Ī
Password	-			0			İ
acleAS Monitor Resource Properties							
OracleAS Monitor Resource Properties							
Interval	60 seconds			0			T
Timeout	120 seconds	1	1				ł
Retry Count	1 time						ł
Wait Time to Start Monitoring	0 second	-	-	_			ł
			-				ļ
Monitor Timing	Active (fixed)		-				ļ
Target Resource	<u> </u>	<u> </u>		U			1
Error Detection Server	1						
Error Detection Server	All Servers						ĺ
Servers that can run the Group (Add,	-			0			ſ
		L					J
Remove)							
Error Detection Tab				0			Ī
Error Detection Tab Recovery Target	-			_	_		4
Error Detection Tab	- zero						ļ
Error Detection Tab Recovery Target Reactivation Threshold	zero			0			l
Error Detection Tab Recovery Target Reactivation Threshold Failover Target Server	zero Stable operation server			0 0			1
Error Detection Tab Recovery Target Reactivation Threshold	zero Stable operation server Set as many as the number of			0 0			
Error Detection Tab Recovery Target Reactivation Threshold Failover Target Server Failover Threshold	zero Stable operation server			000			
Error Detection Tab  Recovery Target Reactivation Threshold Failover Target Server Failover Threshold  Specify the count	zero Stable operation server Set as many as the number of the servers -			0000			
Error Detection Tab Recovery Target Reactivation Threshold Failover Target Server Failover Threshold	zero Stable operation server Set as many as the number of the servers - Stop the cluster service and			0000			
Error Detection Tab  Recovery Target  Reactivation Threshold  Failover Target Server  Failover Threshold  Specify the count  Final Action	zero Stable operation server Set as many as the number of the servers - Stop the cluster service and shutdown OS			0000			
Error Detection Tab  Recovery Target Reactivation Threshold Failover Target Server Failover Threshold  Specify the count	zero Stable operation server Set as many as the number of the servers - Stop the cluster service and			0000			

Parameters I		Default		How to change							
			1	2	3	4	5	6			
	Install path	C:\product\10.1.3.2\companionC DHome_1			0						

### **Upper limits of registration**

	Builder version	You can register up to
Cluster	2.0.0-1 or later	1
Server	2.0.0-1 or later	32
Group	2.0.0-1 or later	64
Group resource (Per one group)	2.0.0-1 or later	256
Monitor resource	2.0.0-1 or later	384
Heartbeat resource	2.0.0-1 or later	16
Network Partition Resolution Resource	2.0.0-1 or later	64
Mirror disk resources and hybrid disk resources (Per cluster) in total	2.0.0-1 or later	8

# Chapter 4 ExpressCluster command reference

This chapter describes commands that are used on ExpressCluster.

#### This chapter covers:

•	Operating the cluster from the command line	202
•	ExpressCluster commands	202
•	Displaying the cluster status (clpstat command)	204
•	Examples of executing the command that displays status (clpstat command)	
•	Status Descriptions	
•	Operating the cluster (clpcl command)	
•	Shutting down a specified server (clpdown command)	
•	Shutting down the entire cluster (clpstdn command)	
•	Operating groups (clpgrp command)	
•	Collecting logs (clplogcc command)	
•	Collecting information at emergency OS shutdown	
•	Creating a cluster and backing up configuration data (clpcfctrl command)	269
•	Adjusting time-out temporarily	
•	Modifying the log level and size	
•	Mirror-related commands	
•	Mirror status display commands	
•	Mirror disk resource operation command	
•	Partition size tuning command	
•	Snapshot backup command of hybrid disk resource	
•	Hybrid disk status display command	
•	Hybrid disk resource operation command	
•	Message output command	
•	Controlling monitor resources (clpmonctrl command)	
•	Controlling group resources (clprsc command)	
•	Network warning light switch off command	
•	CPU frequency control command	
•	Chassis identify control command	
•	Inter-cluster processing request command	
•	BMC information change command	
•	Shutdown hook configuration command	

### Operating the cluster from the command line

ExpressCluster provides various commands to operate a cluster by the command prompt. These commands are useful for things like constructing a cluster or when you cannot use the WebManager. You can perform greater number of operations using the command line than WebManager.

#### Note:

When you have configured a group resource (examples: disk resource and application resource) as a recovery target in the settings of error detection by a monitor resource, and the monitor resource detects an error, do not perform the following actions by commands related to the actions or by the WebManager while recovery (reactivation -> failover -> final action) is ongoing.

- terminate/suspend the cluster
- start/terminate/migrate a group

If you perform the actions mentioned above against the cluster while the recovery caused by detection of an error by a monitor resource is ongoing, other group resources of that group may not terminate. However, you can perform these actions as long as the final action has been executed, even if a monitor resource detected an error.

### **ExpressCluster commands**

Commands for o	configuring a cluster	
Command	Description	Page
clpcfctrl.exe	Distributes configuration data created by the Builder to servers.	269
	Backs up the cluster configuration data to be used by the Builder.	
Commands for	displaying status	
Command	Description	Page
clpstat.exe	Displays the cluster status and configuration information.	204
Commands for	cluster operation	
Command	Description	Page
clpcl.exe	Starts, stops, suspends, or resumes the ExpressCluster service.	251
clpdown.exe	Stops the ExpressCluster service and shuts down the server.	256
clpstdn.exe	Stops the ExpressCluster service across the whole cluster and shuts down all servers.	257
clpgrp.exe	Starts, stops, or moves groups.	258
clptoratio.exe	Extends or displays the various time-out values of all servers in the cluster.	276
clpmonctrl.exe	Suspends or resumes monitor resources on a single server.	313
clprsc.exe	Stops or resumes group resources	318
clpcpufreq.exe	Controls CPU frequency	323
clpledctrl.exe	Controls Chassis Identify	325

clptrnreq.exe	Requests the server to execute a process	327					
clpbmccnf.exe	Changes the information on BMC user name and password	330					
clphookctrl.exe	Configures the shutdown hook function	332					
Log-related commands							
Command	Description	Page					
clplogcc.exe	Collects logs and OS information.	263					
clplogcf.exe	Modifies and displays a configuration of log level and the file size of log output.	279					
Script-related co	ommands						
Command	Description	Page					
clplogcmd.exe	Writes texts in the script resource script to create a desired	311					

#### Important:

The installation directory contains executable-format files and script files that are not listed in this guide. Do not execute these files by programs or applications other than ExpressCluster. Any problems caused by not using ExpressCluster will not be supported.

Mirror-related commands (when the Replicator/Replicator DR is used)					
Command	Description	Page			
clpmdstat.exe	Displays a mirroring status and configuration information.	288			
clpmdctrl.exe	Activates/deactivates a mirror disk resource, or recovers mirror.	293			
clphdstat.exe	Displays a hybrid disk status and configuration information.	302			
clphdctrl.exe	Activates/deactivates a hybrid disk resource, or recovers mirror.	307			
clpvolsz.exe	Checks and adjusts the size of partitions to be mirrored.	297			
clphdsnapshot.exe	Controls the access restriction or alike when snap shot backups of data partition in the hybrid disk resource are collected	299			

Mirror-related commands (when the Replicator/Replicator DR is used)		
Command Description F		Page
clpmdstat.exe Lights off the network warning light.		322

### Displaying the cluster status (clpstat command)

**clpstat:** the clpstat command displays cluster status and configuration information.

#### **Command line:**

```
clpstat-s [-h <hostname>]
clpstat-g [-h <hostname>]
clpstat-m [-h <hostname>]
clpstat-n [-h <hostname>]
clpstat-p [-h <hostname>]
clpstat-i [--detail] [-h <hostname>]
clpstat-cl [--detail] [-h <hostname>]
clpstat--sv [<srvname>] [--detail] [-h <hostname>]
clpstat--hb [<hbname>] [--detail] [-h <hostname]
clpstat--np [<npname>] [--detail] [-h <hostname>]
clpstat--svg [<svyname>] [--detail] [-h <hostname>]
clpstat--grp [<grpname>] [--detail] [-h <hostname>]
clpstat--rsc [<recname>] [--detail] [-h <hostname>]
clpstat--rsc [<recname>] [--detail] [-h <hostname>]
clpstat--mon [<monname>] [--detail] [-h <hostname>]
```

plays a cluster status and configuration data.
--

Option	-S	Displays a cluster status.	
	No option		
	-g	Displays a cluster group map.	
	-m	Displays status of each monitor resource on each server.	
	-n	Displays each heartbeat resource status on each server.	
	-p	Displays the status of each network partition resolution on each server.	
	-i	Displays the configuration information of the whole cluster.	
	cl	Displays the cluster configuration data. Displays the Mirror Agent information as well for the Replicator/Replicator DR.	
	sv [server_name]	Displays the server configuration information. By specifying the name of a server, you can display information of the specified server.	
	hb [hb_name]	Displays heartbeat resource configuration information. By specifying the name of a heartbeat resource, you can display only the information on the specified heartbeat.	
	np [ <i>np_name</i> ]	Displays the configuration information on the network partition resolution resource. By specifying the name of a network partition resolution resource, you can display only the information on the specified network partition resolution resource.	

	grp [group_name]	Displays group configuration information. By specifying the name of a group, you can display only the information on the specified group.		
	svg [svgname]	Displays server group configuration information. By specifying the name of a server group, you can display only the information on the specified server group.		
	rsc [resource_name]	Displays group resource configuration information. By specifying the name of a group resource, you can display only the information on the specified group resource.		
	mon [monitor_name]	Displays monitor resource configuration information. By specifying the name of a monitor resource, you can display only the information on the specified monitor resource.		
	detail	Displays more detailed information on the setting.		
	-h host_name	Acquires information from the server specified with <i>host_name</i> . Acquires information from the command running server (local server) when the -h option is omitted.		
Return Value	0	Success		

Return Value	0	Success
	Other than 0	Failure

Remarks	According to the combination of options, configuration information shows information in various forms.
---------	--

#### Note:

Run this command as a user with Administrator privileges. The ExpressCluster service must be activated on the server where you run this command. When you specify the name of a server for the –h option, the server should be in the cluster.

Examples of information displayed after running these commands are provided in the next section.

#### **Error Messages**

Message	Cause/Solution		
Log in as administrator.	Log in as a user with Administrator privileges.		
Invalid configuration file. Create valid cluster configuration data by using the Builder.	Create valid cluster configuration data by using the Builder.		
Invalid option.	Specify a valid option.		
Could not connect to the server. Check if the cluster service is active	Check if the ExpressCluster service is operating.		
Invalid server status.	Check if the ExpressCluster service is operating.		
Server is not active. Check if the cluster service is active.	Check if the ExpressCluster service is operating.		
Invalid server name. Specify a valid server name in the cluster.	Specify the valid server name in the cluster.		
Invalid heartbeat resource name.	Specify the valid heart beat resource		
Specify a valid heartbeat resource name in the cluster.	name in the cluster.		
Invalid network partition resource	Specify the valid network partition		

name. Specify a valid network partition resource name in the cluster.	resolution resource name in the cluster.
Invalid group name. Specify a valid group name in the cluster.	Specify the valid name of a group in the cluster.
Invalid group resource name. Specify a valid group resource name in the cluster.	Specify the valid name of a group resource in the cluster.
Invalid monitor resource name. Specify a valid monitor resource name in the cluster.	Specify the valid name of a monitor resource in the cluster.
Connection was lost. Check if there is a server where the cluster service is stopped in the cluster.	Check if there is any server on which the ExpressCluster service has stopped in the cluster.
Invalid parameter.	An invalid value may be specified to command argument.
Internal communication timeout has occurred in the cluster server. If it occurs frequently, set a longer timeout.	A time-out occurred in the ExpressCluster internal communication. If time-out keeps occurring, set the internal communication time-out longer.
Internal error. Check if memory or OS resources are sufficient.	Check if the memory or OS resource is sufficient.

# Examples of executing the command that displays status (clpstat command)

### Displaying the status

The following is an example of display when you run the clostat command with the -s option or without any option:

#### Example of the display after running the command

```
Cluster : cluster
                                                                      > See (1)
  <server>
                                             server1
                                                                    -> See (2)
   *server1 ....: Online
    lanhb1 : Normal LAN Heartbeat -> See (2)
lanhb2 : Normal LAN Heartbeat -> See (3)
pingnp1 : Normal ping resolution -> See (4)
server2 . . . . : Online server2
lanhb1 : Normal LAN Heartbeat
lanhb2 : Normal LAN Heartbeat
pingnp1 : Normal ping resolution
group>
  <group>
    ManagementGroup: Online
                                               Management Group ->See (5)
      current : server1
ManagementIP : Online
                                                10.0.0.10
    failover1 ....: Online
                                               failover group1 ->See (6)
      current : server1
      fip1 : Online md1 : Online script1 : Online
                                                                      ->See (7)
                                               10.0.0.11
                                               I:
                                               script resource1
    failover2 ....: Online
                                               failover group2
      current : server2
fip2 : Online
md2 : Online
script1 : Online
                                                10.0.0.12
                                                J:
                                               script resource2
  <monitor>
    fipw1 : Normal
fipw2 : Normal
ipw1 : Normal
mdnw1 : Normal
mdnw2 : Normal
mdw1 : Normal
mdw2 : Normal
mdw2 : Normal
                                               fip1
                                                                      ->See (8)
                                               fip2
                                               ip monitor1
                                               md1
                                               md2
                                               md1
                                               md2
______
(1) Cluster
                               : Cluster name
(2) Server name : Status
                               Server comment
    "*" indicates the server has executed this command.
(3) Heartbeat resource name
                               : Heartbeat resource comment
(4) NP resolution resource name: NP resolution resource comment
(5) Management group name
                               : Management group comment
(6) Group name
                                : Group comment
                            : Server name
    current
    Shows the server to which the group belongs now.
(7) Group Resource Name
                            : Status
                                     Group resource comment
(8) Monitor Resource Name : Status
                                      Monitor resource comment
```

Information on each status is provided in "Status Descriptions" on page 249.

### Displaying a group map (clpstat command)

To display a group map, run the clostat command with the -g option.

#### **Example of the display after running the command:**

```
Cluster : cluster
                                        -> See (1)
  *server0 : server1
                                        -> See (2)
   server1 : server2
  server0 [o] : failover1[o] failover2[o] -> See(3)
  server1 [o] : failover3[o]
______
(1) Cluster
                     :Cluster name
(2) server n
                     :Server name (n is the index number of a server)
   "*" indicates the server has executed this command.
(3) server n [server status]
                    : Group Name [status] Group Name [status].
```

- Displays the status of groups in the n-th server.
  - In the example above, the groups failover1 and failover2 exist on server0, and the group failover 3 exists on server 3.
- Groups that are not running are not displayed.
- Information on each status is provided in "Status Descriptions" on page 249.

### Displaying the status of monitor resources (clpstat command)

To display the status of monitor resources, run the clpstat command with the -m option.

#### **Example of the display after running the command:**

```
======== MONITOR RESOURCE STATUS ==========
 Cluster : cluster -> see (1)
 *server0 : server1
                          -> see (2)
                          -> see (2)
  server1 : server2
 Monitor0 [fipw1 : Normal] -> see (3)
  Monitor1 [fipw2 : Normal]
                      ______
  server0 [o] : Offline
  server1 [o] : Online
 Monitor2 [ipw1 : Normal]
                   _____
  server0 [o] : Online
server1 [o] : Online
 Monitor3 [mdnw1 : Normal]
  server0 [o] : Online
server1 [o] : Online
 Monitor4 [mdnw2 : Normal]
  server0 [o] : Online
  server1 [o] : Online
```

```
Monitor5 [mdw1 : Normal]

server0 [o] : Online
server1 [o] : Online

Monitor6 [mdw2 : Normal]

server0 [o] : Online
server1 [o] : Online
```

- (1) Cluster: Cluster name
- (2) server n : Server name (n is the index number of a server) "\*" indicates the server has executed this command.
- (3) Monitor n [monitor\_resource\_name: status](n is the identification number of a monitor resource)The status of a monitor resource gathering status information per server is displayed here.
- (4) server n [server\_status] : status
  Displays the status of each monitor resource per server.

Information on each status is provided in "Status Descriptions" on page 249.

### Displaying the status of heartbeat resources (clpstat command)

To display the status of heartbeat resources, run clpstat command with the -n option.

#### **Example of the display after running the command:**

```
========= HEARTBEAT RESOURCE STATUS ==========
Cluster : cluster -> see (1)

*server0 : server1 -> see (2)

server1 : server2 -> see (2)

> see (3)
 HB0 : lanhb1
                    -> see (3)
  HB1 : lanhb2
                    -> see (3)
  [on server0 : Online] -> see (4)
       HB 0 1 -> see (5)
_____
  server0: o o \rightarrow see (5)
  server1: o x
  [on server1 : Online]
  HB 0 1
  server0 : o x
  server1 : o o
______
```

#### **Explanation of each item**

- (1) Cluster: Cluster name
- (2) server n : Server name (n is the index number of a server) "\*" indicates the server has executed this command.
- (3) HB n : Heartbeat resource name (n is the identification number of a heartbeat resource)
- (4) [on server n : status]
  Displays the status of the server whose index number is n.

(5) HB 0 1 2 .

server n : status status status

Displays the status of heartbeat resource on the server.

The numbers following HB are heartbeat resource identification numbers described in (3).

Detailed information on each status is provided in "Status Descriptions" on page 249.

#### The status of the example shown above:

The example above presents the status of all heartbeat resources seen from server0 and server1 when the kernel-mode LAN heartbeat resource that has the second-highest priority is disconnected.

Because kernel-mode LAN heartbeat resource lankhb1 is not able to communicate from both servers, communication to server1 on server0 or communication to server0 on server1 is unavailable.

The rest of heartbeat resources on both servers are in the status allowing communications.

# Displaying the status of network partition resolution resources (clpstat command)

Specify the –p option to the clpstat command and execute the command to display the status of the network partition resolution resources.

#### Example of the display after running the command:

#### **Explanation of each item**

- (1) Cluster: Cluster name
- (2) server n : Server name (n is the index number of a server) "\*" indicates the server has executed this command.
- (3) NP n : network partition resolution resource name (n is the identification number of a network partition resolution resource)
- (4) [on server n : *status*] Displays the status of the server whose index number is n.
- server n : status status status

  Displays the status of network partition resolution resource on the server.

  The numbers following NP are network partition resolution resource identification numbers described in (3).

Detailed information on each status is provided in "Status Descriptions" on page 249.

# Displaying the cluster configuration data (clpstat command, --cl option)

To display the configuration data of a cluster, run the clpstat command with the -i, --cl, --sv, --hb, --np, --svg, --grp, --rsc, or --mon option. You can see more detailed information by specifying the -detail option. See a separate section, "Parameter details" on page 118 for details of each item of the list.

To display the cluster configuration data, run the clustat command with the --cl option.

#### Example of the display after running the command:

==	======== CLUSTER INF	ORI	MATION ======	======
	[Cluster Name: cluster]			-> see (1)
,	Comment: failover cluster <heartbeat f="" i=""></heartbeat>			-> see (2)
- (		:	Enable	-> see (3)
	Cast Method	:	Unicast	-> see (4)
	<timeout></timeout>			
- 1	Server Sync Wait Time	:	300	-> see (5)
	Heartbeat Timeout	:	90000	-> see (6)
			3000	-> see (7)
	Server Internal Timeout	:	180	-> see (8)
	Timeout Ratio	:	1	-> see (9)
	<port number=""></port>			(10)
	Server Internal Port Number		29001	-> see (10)
	Data Transfer Port Number		29002	-> see (11)
- [	Kernel Heartbeat Port Number			-> see (12)
- 1	Client Service Port Number		29007	-> see (13)
	WebManager HTTP Port Number			-> see (14)
	Alert Sync Port Number			-> see (15)
			29004	-> see (16)
	Mirror Driver Port Number <recovery></recovery>	:	29005	-> see (17)
- 1	Max Reboot Count	:	0	-> see (18)
	Max Reboot Count Reset Time	:	0	-> see (19)
	Use Forced Stop	:	Enable	-> see (20)
	Forced Stop Action	:	BMC power off	-> see (21)
	Forced Stop Timeout	:	30	-> see (22)
	<power saving=""></power>			1
	Use CPU Frequency Control <delay warning=""></delay>	:	Off	-> see (23)
- 1	Heartbeat Delay Warning	:	80	-> see (24)
	Monitor Delay Warning	:	80	-> see (25)
	COM Delay Warning	:	80	-> see (26)
	<alert service=""></alert>			
	E-mail Address	:		-> see (27)
	Use Network Warning Light			-> see (28)
	Use Chassis Identify		Off	-> see (29)
	Enable Alert Setting	:	Off	-> see (30)
- [	<mirror disk=""></mirror>		- 11	(21)
	Auto Mirror Initial Construction			-> see (31)
- 1	Auto Mirror Recovery		Enable	-> see (32)
	Mirror Disk Disconnection Retry			-> see (33)
	Mirror Disk Disconnection Retry Mirror Disk Disconnection Final	7 I	Interval: 3	-> see (34)
i	MITIOI DISK DISCOMMECCIOM FINAL	LF	ACCIOII: DISCOIIIECU	
1	<disk></disk>			-> see (35)
- X	Shared Disk Disconnection Retry	<i>,</i> п	hreshold. 10	-> see (36)
	ad functions of Express Cluster	· <del>·</del>		, 500 (50)

Shared Disk Disconnection Retry Interval: 3 -> see (37)
Shared Disk Disconnection Final Action: Disconnect forcefully
-> see (38)

<Auto Recovery>
Auto Return :Off -> see (39)

◆ The items in dotted frame are displayed when the --detail option is used.

#### **Explanation of each item**

(1) Cluster : Cluster name(2) Comment : Comment

<Heartbeat I/F>

(3) Server Down Notification
 (4) Cast Method
 : Server Down Notification
 : Heartbeat Cast Method

<Timeout>

(5) Server Sync Wait Time : Time to wait for synchronization (in seconds)

(6) Heartbeat Timeout : Heartbeat time-out (in milliseconds)

(7) Heartbeat Interval : Heartbeat send interval (in milliseconds)

(8) Server Internal Timeout : Internal communication time-out (in seconds)

(9) Timeout Ratio : Current time-out ratio

<Port Number>

(10) Server Internal Port Number : Internal communication port number

(11) Data Transfer Port Number : Data transfer port number

(12) Kernel Heartbeat Port Number : Kernel mode heartbeat port number

(13) Client Service Port Number : Client Service Port Number

(14) WebManager HTTP Port Number: WebManager HTTP port number

(15) Alert Sync Port Number : Alert synchronous port number

(16) Disk Agent Port Number : Disk Agent Port Number

(17) Mirror Driver Port Number : Mirror Driver Port Number

<Recovery>

(18) Max Reboot Count : Maximum reboot count

(19) Max Reboot Count Reset Time : Time to reset the maximum reboot count (in seconds)

(20) Use Forced Stop : Forced stop

(21) Forced Stop Action : Forced stop action(22) Forced Stop Timeout : Forced stop timeout

<Power Saving>

(23) Use CPU Frequency Control : CPU frequency control

<Delay Warning>

(24) Heartbeat Delay Warning
 (25) Monitor Delay Warning
 (26) COM Delay Warning
 (27) Delay warning of monitor resource (%)
 (28) Delay Warning
 (29) Delay Warning of COMNP resource (%)

<Alert Service>

(27) E-mail Address : E-mail address to be reported

(28) Use Network Warning Light : Network warning light

(29) Use Chassis Identify : Chassis Identify

(30) Enable Alert Setting : Alert setting

The items of the information on mirror are displayed when not using the Replicator/Replicator DR as well.

<Mirror Disk>

(31) Auto Mirror Initial Construction : Auto Mirror Initial Construction

(32) Auto Mirror Recovery : Auto Mirror Recovery

(33) Mirror Disk Disconnection Retry Threshold : Mirror Disk Disconnection Retry Threshold

(34) Mirror Disk Disconnection Retry Interval : Mirror Disk Disconnection Retry Interval (in

seconds)

(35) Mirror Disk Disconnection Final Action : Mirror Disk Disconnection Final Action

<Disk>

(36) Shared Disk Disconnection Retry Threshold

Threshold

: Shared Disk Disconnection Retry

(37) Shared Disk Disconnection Retry Interval

: Shared Disk Disconnection Retry Interval

(in seconds)

(38) Shared Disk Disconnection Final Action

: Shared Disk Disconnection Final

Action

<Auto Recovery>

(39) Auto Return : Auto Recovery of Servers

### Displaying only the configuration data of certain servers (clpstat command with the --sv option)

When you want to display only the cluster configuration data on a specified server, specify the name of the server after the --sv option in the clpstat command. To see the details, specify the --detail option. When the server name is not specified, cluster configuration data of all the servers is displayed.

#### Example of a command entry

```
# clpstat --sv server1 --detail
```

#### **Example of the display after running the command:**

```
[Server0 : server1]
                                                   -> see (1)
  Comment
                                                   -> see (2)
                   : server1
  Product
                  : ExpressCluster x 2.1 for Windows -> see (3)
  Internal Version : 10.11
                                                   -> see (4)
  Install Path : C:\Program Files\EXPRESSCLUSTER
                                                   -> see (5)
  IP Address
                   : 10.0.0.1
                                                   -> see (6)
 Network warning light IP Address
                  : 10.0.0.10
                                                   -> see (7)
  BMC Address
                   : 10.0.0.11
                                                   -> see (8)
 CPU Frequency Status :high
                                                   -> see (9)
```

♦ The items in dotted frame are displayed when the --detail option is used.

#### **Explanation of each item**

(1) [Server n: server\_name] (n is index number of a server)

(2) Comment : Comment(3) Product : Product

(4) Internal Version : Internal Version

(5) Install Path : Install Path

(6) IP Address : Public LAN address

(7) Network Warning Light IP Address

: Network warning light IP address

(8) BMC IP Address : BMC IP address

(9) CPU Frequency Status : CPU Frequency Status

# Displaying only the resource information of certain heartbeats (clpstat command with the --hb option)

When you want to display only the cluster configuration data on a specified heartbeat resource, specify the name of the heartbeat resource after the --hb option in the clpstat command. If you want to see the details, specify the --detail option. When the heartbeat resource is not specified, the cluster configuration data of all the heartbeat resources is displayed.

#### Example of a command entry (For a kernel-mode LAN heartbeat resource)

```
# clpstat --hb lankhb1 --detail
```

#### Example of the display after running the command:

```
[HB0 : lanhb1]
 Type
                  : lanhb
                                     -> see (2)
 Comment
        : LAN Heartbeat
                                     -> see (3)
 <server1>
 IP Address
                  : 192.168.0.1
                                     -> see (4)
 <server2>
 IP Address
                  : 192.168.0.2
                             <del>--</del>-----
```

- ♦ The items marked by the solid line are common to all heartbeat resources.
- ◆ The lines below "Comment" are displayed when the --detail option is used.

#### Information common to all heartbeat resources

- (1) [HB n: heartbeat\_resource\_name] (n is the identification number of a heartbeat resource)
- (2) Type : Heartbeat resource type
- (3) Comment : Comment

#### **Description of item**

(4) IP Address: Interconnect address

#### ◆ Tips

By using the --sv option and the --hb option together, you can see the information as follows.

#### Command Line # clpstat --sv --hb --detail

```
Comment
                 : server2
  Product
                 : ExpressCluster x 2.1 for Windows
  Version
                 : 10.11
  : 10.0.0.2
  IP Address
  Network Warning Light IP Address
                 : 10.0.0.10
               : 10.0.0.12
  BMC IP Address
  CPU Frequency Status: high
   [HB0 : lankhb1]
     Type
                 : lankhb
                 : LAN Heartbeat
     Comment
     IP Address : LAN Heartbe
   [HB1 : lankhb2]
     Type
                 : lankhb
                   : LAN Heartbeat
     Comment
     IP Address
                 : 10.0.0.2
______
```

# Displaying only the resource information of certain network partition resolutions (clpstat command with the --np option)

When you want to display only the cluster configuration data on a specified network partition resolution resource, specify the name of the network partition resolution resource after the --np option in the clpstat command. If you want to see the details, specify the --detail option. If the network partition name is not specified, the cluster configuration data on all the network partition resources is displayed.

**Example of a command entry (For a** DISK network partition resolution **resource)** 

```
# clpstat --np disknp1 --detail
```

#### Example of the display after running the command:

```
[NP0 : disknp1]
                                        -> see (1)
                      : disknp
                                        -> see (2)
   Type
                      : disk resolution
   Comment
   <server1>
   Volume Mount Point
                      : H:\
                                         -> see (4)
   Disk I/O Wait Time
                     : 80
                                         -> see (5)
   <server2>
    Volume Mount Point
                      : H:\
    Disk I/O Wait Time
                      : 80
```

- The items marked by the solid line are common to all network partition resolution resources.
- ♦ The lines below "Comment" are displayed when the --detail option is used.

#### Information common to all network partition resolution resources

- (1) [NP n: network partition resolution resource name] (n is the identification number of a network partition resolution resource)
- (2) Type: Network partition resolution resource type
- (3) Comment : Comment

#### **Description of items**

(4) Volume Mount Point : Volume mount point(5) Disk I/O Wait Time : Disk I/O wait time

#### Example of a command entry (For a COM network partition resolution resource)

#### # clpstat --np comnp1 --detail

#### Example of the display after running the command:

#### **Description of item**

(1) Port Name: COM port name

# Example of a command entry (For a PING network partition resolution resource)

```
# clpstat --np pingnp1 --detail
```

# Example of the display after running the command:

# **Description of items**

```
(1) IP Addresses : IP addresses of ping destination(2) Ping Interval: Ping interval (in seconds)
```

- (3) Ping Timeout : Ping time-out (in seconds)
- (4) Ping Retry Count : Ping retry count

# Example of a command entry (For a majority network partition resolution resource)

```
# clpstat --np majonp1 --detail
```

# Example of the display after running the command:

#### **Description of item**

There is no item specific to a majority network partition resolution resource.

# Displaying only the configuration data of certain server groups (clpstat command with the --svg option)

When you want to display only the cluster configuration data on a specified server group, specify the name of the server group after the --svg option in the clpstat command. When a server group name is not specified, the cluster configuration data on all the server groups is displayed.

#### Example of a command entry

# # clpstat --svg servergroup1

#### **Example of the display after running the command:**

- Description of item
- (1) [ServerGroup n : server\_group\_name] (n is the identification number of a server group)
- (2) Server n : n is the priority number in a server group

# Displaying only the configuration data of certain groups (clpstat command with the --grp option)

When you want to display only the cluster configuration data on a specified group, specify the name of the group after the --grp option in the clpstat command. If you want to see the details, specify the --detail option. When the group name is not specified, the cluster configuration data on all the groups is displayed.

#### Example of a command entry

```
# clpstat --grp --detail
```

#### Example of the display after running the command:

```
=========== CLUSTER INFORMATION ============
  [Group0 : ManagementGroup]
                                                                           -> see (1)
                                               : cluster
                                                                             -> see (2)
    Type
    Comment
Startup Attribute
                                                                              -> see (3)
    -> see (3)
-> see (4)
Failover Exclusive Attribute : Off -> see (5)
Failback Attribute
    Failover Exclusive Attribute : Off -> see (5)
Failback Attribute : Manual Failback -> see (6)
Failover Attribute : Auto Failover -> see (7)
Servers that can run the Group: 0 server1 -> see (8)
                                              -> see (1)
: failover -> see (2)
: failover group1 -> see (3)
: Auto Startup -> see (4)
: Off
  [Group1 : failover1]
    Type
    Startup Attribute
    Startup Attribute : Additional Failback -> see (6)

Failback Attribute : Manual Failback -> see (7)

Manual Failback -> see (8)
                                              : 1 server2
  [Group2 : failover2]
                                               : failover
    Type
    Comment
Startup Attribute
                                               : failover group2
                                                : Auto Startup
    Failover Exclusive Attribute : Off
```

Failback Attribute : Auto Failback Failover Attribute : Auto Failover Servers that can run the Group: 0 server1 : 1 server2

\_\_\_\_\_\_

◆ The items below "Comment" are displayed when the --detail option is used.

(1) [Group n : group\_name] (n is the identification number of a group)

(2) Type : Group type
 (3) Comment : Comment
 (4) Startup Attribute : Startup type

Manual StartupAuto Startup

(5) Failover Exclusive Attribute : Startup exclusive attributes

No ExclusionNormal

Absolute

(6) Failback Attribute : Failback attribute

Manual FailbackAuto Failback

(7) Failover Attribute : Failover attribute

Manual FailoverAuto Failover

(8) Servers that can run the Group : Failover order

Servers that can run the Group are displayed in the failover policy sequence.

# Displaying only the configuration data of a certain group resource (clpstat command with the --rsc option)

When you want to display only the cluster configuration data on a specified group resource, specify the group resource after the --rsc option in the clpstat command. If you want to see the details, specify the --detail option. When the group resource name is not specified, the cluster configuration data on all the group resources is displayed.

#### **Example of a command entry (For floating IP resource)**

```
# clpstat --rsc fip1 --detail
```

#### Example of the display after running the command:

```
[Resource0 : fip1]
                                 : fip
                                                             -> see (2)
      Type
                              : 10.0.0.11
                                                           -> see (3)
      Comment
    Failover Target Server : stable operation server-> \sec(4)
Failover Threshold : Number of Servers -> \sec(5)
    Retry Count at Activation Failure: 5
                                                             -> see (6)
    Retry Interval at Activation Failure: 5
                                                             -> see (7)
    Final Action at Activation Failure:
    No Operation (Not activate next resource) > see (8)

Execute Script before Final Action: Off > see (9)

Retry Count at Deactivation Failure: 0 > see (10)

Retry Interval at Inactivation Failure: 5 > see (11)
     Final Action at Deactivation Failure: Stop the cluster
      service and shut down OS
                                                             +> see (12)
      Execute Script before Final Action: Off
                                                             +> see (13)
      Depended Resources :
                                                            see (14)-<mark>′۔</mark>
      IP Address : 10.0.0.11 -> see (15)
     Run ping
                                 : On
     Ping Timeout (msec) : 1000
Ping Retry Count : 5
                                                             > see (18)
      Ping Retry Interval(sec): 1
                                                             -> see (19)
     FIP Force Activation : Off
                                                             \rightarrow see (20)
___^==\
```

- The items marked by the solid line are common to all resources.
- The items marked by the dotted lines are displayed when the --detail option is used.

# Information common to all group resources

(1) [Resource n : group\_resource\_name] (n is the identification number of group resource)

(2) Type : Group resource type

(3) Comment : Comment

(4) Failover Target Server : Failover target server

The most prioritized server

• Stable operation server

(5) Failover Threshold : Failover count

(6) Retry Count at Activation Failure : Activation retry count

(7) Retry Interval at Activation Failure : Activation retry interval (in seconds)
 (8) Final Action at Activation Failure : Final action at activation failures

• No Operation (Activate next resource)

- No Operation (Not activate next resource)
- Stop Group
- Stop cluster service
- Stop the cluster service and shut down
- Stop cluster service and reboot OS
- Generate an Intentional Stop Error

(9) Execute Script before Final Action : Whether or not to execute script upon

activation failure

(10) Retry Count at Deactivation Failure : Deactivation retry count

(11) Retry Interval at Inactivation Failure : Deactivation retry interval (in seconds)

(12) Final Action at Deactivation Failure : Final action at inactivation failures

• No Operation (Deactivate next resource)

• No Operation (Not deactivate next resource)

Stop the cluster service and shut down

• Stop cluster service and reboot OS

• Generate an Intentional Stop Error

(13) Execute Script before Final Action : Whether or not to execute script upon

deactivation failure

(14) Dependent Resources : Dependent resources

# **Explanation of each item**

(15) IP Address : Floating IP address

(16) Run ping : Run ping / Do not run ping

(17) Ping Timeout (msec) : Time-out of ping to confirm redundancy (in

milliseconds)

(18) Ping Retry Count : ping retry count

(19) Ping Retry Interval (sec) : ping retry interval (in seconds)

(20) Forced FIP Activation : Floating IP force activation

#### **Example of a command entry (For virtual IP resource)**

```
# clpstat --rsc vip1 --detail
```

# Example of the display after running the command:

```
[Resource0 : vip1]
    Type
                                : vip
                      Comment
    Failover Target Server : stable operation server Failover Threshold : Number of Servers
    Retry Count at Activation Failure: 5
    Retry Interval at Activation Failure: 5
    Final Action at Activation Failure: No Operation (Not activate
                                       next resource)
    Execute Script before Final Action: Off
    Retry Count at Deactivation Failure: 0
    Retry Interval at Inactivation Failure: 0
    Final Action at Deactivation Failure: Stop the cluster setvice
                                         and shut down OS
    Execute Script before Final Action: Off
    Dependent Resources
    IP Address
                               : 10.0.1.11
                                                     see \rightarrow (1)
    Subnet Mask : 255.255.255.0
                                                     see -> (2)
    Run ping
                               : Enable
                                                     see -> (3)
    Run ping : Enable ping Timeout (msec) : 1000 Ping Retry Count : 5
                                                     see \rightarrow (4)
                                                     see -> (5)
    Ping Retry Interval (sec) : 1
                                                     see -> (6)
    VIP Force Activation : Disable
                                                     see -> (7)
```

#### **Explanation of each item**

(1) IP Address : Virtual IP address

(2) Subnet Mask : Subnet mask of the virtual IP address

(3) Run ping : Run ping / Do not run ping

(4) Ping Timeout (msec) : Time-out of ping to confirm redundancy (in milliseconds)

(5) Ping Retry Count : Ping retry count

(6) Ping Retry Interval (sec) : Ping retry interval (in seconds)

(7) VIP Forced Activation : Virtual IP forced activation

#### **Example of a command entry (For virtual computer name resource)**

# clpstat --rsc vcom1 --detail

#### Example of the display after running the command:

```
[Resource0 : vcom1]
    Type
                             : vcom
   Comment : vcom11 ....
    Failover Target Server : stable operation server Failover Threshold : Number of Servers
    Retry Count at Activation Failure: 5
    Retry interval at Activation Failure: 5
    Final Action at Activation Failure: No Operation (Not activate
                                   next resource)
    Execute Script before Final Action: Off
    Retry Count at Deactivation Failure: 0
    Retry interval at Activation Failure: 5
    Final Action at Deactivation Failure: Stop the cluster service
                                      and shut down OS
    Execute Script before Final Action: Off
    Dependent Resources : fip1
Virtual Computer Name : vcom
                                                 -> see (1)
                             : vcom11
    Target FIP Resource Name
                             : fip1
                                                -> see (2)
______
```

(1) Virtual Computer Name : Virtual computer name

(2) Target FIP Resource Name : bind target FIP resource name

# Example of a command entry (For disk resource)

```
# clpstat --rsc sd1 --detail
```

#### **Example of the display after running the command:**

```
[Resource 0 : sd1]
    Type
                              : sd
   _Comment____:_I:_
   Failover Target Server : stable operation server Failover Threshold : Number of Servers
    Retry Count at Activation Failure: 0
Retry Interval at Activation Failure : 5
    Final Action at Activation Failure: No Operation (Not activate
                                    next resource)
    Execute Script before Final Action: Off
    Retry Count at Deactivation Failure: 0
    Retry Interval at Inactivation Failure
    Final Action at Deactivation Failure: Stop the cluster service
                                       and shutdown OS
    Execute Script before Final Action: Off
    Dependent Resources
                              : disk1,fip1
    Drive Letter
                              : I:
                                                  -> see (1)
______
```

# **Explanation of each item**

(1) Drive Letter : Mount point of the volume

#### Example of a command entry (Mirror disk resource: when the Replicator is used)

# clpstat --rsc md1 --detail

#### **Example of the display after running the command:**

```
======= CLUSTER INFORMATION
   [Resource0 : md1]
    Type
                                 · md
    Comment__
                           ______;_
    Failover Target Server : stable operation server Failover Threshold : Number of Servers
    Retry Count at Activation Failure: 0
    Retry Interval at Activation Failure
    Final Action at Activation Failure: No Operation (Not activate
                                       next resource)
    Execute Script before Final Action: Off
    Retry Count at Deactivation Failure: 0
    Retry Interval at Inactivation Failure : 5
    Final Action at Deactivation Failure: Stop the cluster service
                                         and shut down OS
    Execute Script before Final Action: Off
    Depended Resources
    Mirror Disk No.
                                                       -> see (1)
                                : I:
    Drive Letter
                                                       -> see (2)
    Cluster Partition - Drive Letter: H:
                                                      -> see (3)
    Cluster Partition - Offset Index : 0
                                                      -> see (4)
    Execute the initial mirror construction: Enable
                                                      -> see (5)
    Mode : Synchronous
    Request Queue Maximum Size(KB): 2048
    Mirror Connect Timeout(sec) : 20
                                                      -> see (8)
    Asynchronous - History Files Store Folder: -> see (9) Asynchronous - Kernel Queue Size (KB): 2048 -> see (10)
    Asynchronous - Application Queue Size(KB): 2048 -> see (11)
    Asynchronous - Thread Timeout (sec): 30 -> see (12)
```

#### Explanation of each item

- (1) Mirror Disk No.: Mirror disk number
- (2) Drive Letter : Drive letter
- (3) Cluster Partition Drive letter : Drive letter
- (4) Cluster Partition Offset Index : Offset index
- (5) Execute the initial mirror construction : Execute the initial mirror construction/Do not execute the initial mirror construction
- (6) Mode : Synchronous/Asynchronous
- (7) Request Queue Maximum Size(KB) : Maximum size of the request queue (KB)
- (8) Mirror Connect Timeout(sec): Mirror connect time-out (in seconds)
- (9) Asynchronous History Files Store Folder : History file storage folder
- (10) Asynchronous Kernel Queue Size (KB): Kernel queue size (KB)
- (11) Asynchronous Application Queue Size(KB) : Application queue size (KB)
- (12) Asynchronous Thread Timeout(sec): Thread time-out (in seconds)

# **Example of a command entry (For print spooler resource)**

# clpstat --rsc spool1 --detail

#### **Example of the display after running the command:**

```
[Resource0 : spool1]
    Type
                              : regsync
    Comment
    Failover Target Server : stable operation server
    Failover Threshold
                             : Number of Servers
    Retry Count at Activation Failure: 0
Retry Interval at Activation Failure
    Final Action at Activation Failure: No Operation (Not activate
                                    next resource)
    Execute Script before Final Action: Off
    Retry Count at Deactivation Failure: 0
    Retry Interval at Inactivation Failure
    Final Action at Deactivation Failure: Stop the cluster service
                                      and shutdown OS
    Execute Script before Final Action: Off
    Dependent Resources
                              : md1
    Printer Name
                              : NEC MultiImpact 700EX -> see (1)
                              : I:
                                                    -> see (2)
    Partition
    Spool Directory
                              : \SPOOL1
                                                    -> see (3)
______
```

#### **Explanation of each item**

Printer Name : Printer name
 Partition : Partition
 Spool directory : Spool directory

# Example of a command entry (For a registry synchronization resource)

# clpstat --rsc regsync1 --detail

#### Example of the display after running the command:

```
========== CLUSTER INFORMATION ===========
   [Resource0 : regsync1]
     Type
                                   : regsync
     Comment
    Failover Target Server : stable operation server
    Failover Threshold
                                  : Number of Servers
    Retry Count at Activation Failure: 0 Retry Interval at Activation Failure
    Final Action at Activation Failure: No Operation (Not activate
                                          next resource)
    Execute Script before Final Action: Off
     Retry Count at Deactivation Failure: 0
     Retry Interval at Inactivation Failure
     Final Action at Deactivation Failure: Stop the cluster service
                                            and shutdown OS
     Execute Script before Final Action: Off
     Dependent Resources
                                   : fip1,vcom1,md1
: HKEY_LOCAL_MACHINE\SOFTWARE\A
     Registry Key
                                   -> see (1)
```

# **Explanation of each item**

(1) Registry Key : Registry key

#### **Example of a command entry (For application resource)**

# clpstat --rsc appli1 --detail

# Example of the display after running the command:

```
[Resource0 : appli1]
    Type
                                 : appli
                          : notepad
    Comment
    Failover Target Server : stable operation server Failover Threshold : Number of Servers
    Retry Count at Activation Failure : 0
    Retry Interval at Activation Failure
    Final Action at Activation Failure: No Operation (Not activate
                                       next resource)
    Execute Script before Final Action: Off
    Retry Count at Deactivation Failure: 0
    Retry Interval at Inactivation Failure
    Final Action at Deactivation Failure: Stop the cluster service
                                         and shutdown OS
    Execute Script before Final Action: Off
    Depended Resources : fip1, vcom, md1
    Resident Type : Resident -> see (1)
                                            -> see (2)
    Target VCOM Resource Name:
    Start Path : C:\WINDOWS\notepad.exe-> see (3)
[Start] Type : Synchronous -> see (4)
     [Start] Type : Syncr
[Start] Timeout(sec) : 1800
                                                      -> see (5)
     [Start] Current Directory:
                                                      -> see (6)
     [Start] Option Parameter :
                                                      -> see (7)
     [Start] Window Size : Hide
                                                      -> see (8)
     [Start] Domain
                                                      -> see (9)
     [Start] Account
                                                     -> see (10)
     [Start] Allow to Interact with Desktop: Disable -> see (11)
     [Start] Execute from the Command Prompt: Disable, -> see (12)
    Stop Path :
                                                     -> see (13)
     [Stop ] Type : Synchronous [Stop ] Timeout (sec) : 1800
    [Stop ] Type
                                                     i -> see (14)
                                                     \rightarrow see (15)
     [Stop ] Current Directory:
                                                     ' -> see (16)
     [Stop ]Option Parameter :
                                                     -> see (17)
     [Stop ] Window Size : Hide
                                                     -> see (18)
     [Stop | Domain
                                                     -> see (19)
     [Stop ] Account
                                                     -> see (20)
     [Stop ] Allow to Interact with Desktop: Disable -> see (21)
     [Stop] Execute from the Command Prompt: Disable -> see (22)
_____
```

#### **Explanation of each item**

(1)	Resident Type	: Resident/Non-Resident

(2) Target VCOM Resource Name : Virtual computer name resource of target

(3) Start Path : Application path at start

(4) [Start] Type : Synchronous/Asynchronous at start(5) [Start] Timeout (sec) : Time-out period at start (in seconds)

(6) [Start] Current Directory : Execution directory at start
 (7) [Start] Option Parameter : Option parameter at start
 (8) [Start] Window Size : Window size at start

(9) [Start] Domain :Domain at start

(10) [Start] Account :Account at start

(11) [Start] Allow to Interact with Desktop :Allow to interact with desktop at start/Do not allow to interact with desktop at start

(12) [Start] Execute from the Command Prompt :Execute from the command prompt at start/Do not Execute from the command prompt at start

(13) Stop Path : Application path at stop

(14) [Stop ]Type : Synchronous/Asynchronous at stop(15) [Stop ]Timeout(sec) : Time-out period at stop (in seconds)

(16) [Stop ]Current Directory
(17) [Stop ]Option Parameter
(18) [Stop ]Window Size
(19) [Stop ]Domain
(20) [Stop ]Account
(20) Execution directory at stop
(21) (Stop )

(21) [Stop ]Allow to Interact with Desktop : Allow to interact with desktop at stop/Do not allow to interact with desktop at stop

(22) [Stop ]Execute from the Command Prompt : Execute from the command prompt at stop/Do not execute from the command prompt at stop

#### Example of a command entry (For script resource)

# clpstat --rsc script1 --detail

# Example of the display after running the command:

```
[Resource0 : script1]
 Type
                            : script
 Comment
                      : script resource1
 Failover Target Server : stable operation server
Failover Threshold : Number of Servers
 Retry Count at Activation Failure: 0
 Retry Interval at Activation Failure
 Final Action at Activation Failure: No Operation (Not activate
                                  next resource)
 Execute Script before Final Action: Off
 Retry Count at Deactivation Failure: 0
 Retry Interval at Inactivation Failure
 Final Action at Deactivation Failure: Stop the cluster service
                                    and shut down OS
 Execute Script before Final Action: Off
                         : fip1,vcom,md1
 Depended Resources
 Depended Resource Name :
 Start Path : start.bat
                                        -> see (2)
-> see (3)
 [Start] Type : Synchronous [Start] Timeout(sec) : 1800
 [Start] Allow to Interact with Desktop: Disable : -> see (5)
 Stop Path : stop.bat -> see (6)
 [Stop ] Type : Synchronous [Stop ] Timeout (sec) : 1800
                                                -> see (7)
 [Stop ] Allow to Interact with Desktop:Disable -> see (8)
```

### **Explanation of each item**

(1) Target VCOM Resource Name : Target VCOM resource name

(2) Start Path : Path of start script

(3) [Start] Type :Synchronous/Asynchronous of start script path

(4) [Start] Timeout (sec) :Time-out period of start script (in seconds)

(5) [Start] Allow to Interact with Desktop : Allow to interact with desktop at start / Do not

allow to interact with desktop at start

(6) Stop Path : Path of stop script

(7) [Stop]Type : Synchronous/Asynchronous of stop script

(8) [Stop]Timeout (sec) : Time-out period (in seconds) of stop script

(9) [Stop ]Allow to Interact with Desktop : Allow to interact with desktop at stop /Do not allow to interact with desktop at stop

#### Example of a command entry (For service resource)

# clpstat --rsc service1 --detail

#### Example of the display after running the command:

```
[Resource0 : service1]
    Type
                              : service
    _Comment ______: Telnet _____
   Failover Target Server : stable operation server Failover Threshold : Number of Servers
    Retry Count at Activation Failure : 0
    Retry Interval at Activation Failure
    Final Action at Activation Failure: No Operation (Not activate
                                    next resource)
    Execute Script before Final Action: Off
    Retry Count at Deactivation Failure: 0
    Retry Interval at Inactivation Failure
    Final Action at Deactivation Failure: Stop the cluster service
                                       and shut down OS
    Execute Script before Final Action: Off
    Dependent Resources : fip1,vcom,md1
                            : Telnet
    Service Name
                                                  -> see (1)
    Start Parameters
                                                  -> see (2)
    Do not assume it as an error when the service is already started:
    Disable
    Target VCOM Resource Name:
                                                  -> see (4)
    [Start] Type : Synchronous [Start] Timeout(sec) : 1800
                                                  -> see (5)
                                                  -> see (6)
                            : Synchronous
    [Stop] Type
                                                  -> see (7)
    [Stop]Timeout(sec) : 1800
______
```

# **Explanation of each item**

- (1) Service Name : Service name/Service display name
- (2) Start Parameter: Parameter to give when service starts
- (3) Do not assume it as an error when the service is already started : Behaviors when service has been already started
- (4) Target VCOM Resource Name : Target VCOM resource name
- (5) [Start] Type :Synchronous/Asynchronous when service starts
- (6) [Start] Timeout (sec) :Time-out period (in seconds) when service starts
- (7) [Stop] Type :Synchronous/Asynchronous when service stops
- (8) [Stop ] Timeout(sec) :Time-out period (in seconds) when service stops

# ◆ Tips

By using the --grp option and the --rsc option together, you can display the information as follows

# Command Line # clpstat --grp --rsc

```
========== CLUSTER INFORMATION ===========
 [Group0 : ManagementGroup]
  Comment
   [Resource0 : ManagementIP]
                             : fip
    Type
    Comment
                             : 10.0.0.10
    IP Address
 [Group1 : failover1]
   Comment
                             : failover group1
   [Resource0 : fip1]
    Type
                             : fip
                             : 10.0.0.11
    Comment
    IP Address
                             : 10.0.0.11
   [Resource1 : md1]
    Type
                             : md
    Comment
                             : I:
    Mirror Disk No.
                             : 1
    Drive Letter
                             : I:
   [Resource2 : script1]
    Type
                            : script
                             : script resource1
    Comment
                             : start.bat
    Start Path
    Stop Path
                             : stop.bat
 [Group2 : failover2]
   Comment
                             : failover group2
   [Resource0 : fip2]
    Type
                             : fip
    Comment
                             : 10.0.0.12
    IP Address
                             : 10.0.0.12
   [Resource1 : md2]
    Type
                             : md
    Comment
                             : J:
    Mirror Disk No.
                             : 2
    Drive Letter
                             : J:
   [Resource2 : script2]
    Type
                             : script
    Comment
                             : script resource2
    Start Path
                             : start.bat
    Stop Path
                            : stop.bat
______
```

# Displaying only the data of a certain monitor resource (clpstat command with the --mon option)

When you want to display only the cluster configuration data on a specified monitor resource, specify the name of the monitor resource after the --mon option in the clostat command. If you want to see the details, specify --detail option. When a monitor resource name is not specified, the configuration data of all the monitor resources is displayed.

#### **Example of a command entry (For floating IP monitor resource)**

# clpstat -mon fipw1 --detail

#### Example of the display after running the command:

```
[Monitor0 : fipw1]
                                                                    -> see (1)
   Type
                                          : fipw
                                                                     -> see (2)
  : fip1
/Monitor Timing
                                                                    -> see (3)
                                         : Active
                                                                    -> see (4)
   Monitor Timing : Active
Target Resource : fip1
Interval : 60
Timeout : 60
Retry Count : 1
Final Action : No Operation
Execute Script before Final Action: Off
Recovery Target : failover1
Recovery Target Type : Group
Reactivation Threshold : 3
   Target Resource : fip1
                                                                    -> see (5)
                                                                    -> see (6)
                                                                    -> see (7)
                                                                    -> see (8)
                                                                    -> see (9)
                                                                    -> see (10)
                                                                   -> see (11)
   Recovery Target Type : Group -> see
Reactivation Threshold : 3 -> see
Failover Target Server : Stable operation server
                                                                    -> see (12)
                                                                   -> see (13)
                                                                    -> see (14)
                                : Number of Servers -> see (15)
   Failover Threshold
   Wait Time to Start Monitoring : 0
                                                                   ' -> see (16)
   Monitor NIC Link Up/Down : Enable
                                                                    -> see (17)
______
```

- ◆ The items marked by the solid line are common to all resources.
- ◆ The items marked by the dotted line are displayed when the --detail option is used.

#### Explanation of items common to all monitor resources

(1) [MONITOR n: monitor\_resource\_name] (n is the identification number of the group)

(2) Type : Monitor resource type

(3) Comment : Comment

(4) Monitor Timing : Timing to start monitoring

Always

Active

(5) Target Resource : Monitor target resource

(6) Interval : Monitor interval

(7) Timeout : Monitor time-out (in seconds)

(8) Retry Count : Monitor retry count

(9) Final Action : Action taken when the retry count exceeds

No Operation Stop Group

Stop the cluster service

Stop the cluster service and shutdown OS

Stop cluster service and reboot OS

Generate an Intentional Stop Error

(10) Execute Script before Final Action : Whether or not to execute script before final action

(11) Recovery Target : Target to be recovered when an error is detected

(12) Recovery Target Type : Type of a target to be recovered when an error is detected

Group Resource Itself

(13) Reactivation Threshold : Restart count

(14) Failover Target Server : Failover target server

The most prioritized server

• Stable operation server

(15) Failover Threshold : Failover count

(16) Wait Time to Start Monitoring: Time to wait for the start of monitoring

# **Explanation of each item**

 $(17)\ Monitor\ NIC\ Link\ Up/Down/Do\ not\ monitor\ NIC\ Link\ Up/Down/Do\ not\ monitor\ NIC\ Link$ 

Up/Down

# Example of a command entry (For virtual IP monitor resource)

# clpstat -mon vipw1 --detail

#### **Example of the display after running the command:**

```
[Monitor0 : vipw1]
Type : vipw
Comment : vip1
Monitor Timing : Active
Target Resource : vip1
Interval : 60
Timeout : 1
Final Action : No Operation
Execute Script before Final Action: Off
Recovery Target : failover1
Recovery Target Type : Group
Reactivation Threshold : 3
Failover Target Server : stable operation server
Failover Threshold : Number of Servers
Wait Time to Start Monitoring : 0
```

#### **Explanation of each item**

There is no item specific to virtual IP monitor resource.

#### **Example of a command entry (For virtual computer name monitor resource)**

# clpstat -mon vcomw1 --detail

### **Example of the display after running the command:**

```
[Monitor0 : vcomw1]
   Type
                                  : vcomw
  Comment : vcom1

Monitor Timing : Active
  Target Resource : vcom1
                                 : 60
: 60
   Interval
   Timeout
  Retry Count
                                 : 1
                        : Stop the cluster service and shut
  Final Action
                                   down OS
  Execute Script before Final Action: Off
 Recovery Target : cluster
Recovery Target Type : Itself
Reactivation Threshold : 0
Failover Target Server : stable operation server
Failover Threshold : 0
   Wait Time to Start Monitoring : 0
```

\_\_\_\_\_\_

#### **Explanation of each item**

There is no item specific to virtual computer name monitor resource.

# Example of a command entry (For disk TUR monitor resource)

# clpstat -mon sdw1 --detail

# **Example of the display after running the command:**

```
[Monitor0 : sdw1]
Type : sdw
Comment

Monitor Timing : Always
Target Resource :
Interval : 60
Timeout : 300
Retry Count : 0
Final Action : No Operation
Execute Script before Final Action: Off
Recovery Target : failover1
Recovery Target Type : Group
Reactivation Threshold : 0
Failover Target Server : stable operation server
Failover Threshold : Number of Servers
Wait Time to Start Monitoring : 0
Disk Resource : sd1 -> see (1)
```

#### **Explanation of each item**

(1) Disk Resource: Target disk resource name

#### Example of a command entry (For disk RW monitor resource)

# clpstat --mon diskw1 --detail

#### **Example of the display after running the command:**

```
[Monitor0 : diskw1]
   Type
                                 : diskw
 Comment : Always
Monitor Timing : Always
Target Resource :
                 : 30
: 300
: 0
: No Operation
   Interval
  Timeout
 Retry Count
Final Action
  Execute Script before Final Action: Off
  Recovery Target : failover1
Recovery Target Type : Group
Reactivation Threshold : 0
Failover Target Server : stable operation server
Failover Threshold : Number of Servers
   Wait Time to Start Monitoring: 0
  File Name : C:\a.txt
                                                      -> see (1)
  I/O Size (byte) : 2000000 -> see (2)
Action on Stall : STOP Error -> see (3)
```

# **Explanation of each item**

(1) File Name : File name

(2) I/O size (byte) : I/O size (in bytes)

(3) Action on Stall: Actions taken when an stall is detected

# Example of a command entry (For mirror disk monitor resource)

# clpstat --mon mdw1 --detail

#### Example of the display after running the command:

```
[Monitor0 : mdw1]
Type : mdw
Comment : ...
Monitor Timing : Always
Target Resource :
Interval : 30
Timeout : 999
Retry Count : 0
Final Action : No Operation
Execute script Before Final Action: Off
Recovery Target : md1
Recovery Target Type : Resource
Reactivation Threshold : 0
Failover Target Server : stable operation server
Failover Threshold : Number of Servers
Wait Time to Start Monitoring : 0
Mirror Disk Resource Name : md1 -> see (1)
```

# **Explanation of each item**

(1) Mirror Disk Resource Name : Target mirror disk resource name

#### **Example of a command entry (For mirror connect monitor resource)**

# clpstat --mon mdnw1 --detail

### **Example of the display after running the command:**

```
[Monitor0 : mdnw1]
  Type
                             : mdnw
  Comment
 Monitor Timing : Always
Target Resource :
                            : 60
: 10
  Interval
 Timeout
               : 0
: No Operation
 Retry Count
Final Action
  Execute Script before Final Action: Off
 Recovery Target : mdl
Recovery Target Type : Resource
Reactivation Threshold : 0
Failover Target Server : stable operation server
Failover Threshold : 0
  Wait Time to Start Monitoring: 0
  Mirror Disk Resource Name : mdl
                                               -> see (1)
______
```

# **Explanation of each item**

(1) Mirror Disk Resource Name : Target mirror disk resource name

#### **Example of a command entry (For print spooler monitor resource)**

# clpstat --mon spoolw1 --detail

### **Example of the display after running the command:**

```
[Monitor0 : spoolw1]
Type : spoolw
Comment : spool1

Monitor Timing : Active
Target Resource : spool1
Interval : 60
Timeout : 60
Retry Count : 1
Final Action : No Operation
Execute Script before Final Action: Off
Recovery Target : failover1
Recovery Target Type : Group
Reactivation Threshold : 3
Failover Target Server : stable operation server
Failover Threshold : Number of Servers
Wait Time to Start Monitoring : 0
```

#### **Explanation of each item**

There is no item specific to print spooler monitor resources.

#### **Example of a command entry (For registry synchronization monitor resource)**

# clpstat --mon regsyncw1 --detail

#### **Example of the display after running the command:**

```
[Monitor0 : regsyncw1]
                Type
                                                                                                                                                                    : regsyncw
         : regsynce : Active : Target Resource : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regsynce : regs
                                                                                                                                                                           regsync1
                                                                                                                                                                : regsync1
                                                                                                                                                                 : 60
               Interval
                                                                                                                                                                 : 60
              Timeout
         Retry Count
Final Action
                                                                                                                                                               : 1
                                                                                                                  : No Operation
               Execute Script before Final Action: Off
           Recovery Target : failover1
Recovery Target Type : Group
         Recovery Target Type : Group
Reactivation Threshold : 3
Failover Target Server : stable operation server
Failover Threshold : Number of Servers
                                                                                                                                                                : Number of Servers
               Failover Threshold
               Wait Time to Start Monitoring: 0
```

#### **Explanation of each item**

There is no item specific to registry synchronous monitor resources.

# Example of a command entry (For application monitor resource)

# clpstat --mon appliw1 --detail

# Example of the display after running the command:

#### **Explanation of each item**

There is no item specific to application monitor resources.

#### **Example of a command entry (For service monitor resource)**

# clpstat --mon servicew1 --detail

### **Example of the display after running the command:**

```
[Monitor0 : servicew1]
   Type
                                 : servicew
 Comment
Monitor Timing
Target Resource
                : service1
                                : Active
                                : service1
                                : 60
: 60
   Interval
  Timeout
  Retry Count
Final Action
                      : 1
: No Operation
   Execute Script before Final Action: Off
  Recovery Target : failover1
Recovery Target Type : Group
  Recovery Target Type : Group
Reactivation Threshold : 3
Failover Target Server : stable operation server
Failover Threshold : Number of Servers
                                : Number of Servers
   Failover Threshold
Wait Time to Start Monitoring: 0
```

#### **Explanation of each item**

There is no item specific to service monitor resources.

# Example of a command entry (For IP monitor resource)

# clpstat --mon ipw1 --detail

#### Example of the display after running the command:

### **Explanation of each item**

- (1) IP Addresses : Monitor Target IP Addresses
- (2) Ping Timeout (msec) : ping time-out time (in milliseconds)

#### Example of a command entry (For NIC Link Up/Down monitor resource)

# clpstat --mon miiw1 --detail

### **Example of the display after running the command:**

```
[Monitor0 : miiwl]
   Type
                                  : miiw
   Comment
  Monitor Timing
                                  : Always
  Target Resource
                                 : 60
   Interval
   Timeout
                                 : 60
  Retry Count
Final Action
                                 : 1
                               : No Operation
  Execute Script before Final Action: Off
Recovery Target : cluster
Recovery Target Type : Itself
  Recovery Target Type : Itself
Reactivation Threshold : 0
Failover Target Server : stable operation server
Failover Threshold : 0
   Failover Threshold
   Wait Time to Start Monitoring: 0
```

#### **Explanation of each item**

There is no item specific to NIC Link Up/down monitor resources.

# **Example of a command entry (For multi target monitor resource)**

# clpstat --mon mtw1 --detail

# Example of the display after running the command:

```
========= CLUSTER INFORMATION ===========
 [Monitor0 : mtw1]
   Type
                                    : mtw
   Comment
  Monitor Timing : Always
Target Resource :
Interval
                                   : 60
   Interval
                                   : 60
  Timeout
  Retry Count : 1
Final Action : No Operation
   Execute Script before Final Action: Off
  Recovery Target : failover1
Recovery Target Type : Group
Reactivation Threshold : 3
Failover Target Server : stable operation server
Failover Threshold : Number of Servers
   Wait Time to Start Monitoring: 0
   Monitor Resources : appliw1
                                                          -> see (1)
                                   : fipw1
______
```

#### **Explanation of each item**

(1) Monitor Resources: Monitor resources to be grouped

# Displaying all cluster configuration data (clpstat command with the -i option)

By specifying the -i option, you can display the configuration information that is shown when --cl, --sv, --hb, --np, --svg, --grp, --rsc, and --mon options are all specified.

If you run the command with the -i option and the --detail option together, all the detailed cluster configuration data is displayed. Because this option displays large amount of information at a time, use a command, such as the more command, and pipe, or redirect the output in a file for the output.

# ◆ Tips

Specifying the -i option displays all the information on a console. If you want to display some of the information, it is useful to combine the --cl, --sv, --hb, --np, --svg, --grp, --rsc, and/or --mon option. For example, you can use these options as follows:

# Example of a command entry:

If you want to display the detailed information of the server whose name is "server0," the group whose name is "failover1," and the group resources of the specified group, enter:

```
# clpstat --sv server0 --grp failover1 --rsc --detail
```

# **Status Descriptions**

Server			
Function	Status	Description	
Status display	Online	Starting	
Heartbeat resource status	Offline	Offline pending	
display	Warning	Heartbeat resource failure	
	Isolated	Suspension (isolated)	
	Online Pending	Now being started	
	Offline Pending	Now being stopped	
	Pending	Suspension (Network partition unsolved)	
	Unknown	Status unknown	
Group map display	0	Starting	
Monitor resource status display	i	Suspension (isolated)	
	р	Now being started/stopped, , Network partition unsolved	
	х	Offline Pending	
	-	Status unknown	

Heartbeat Resource			
Function	Status	Description	
Status display	Normal	Normal	
	Warning	Failure (Some)	
	Error	Failure (All)	
	Not Used	Not used	
	Unknown	Status unknown	
Heartbeat resource status	0	Able to communicate	
display	х	Unable to communicate	
	-	Not used or status unknown	

Network Partition Resolution Resource			
Function	Status	Description	
Status display	Normal	Normal	
	Caution	Failure (Some)	
	Error	Failure (All)	
	Unused	Not used	
	Unknown	Status unknown	
Network partition resolution	0	Able to communicate	
resource status display	х	Unable to communicate	
	-	Not used or status unknown	

Group			
Function	Status	Description	
Status display	Online	Started	
	Offline	Stopped	
	Online Pending	Now being started	
	Offline Pending	Now being stopped	
	Error	Error	
	Unknown	Status unknown	
Group map display	0	Started	
	е	Error	
	р	Now being started/stopped	

Group Resource			
Function	Status	Description	
Status display	Online	Started	
	Offline	Stopped	
	Online Pending	Now being started	
	Offline Pending	Now being stopped	
	Online Failure	Starting failed	
	Offline Failure	Stopping failed	
	Unknown	Status unknown	

Monitor Resource			
Function	Status	Description	
Status display	Normal	Normal	
	Warning	Error (Some)	
	Error	Error (All)	
	Not Used	Not Used	
	Unknown	Status Unknown	
Monitor resource status display	Online	Started	
	Offline	Stopped	
	Warning	Warning	
	Suspend	Stopped temporary	
	Online Pending	Now being started	
	Offline Pending	Now being stopped	
	Online Failure	Starting failed	
	Offline Failure	Stopping failed	
	Not Used	Not used	
	Unknown	Status unknown	

# **Operating the cluster (clpcl command)**

clpcl: the clpcl command operates a cluster

# **Command line:**

```
clpcl -s [-a] [-h hostname]
clpcl -t [-a] [-h hostname] [-w time-out]
clpcl -r [-a] [-h hostname] [-w time-out]
clpcl -return [-h hostname]
clpcl --suspend [--force] [-w time-out]
clpcl --resume
```

Description	This command starts, stops, return, suspends, or resumes the	
	ExpressCluster service.	

Option	-S	Starts the ExpressCluster service.	
	-t	Stops the ExpressCluster service.	
	-r	Restarts the ExpressCluster service.	
	return	Returns the ExpressCluster service.	
	suspend	Suspends the entire cluster	
	resume	Resumes the entire cluster	
	-a	Executed the command on all servers	
	-h host_name	Makes a request to run the command to the server specified in <i>host_name</i> . Makes a processing request to the server on which this command runs (local server) if the -h option is omitted.	
	-W time-out	Whent,r, orsuspend option is used, specify the wait time in seconds that the clpcl command waits for the ExpressCluster service to be completely stopped or suspended.	
		When a time-out is not specified, it waits for unlimited time.	
		When "0 (zero)" is specified, it does not wait.	
		When the -w option is not specified, it waits for twice the heartbeat time-out (in seconds).	
	force	When used with thesuspend option, forcefully suspends the cluster regardless of the status of all the servers in the cluster.	

Return Value	0	Success
	Other than 0	Failure

#### Notes

Run this command as a user with Administrator privileges.

For the name of a server for the -h option, specify the name of a server in the cluster that allows name resolution.

When you suspend the cluster, the ExpressCluster service should be activated in all servers in the cluster. When the --force option is used, the cluster is forcefully suspended even if there is any stopped server in the cluster.

When you start up or resume the cluster, access the servers in the cluster in the order below, and use one of the paths that allowed successful access.

- 1. via the IP address on the interconnect LAN
- 2. via the IP address on the public LAN
- 3. via the IP address whose name was resolved by the server name in the cluster configuration data

When you resume the cluster, use the clpstat command to see there is no activated server in the cluster.

# Example of a command entry

**Example 1:** Activating the ExpressCluster service in the local server

# clpcl -s

Command succeeded

**Example 2:** Activating the ExpressCluster service in server1 from server0

# clpcl -s -h server1

Start server1 : Command succeeded.

If a server name is specified, the display after running the command should look similar to above.

Start server\_name: Execution result

**Example 3:** Activating the ExpressCluster service in all servers

# clpcl -s -a

Start server0 : Command succeeded.

Start server1 : Performed startup processing to the active cluster service.

When all the servers are activated, the display after running the command should look similar to above.

Start server\_name: Execution result

**Example 4:** Stopping the ExpressCluster service in all servers

# clpcl -t -a

Stop server0 : Command succeeded.

Stop server1 : Command succeeded.

When all the servers are stopped, the display after running the command should look similar to above. Stop *server\_name*: Execution result.

When the stopping process fails, the display may be different from the example above depending on the process.

Wait for the stopping of all servers of the ExpressCluster service.

#### ♦ Suspend and Resume

When you want to update the cluster configuration data or ExpressCluster, you can stop the ExpressCluster service while continuing the operation. This status is called "suspend." Returning from the suspended status to normal status is called "resume."

Suspend and resume are executed to all servers in the cluster. When you suspend the cluster, the ExpressCluster service should be activated in all servers in the cluster.

The following functions stop when the cluster is suspended because the ExpressCluster service stops while active resources stay active.

- All heartbeat resources stop.
- All network partition resolution resources stop.
- All monitor resources stop.
- You cannot work on groups or group resources (start, stop, or move).
- You cannot display or change the cluster status by the WebManager or with the clpstat command.
- The following commands are disabled;
  - clpstat
  - clpcl options other than --resume
  - clpdown
  - clpstdn
  - clpgrp
  - clptoratio
  - clpmonctrl

#### **Error Messages**

Message	Cause/Solution	
Log in as administrator.	Log in as a user with Administrator privileges.	
Invalid configuration file. Create valid cluster configuration data by using the Builder.	Create valid cluster configuration data using the Builder.	
Invalid option.	Specify a valid option	
Performed stop processing to the stopped cluster service.	The stopping process has been executed to the stopped ExpressCluster service.	
Performed startup processing to the active cluster service.	The startup process has been executed to the activated ExpressCluster service.	
Command timeout.	The command timed out.	
Failed to return the server. Check the status of failed server.	Failed to return the server. Check the status of the failed server.	
Could not connect to the server. Check if the cluster service is active.	Check if the ExpressCluster service is activated.	
Failed to obtain the list of nodes. Specify a valid server name in the cluster.	Specify the valid name of a server in the cluster.	
Failed to obtain the service name.	Failed to obtain the service name.	
Failed to operate the service.	Failed to operate the service.	
Resumed the cluster service that is not suspended.	Resumed the ExpressCluster service that is not suspended.	
invalid server status.	Check if the ExpressCluster service is activated.	
Server is busy. Check if this command is already run.	This command may be run already. Check it.	
Server is not active. Check if the cluster service is active.	Check if the ExpressCluster service is activated.	
There is one or more servers of which cluster service is active. If you want to perform resume, check if there is any server whose cluster service is active in the cluster.	When you execute the command to resume, check if there is no server in the cluster on which the ExpressCluster service is activated.	
All servers must be activated. When suspending the server, the cluster service need to be active on all servers in the cluster.	When you execute the command to suspend, the ExpressCluster service must be activated in all servers in the cluster.	
Resume the server because there is one or more suspended servers in the cluster.	Execute the command to resume because some server(s) in the cluster is suspended.	
Invalid server name. Specify a valid server name in the cluster.	Specify the valid name of a server in the cluster.	
Connection was lost. Check if there is a server where the cluster service is stopped in the cluster.	Check if there is any server on which the ExpressCluster service has stopped in the cluster.	
invalid parameter.	The value specified as a command parameter may be invalid.	

Message	Cause/Solution
Internal communication timeout has occurred in the cluster server. If it occurs	A timeout occurred in the ExpressCluster internal communication.
frequently, set the longer timeout.	If time-out keeps occurring, set the internal communication time-out longer.
Processing failed on some servers. Check the status of failed servers.	If stopping process is executed to all servers, there is one or more servers on which the stopping process has failed.
	Check the status of the server(s) on which the stopping process has failed.
Internal error. Check if memory or OS resources are sufficient.	Check if the memory or OS resource is sufficient.

## Shutting down a specified server (clpdown command)

clpdown: the clpdown command shuts down a specified server.

#### **Command line**

Description	This command stops the ExpressCluster service and shuts down a server.	
Option	None	Shuts down a server.
	-r	Reboots the server.
	-h host_name	Makes a processing request to the server specified in <i>host_name</i> . Makes a processing request to the server on which this command runs (local server) if the -h option is omitted.
Return Value	0	Success
	Other than 0	Failure
Notes	Run this command as a user with Administrator privileges.  For the name of a server for the -h option, specify the name of a server in the cluster.  When the Replicator/Replicator DR is used, do not run this command while activating a group.  A group can not be deactivated while it is being activated. Because of this, the OS may shut down while the mirror disk resource/hybrid disk resource is not deactivated properly, which can result in mirror break.	
Example of a command entry	Example 1: Stopping and shutting down the ExpressCluster service in the local server # clpdown Example 2: Shutting down and rebooting server1 from server0	
	# clpdown	-r -h server1
Error Message	See "Operating the cluster (clpcl command)" on page 251.	

## Shutting down the entire cluster (clpstdn command)

 $clpstdn: \ the \ clpstdn \ command \ shuts \ down \ the \ entire \ cluster$ 

#### **Command line**

clpstdn [-r] [-h hostname]

Description	This command stops the ExpressCluster service in the entire cluster and shuts down all servers.	
Option	None Executes cluster shutdown.	
	-r	Executes cluster shutdown reboot.
	-h host_name	Makes a processing request to the server specified in <i>host_name</i> . Makes a processing request to the server on which this command runs (local server) if the -h option is omitted.
Return Value	0	Success
	Other than 0	Failure
Notes	Run this command as a user with Administrator privileges.  For the name of a server for the -h option, specify the name of a server in the cluster.  A server that cannot be accessed from the server that runs the command (for example, a server with all LAN heartbeat resources are off-line.) will not shut down.  When the Replicator/Replicator DR is used, do not execute this command while activating a group.  A group cannot be deactivated while it is being activated. Because of this, the OS may shut down while the mirror disk resource/hybrid disk resource is not deactivated properly, which can result in mirror break.	
Example of a command entry	Example 1: Shutting down the cluster # clpstdn  Example 2:Performing the cluster shutdown reboot # clpstdn -r	
Error Message	See "Operating the cluster (clpcl command)" on page 251.	

## **Operating groups (clpgrp command)**

 $clpgrp: \hbox{the clpgrp command operates groups}$ 

#### **Command line**

```
clpgrp -s [group_name] [-h hostname] [-f]
clpgrp -t [group_name] [-h hostname] [-f]
clpgrp -m group_name [-h hostname] [-a host_name]
```

Description	This command starts, deactivates or moves groups.
-------------	---

	1	
Option	-s [group_name]	Starts groups. When you specify the name of a group, only the specified group starts up. If no group name is specified, all groups start up.
	-t [group_name]	Stops groups. When you specify the name of a group, only the specified group stops. If no group name is specified, all groups stop.
	-m	Moves a specified group.
	group_name	
	-h	Makes a processing request to the server specified in <i>host_name</i> . Makes a processing request to the
	host_name	server on which this command runs (local server) if the -h option is omitted.
	-a	Defines the server which is specified by <i>host_name</i> as a destination to which a group will be moved.
	host_name	When the -a option is omitted, the group will be moved according to the failover policy
	-f	If you use this option with the -s option against a group activated on a remote server, it will
		forcefully be started on the server that requested the process.
		If this command is used with the -t option, the group will be stopped forcefully.

Return Value	0	Success
	Other than 0	Failure

Notes	Run this command as a user with Administrator privileges.		
	The ExpressCluster service must be activated on the server that runs this command		
	Specify a server in the cluster when you specify the name of server name for the -h and -a options.		
	Make sure to specify a group name, when you use the -m option.		
	When "Normal" is configured for the failover exclusion attribute of a group and you want to move the group with the –m option, explicitly specify a server to which the group is moved by using the –a option.		
	Moving a group will fail when "Normal" groups in all servers to which the group can be moved are activated if you omit the –a option.		

#### **Example of Execution**


The following is an example of status transition when operating the groups.

Example: The cluster has two servers and two groups.


Failover policy of group


groupA server1 -> server2 groupB server2 -> serve

**1.** Both groups are stopped.



**2.** Run the following command on server1.






GroupA starts in server1.

**3.** Run the following command in server2.


# clpgrp -s



All groups that are currently stopped but can be started start in server2.

**4.** Run the following command in server1


# clpgrp -m groupA



GroupA moves to server2.

**5.** Run the following command in server1

# clpgrp -t groupA -h server2



GroupA stops.

**6.** Run the following command in server1.


# clpgrp -t

No operable group does not exist.

When the command is run, the error message, "No operable group does not exist.", is displayed since server1 does not have a group that can be stopped.

7. Add –f to the command you have run in Step 6 and execute it on server1.

# clpgrp -t -f



Groups which were started in server2 can be forcefully deactivated from server1.

#### Error message

Massage	Cause/Solution
Message	
Log in as administrator.	Log in as a user with Administrator privileges.
Invalid configuration data. Create valid cluster configuration data by using the Builder.	Create valid cluster configuration data using the Builder
Invalid option.	Specify a valid option
Could not connect to the server. Check if the cluster service is active.	Check if the ExpressCluster service is operating.
Invalid server status. Check if the cluster service is active.	Check if the ExpressCluster service is operating.
Server is not active. Check if the cluster service is active.	Check if the ExpressCluster service is operating.
Invalid server name. Specify a valid server name in the cluster.	Specify the valid server name in the cluster.
Connection was lost. Check if there is a server where the cluster service is stopped in the cluster.	Check if there is any server on which the ExpressCluster service has stopped in the cluster.
Invalid parameter.	The value specified as a command parameter may be invalid.
Internal communication timeout has occurred in the cluster server. If it occurs frequently, set a longer	A time-out occurred in the ExpressCluster internal communication.
timeout.	If time-out keeps occurring, set the internal communication time-out longer.
Specify a group name when -m option is used.	Specify a group name for the -m option
Invalid server. Specify a server that can run and stop the group, or a server that can be a target when you	Server that starts and stops the group or to which the group is moved is invalid.
move the group.	Specify a valid server.
Could not start the group. Try it again after the other server is started, or after the Wait Synchronization time is timed out.	Start up the group after waiting for the remote server to start up, or after waiting for the timeout of the start-up wait time.
No operable group exists in the server.	Check if there is any group that is operable in the server which requested the process.
The group has already been started on the local server.	Check the status of the group by using the WebManager or the clpstat command.
The group has already been started on the other server. To start the group on the local server, use -f option.	Check the status of the group by using the WebManager or the clpstat command.
	If you want to start up a group which was started in a remote server from the local server, move the group or run the command with the -f option.
The group has already been stopped.	Check the status of the group by using the WebManager or the

Message	Cause/Solution
	clpstat command.
Failed to start one or more resources. Check the status of group.	Check the status of group by using the Web Manager or the clpstat command.
Failed to stop one or more resources. Check the status of group.	Check the status of group by using the WebManager or the clpstat command.
The group is busy. Try again later.	The group is now being started or stopped. Wait for a while and try again.
An error occurred on one or more groups. Check the status of group.	Check the status of the group by using the WebManager or the clpstat command.
Invalid group name. Specify a valid group name in the cluster.	Specify the valid name of a group in the cluster.
Server is isolated.	The server has been suspended. The server is rebooted after it went down.
Some invalid status. Check the status of cluster.	The status is invalid. Check the status of the cluster.
Log in as administrator.	Check if the memory or OS resource is sufficient.

## **Collecting logs (clplogcc command)**

clplogcc: the clplogcc command collects logs.

#### **Command line**

```
clplogcc [ [-n targetnode1 -n targetnode2 .....] ]
       [-t collect_type] [-o path] [--local]
```

Description	This command collects information including logs and the OS information by accessing the data transfer server.
-------------	--

Option	None	Collects logs in the cluster.
	-t collect_type	Specifies a log collection pattern. When this option is omitted, a log collection pattern will be type1.  Information on log collection types is provided in the next section.
	-0 path	Specifies the output destination of collector files. When this option is skipped, logs are output under tmp of the installation path.
	-n targetnode	Specifies the name of a server that collects logs. With this specification, logs of the specified server, rather than of the entire cluster, will be collected.
	local	Collects logs on the local server without going through the data transfer server. The -n option cannot be specified at the same time.

Return Value	0	Success
	Other than 0	Failure

Remarks	Since log files are compressed by cab, decompress them using an
	appropriate application.

#### **Notes**

Run this command as a user with Administrator privileges.

All servers in the cluster should check that the data transfer server is active.

For the name of server for the -n option, specify the name of server that allows name resolution. If name resolution is not possible, specify the interconnect or public LAN address.

When you run this command, access the servers in the cluster in the order below, and use one of the paths that allowed successful access.

- 1. via the IP address on the interconnect LAN
- 2. via the IP address on the public LAN
- 3. via the IP address whose name was resolved by the server name in the cluster configuration data

## Example of command execution

**Example 1:** Collecting logs from all servers in the cluster

# clplogcc

Please wait, now collecting..

server status result

-----

server0 Completion Normal server1 Completion Normal

The execution results of the server that collected logs are displayed.

Server name Progress Result

Execution	For this command, the following processes are displayed.			
Result	Steps in Process	Meaning		
	Preparing	Initializing		
	Connecting	Connecting to the server		
	Compressing	Compressing log files		
	Transmitting	Sending log files		
	Disconnecting	Disconnecting from the server		
	Completion	Finished collecting logs		
	The following results (server status) are displayed:			
	Result (server status	s) Meaning		
	Normal	Completed successfully		
	Canceled	Canceled by the user		
	Invalid Parameters	Parameters are invalid		
	Compression Error	There was an error while compressing files		
	Timeout	Time-out occurred.		
	Busy	The server is busy.		
	No Free Space	No free space on the disk.		
	File I/O Error	There was a file I/O error.		
	Unknown Error	Failure caused by other errors		

## Error Message

Message	Cause/Solution
Log in as administrator.	Log in as a user with Administrator privileges.
Invalid option.	Specify a valid option.
Collect type must be specified 'type1' or 'type2' or 'type3'. Incorrect collection type is specified.	Invalid collection type is specified.
Specifiable number of servers are the max number of servers that can constitute a cluster.	The number of servers you can specify is within the maximum number of servers for cluster configuration.
Failed to obtain properties.	Failed to obtain the properties.
Failed to obtain the list of nodes. Specify a valid server name in the cluster.	Specify the valid name of a server in the cluster.
Invalid server name. Specify a valid server name in the cluster.	Specify the invalid server name in the cluster.
Failed to collect log.	Failed to collect logs.
Server is busy. Check if this command is already run.	This command may be run already. Check it.
Internal error. Check if memory or OS resources are sufficient.	Check if the memory or OS resource is sufficient.

#### Collecting logs by specifying a type (-t option)

To collect only the specified types of logs, run the clplogcc command with the –t option.

Specify a type from 1 thorough 3 for the log collection.

	type1	type2	type3
(1) Default collection information	у	у	n
(2) event log	у	у	у
(3) Dr.Watson Log	у	у	у
(4) user dump	у	n	n
(5) Diagnostics Report	у	n	n
(6) Registry	у	у	n
(7) Script	у	у	n

(y=yes, n=no)

Run this command from the command line as follows.

Example: When collecting logs using type2

# clplogcc -t type2

When no option is specified, a log type will be type 1.

- ◆ Information to be collected by default
  - Logs of each module in the ExpressCluster Server
  - Attribute information on each module (dir) in the ExpressCluster Server
    - In bin
    - In alert/bin, webmgr/bin
    - In %SystemRoot%\system32\drivers
  - ExpressCluster version information
  - OS information
  - update log
  - CPU license and node license
  - Configuration file
  - Policy file
  - Shared memory dump
  - Host name and domain name information (hostname execution result)
  - Network information (netstat execution result)
  - Memory usage status (mem execution result)
  - Process existing status (tasklist execution result)
  - ipconfig (ipconfig execution result)
- ♦ event log
  - application log (AppEvent.Evt)
  - system log (SysEvent.Evt)
- ◆ Dr.Watson Log
  - drwtsn32.log
- ♦ User dump
  - user.dmp
- Diagnostics Report
  - the result of running msinfo32.exe

#### ♦ Registry

- Registry information of the ExpressCluster Server
  - HKLM\SOFTWARE\NEC\EXPRESSCLUSTER\Alert
  - HKLM\SOFTWARE\NEC\EXPRESSCLUSTER\MirrorList
  - HKLM \SOFTWARE\NEC\EXPRESSCLUSTER\RC
  - HKLM\SOFTWARE\NEC\EXPRESSCLUSTER\VCOM
  - registry information of diskfltr
- Registry information of OS
  - HKLM\SYSTEM\CurrentControlSet\Services\Disk
  - HKLM\SYSTEM\CurrentControlSet\Control\Session Manager\DOS Devices
  - HKLM\SYSTEM\MountedDevices
  - HKLM\SYSTEM\CurrentControlSet\Enum\SCSI
  - HKLM\SYSTEM\CurrentControlSet\Enum\STORAGE
  - HKLM\SYSTEM\CurrentControlSet\Services\symc8xx
- ◆ Script

Start/stop script for a group that was created with the Builder.

If you specify a user-defined script, it is not included in the log collection information. It must be collected separately.

#### Output paths of log files (-o option)

- ◆ Log file is named and be saved as "server\_name-log.cab"
- Since log files are compressed by cab, decompress them by using an appropriate application.

#### If not specifying -o option

Logs are output in tmp of installation path.

#### When the -o option is specified:

If you run the command as follows, logs are located in the specified c:\tmp directory.

```
# clplogcc -o C:\tmp
```

## Specifying log collector server (-n option)

By using the -n option, you can collect logs only from the specified server.

Example: Collecting logs from Server1 and Server3 in the cluster.

```
# clplogcc -n Server1 -n Server3
```

- Specify a server in the same cluster.
- ◆ The number of servers you can specify is within the maximum number of servers in the cluster configuration.

## Collecting information at emergency OS shutdown

The OS resource information is collected when the cluster service that forms the cluster fails due to termination by an internal status error. Information to be collected is as follows:

- ◆ Information created by running a command
  - Host name and domain name information (hostname execution result)
  - Network information (netstat execution result)
  - Memory usage status (mem execution result)
  - Process existing status (tasklist execution result)
  - ipconfig (ipconfig execution result)

These are collected by default in the log collection. You do not need to collect them separately.

# Creating a cluster and backing up configuration data (clpcfctrl command)

### Creating a cluster (clpcfctrl --push)

**clpcfctrl** --**push**: the clpcfctrl --push command delivers cluster configuration data to servers.

#### **Command line**

```
clpcfctrl --push -[|w| [-x <path>] [-c <hostname>|<IP>] [-h <hostname>|<IP>] [-p <portnumber>] [--force]
```

Description	This command delivers the configuration data created by the Builder to
	servers.

Option	push	Specify this option when delivering the data.
		You cannot omit this option.
	-X	Specify this option to deliver the configuration data that is in the specified directory.
	-W	Displays that the graphic character code of the cluster configuration data file to be delivered is SJIS.
		In general, it is not necessary to specify this option
		You cannot specify -l and -w together. Specify either -l or -w.
	-c	Specifies a server to access for acquiring a list of servers. Specify a host name or IP address.
	-h	Specifies a server to which configuration data is delivered. Specify host name or IP address.
		If this option is omitted, configuration data is delivered to all servers.
	-p	Specifies a port number of data transfer port.
		When this option is omitted, the default value will be used.
		In general, it is not necessary to specify this option.
	force	Even if there is a server on which the data transfer service does not start up, the configuration data is delivered forcefully.

Return Value	0	Success
	Other than 0	Failure

#### **Notes**

Run this command as a user with Administrative authority.

When you run this command, access the servers in the order below, and use one of the paths that allowed successful access.

- 1. via the IP address on the interconnect LAN
- 2. via the IP address on the public LAN
- 3. via the IP address whose name was resolved by the server name in the cluster configuration data

When delivering the cluster configuration data, the current cluster configuration data and the configuration data to be delivered are compared.

If there is any change in the configuration data, the following message output. Follow the instructions of the message to complete the delivery.

Managera	Calution
Message	Solution
Please stop the ExpressCluster.	Stop the server.
Please suspend the ExpressCluster	Suspend the server.
Please stop the following groups.	Stop the group of which setting has been changed.
Reboot of a cluster is necessary to reflect setting.	Shut down and reboot the cluster to reflect the change of settings.
To apply the changes you made, restart the ExpressCluster Web Alert service.	Restart the Web Alert service to reflect the change of settings.
To apply the changes you made, restart the ExpressCluster Manager service.	Restart the ExpressCluster Manager service to reflect the change of settings.
Start of a cluster is necessary to reflect setting.	This is the message displayed at the initial cluster configuration. Start the cluster.

## Example of command execution

**Example 1:** Generating a cluster from the floppy disk with the data saved by the Builder on Windows

# clpcfctrl --push -x C:\tmp\config
file delivery to server 10.0.0.11 success.
file delivery to server 10.0.0.12 success.
Command succeeded.(code:0)

**Example 2:** Delivering configuration data that was saved on the file system using the Builder on Windows

# clpcfctrl --push -x C:\tmp\config -h 10.0.0.11
Command succeeded.(code:0)

#### Error Message

Error Message  Message	Cause/Solution
Log in as administrator.	Log in as a user with Administrator
Log III as administrator.	privileges.
This command is already run.	This command has already been run.
invalid option.	This option is invalid. Check the option.
Invalid mode. Check ifpush orpull option is specified.	Check if thepush is specified.
Invalid host name. Server specified by -h option is not included in the configuration	The server specified with -h is not included in configuration data. Check if the specified server name or IP address is correct.
Failed to initialize the xml library. Check if memory or OS resources are sufficient.	Check if the memory or OS resources are sufficient.
Failed to load the configuration file. Check if memory or OS resources are sufficient.	
Failed to change the configuration file. Check if memory or OS resources are sufficient.	
Failed to load the all.pol file. Reinstall the RPM cluster.	Reinstall the ExpressCluster Server.
Failed to load the cfctrl.pol file. Reinstall the RPM cluster.	Reinstall the ExpressCluster Server.
Failed to get the install path. Reinstall the RPM cluster.	Reinstall the ExpressCluster Server.
Failed to initialize the trncl library. Check if memory or OS resources are sufficient.	Check if the memory or OS resources are sufficient.
Failed to connect to trnsv. Check if the other server is active.	Accessing the server has failed. Check if the other server has been started up.
Failed to get the list of node. Check if the server specified by -c is a member of the cluster.	Check if the server specified by -c is a cluster member.
File delivery failed. Failed to deliver the configuration data. Check if the other server is active and run the	Delivering configuration data has failed. Check if other server(s) has been started.
command again.	Run the command again after the server has started up.
Multi file delivery failed. Failed to deliver the configuration data. Check if the other server is active	Delivering configuration data has failed. Check if other server(s) has been started.
and run the command again.	Run the command again after the server has started up.
Failed to deliver the configuration data. Check if the other server is active and run the command again.	Delivering configuration data has failed. Check if other server(s) has been started.
	Run the command again after the

Message	Cause/Solution
	server has started up.
Failed to upload the configuration file. Check if the other server is active and run the command again.	Delivering configuration data has failed. Check if other server(s) has been started
Canceled to deliver the configuration file since it failed to connect to one or more server. If you want to deliver the configuration file to servers that can be connected, run the command again with "force" option.	Canceled the delivery of the configuration data. There are some servers that failed to connect. If you want to deliver the configuration data only to the server that can be connected, run the command again by using the –force option.
The directory "work" is not found. Reinstall the RPM.	Reinstall the ExpressCluster Server.
Failed to make a working directory.	Check if the memory or OS resources
The directory does not exist.	are sufficient.
This is not a directory.	
The source file does not exist.	
The source file is a directory.	
The source directory does not exist.	
The source file is not a directory.	
Failed to change the character code set (EUC to SJIS).	
Failed to change the character code set (SJIS to EUC).	
Failed to allocate memory.	Check if the memory or OS resources
Failed to change the directory.	are sufficient.
Failed to make a directory.	
Failed to remove the directory.	
Failed to remove the file.	
Failed to open the file.	
Failed to read the file.	
Failed to copy the file.	
Failed to create the mutex.	
Internal error. Check if memory or OS resources are sufficient.	

## Backing up the cluster configuration data

clpcfctrl --pull: the clpcfctrl --pull command backups cluster configuration data.

#### **Command line**

Description	This command backs up cluster configuration data to be used for the Builder.

Option	pull	Specify this option when performing backup.
		You cannot omit this option.
	-X	Specify this option when backing up configuration data in the specified directory.
	-W	Save the configuration data with graphic character code, SJIS.
		You cannot specify both -l and -w together.
		You cannot omit both -l and -w.
	-1	Save the configuration data with graphic character code, EUC.
		You cannot specify both -l and -w together.
		You cannot omit both -l and -w.
	-h	Specifies the source server for backup.
		Specify a host name or IP address.
		When this option is omitted, the configuration data on the server running the command is used.
	-p	Specifies a port number of data transfer port.
		When this option is omitted, the default value is used.
		In general, it is not necessary to specify this option.

Return Value	0	Success
	Other than 0	Failure

Notes	Run this command as a user with Administrator privileges.		
	When you run this command, access the servers in the cluster in the order below, and use one of the paths that allowed successful access.		
	1. via the IP address on the interconnect LAN		
	2. via the IP address on the public LAN		
	3. via the IP address whose name was resolved by the server name in the cluster configuration data		

Example of command execution	Example 1: Backing up configuration data into the specified directory  # clpcfctrlpull -x C:/tmp/config Command succeeded.(code:0)	
	Example 2: Backing up configuration data of the specified server into the specified directory  # clpcfctrlpull -x C:/tmp/config -h 10.0.0.11 Command succeeded.(code:0)	

#### **Error Message**

Message	Cause/Solution
Log in as administrator.	Log on as a user with Administrator privileges.
This command is already run.	This command has already been run.
invalid option.	The option is invalid. Check the option.
Invalid mode. Check ifpush orpull option is specified.	Check if thepull is specified.
Failed to initialize the xml library. Check if memory or OS resources are sufficient.	Check if the memory or OS resources are sufficient.
Failed to load the configuration file. Check if memory or OS resources are sufficient.	
Failed to change the configuration file. Check if memory or OS resources are sufficient.	
Failed to load the all.pol file. Reinstall the cluster.	Reinstall the ExpressCluster Server.
Failed to load the cfctrl.pol file. Reinstall the cluster.	Reinstall the ExpressCluster Server.
Failed to get the install path. Reinstall the cluster.	Reinstall the ExpressCluster Server.
Failed to initialize the trncl library. Check if memory or OS resources are sufficient	Check if the memory or OS resources are sufficient.
Failed to connect to trnsv. Check if the other server is active.	Accessing the server has failed. Check if other server(s) has been started.
The directory "work" is not found. Reinstall the cluster.	Reinstall the ExpressCluster Server.
Failed to make a working directory.	Check if the memory or OS
The directory does not exist.	resources are sufficient.
This is not a directory.	
The source file does not exist.	
The source file is a directory.	
The source directory does not exist.	
The source file is not a directory.	
Failed to change the character code	

Message	Cause/Solution
set (EUC to SJIS).	
Failed to change the character code set (SJIS to EUC).	
Failed to allocate memory.	Check if the memory or OS
Failed to change the directory.	resources are sufficient.
Failed to make a directory.	
Failed to remove the directory.	
Failed to remove the file.	
Failed to open the file.	
Failed to read he file.	
Failed to write the file.	
Failed to copy the file.	
Failed to create the mutex.	Check if the memory or OS
Internal error. Check if memory or OS resources are sufficient.	resources are sufficient.

## Adjusting time-out temporarily

clptoratio: the clptoratio command extends or displays the current time-out ratio.

#### **Command line**

```
clptoratio -r <ratio> -t <time>
clptoratio -i
clptoratio -s
```

Description	This command displays or temporarily extends the various time-out values of the following on all servers in the cluster.	
	+ Monitor resource	
	+ Heartbeat resource	
	+ Disk Agent	
	+ Alert synchronous service	
	+ WebManager service	
	The current time-out ratio is displayed.	

Option	-r	Specifies the time-out ratio.
	ratio	Use 1 or larger integer.
		The maxim time-out ratio is 10,000.
		If you specify "1," you can return the modified time-out ratio to the original as you can do so when you are using the -i option.
	-t time	Specifies the extension period. You can specify minutes for m, hours for h, and days for d. The maximum period of time is 30 days. Example: 2m, 3h, 4d
	-i	Sets back the modified time-out ratio.
	-S	Refers to the current time-out ratio.

Return Value	0	Success
	Other than 0	Failure

Remarks	When the cluster is shutdown, the time-out ratio you have set will become ineffective. However, if any server in the cluster is not shutdown, the time-out ratio and the extension period that you have set will be maintained.		
	With the -s option, you can only refer to the current time-out ratio. You cannot see other information such as remaining time of extended period.  You can see the original time-out value by using the status display command.		
	Heartbeat time-out # clpstatcldetail		
	Monitor resource time-out # clpstatmon monitor_resource_namedetail		

#### Notes

Run this command as a user with Administrator privileges.

Make sure that the ExpressCluster service is activated in all servers in the cluster.

When you set the time-out ratio, make sure to specify the extension period. However, if you set "1" for the time-out ratio, you cannot specify the extension period.

You cannot specify a combination such as "2m3h," for the extension period.

## Example of a command entry

**Example 1:** Doubling the time-out ratio for three days

# clptoratio -r 2 -t 3d

Example 2: Setting back the time-out ratio to original

# clptoratio -i

**Example 3:** Referring to the current time-out ratio

# clptoratio -s

present toratio: 2

The current time-out ratio is set to 2.

#### **Error Message**

Message	Cause/Solution
Log in as administrator.	Log on as a user with Administrator privileges.
Invalid configuration file. Create valid cluster configuration data by using the Builder.	Create valid cluster configuration data by using the Builder.
invalid option.	Specify a valid option.
Specify a number in a valid range.	Specify a number within a valid range.
Specify a correct number.	Specify a valid number.
Scale factor must be specified by integer value of 1 or more.	Specify 1 or larger integer for ratio.
Specify scale factor in a range less than the maximum scale factor.	Specify a ratio that is not larger than the maximum ratio.
Set the correct extension period.	Set a valid extension period.
ex) 2m, 3h, 4d	
Set the extension period in a range less than the maximum extension period.	Set the extension period which does not exceed the maximum extension period.
Could not connect to the server. Check if the cluster service is active.	Check that the ExpressCluster service is operating.
Server is not active. Check if the cluster service is active.	Check that the ExpressCluster service is operating.
Connection was lost. Check if there is a server where the cluster service is stopped in the cluster.	Check if there is any server in the cluster that the ExpressCluster service stopped.
Invalid parameter.	The value specified as the command parameter may be invalid.
Internal communication timeout has occurred in the cluster server. If it occurs frequently, set a longer	A time-out occurred in the ExpressCluster internal communication.
timeout.	If time-out keeps occurring, set the internal communication time-out longer.
Processing failed on some servers. Check the status of failed servers.	There is a server in which the processing has failed.
	Check the statuses of servers in the cluster. Run the command with all servers in the cluster activated.
Internal error. Check if memory or OS resources are sufficient.	Check if the memory or OS resources are sufficient.

## Modifying the log level and size

clplogcf: the clplogcf command modifies and displays log level and log output file size.

#### **Command line**

clplogcf -t <type> -l <level> -s <size>

Description	This command modifies the log level and log output file size, or displays the values currently configured.	
Option	-t	Specifies a module type whose settings will be changed.
		If both -l and -s are omitted, the information set to the specified module will be displayed. See the list of "Types that can be specified to the -t option" for types which can be specified.
	-1	Specifies a log level.
		You can specify one of the following for a log level.
		1, 2, 4, 8, 16, 32
		You can see more detailed information as the log level increases.
		See the list of "Default log levels and log file sizes" for default values of each module type.
	-S	Specifies the size of a file for log output.
		The unit is byte.
	None	Displays the entire configuration information currently set.
Return Value	0	Success
	Other than 0	Failure
Remarks	Each type of output logs from ExpressCluster uses two log files. Therefore, it is necessary to have the disk space that is twice larger than what is specified by -s.	
Notes	Run this comm	and as a user with Administrator privileges.
	To run this command, the ExpressCluster Event service must be started.	

Example of	Example 1: Modifying the pm log level	
command execution	# clplogcf -t pm -1 8	
CACCULON	Example 2:Seeing the pm log level and log file size	
	# clplogcf -t pm	
	TYPE, LEVEL, SIZE	
	pm, 8, 1000000	
	Example 3: Displaying the values currently configured	
	# clplogcf	
	TYPE, LEVEL, SIZE	
	trnsv, 4, 1000000	
	xml, 4, 1000000	
	logcf, 4, 1000000	

#### Error Message

8	
Message	Cause/Solution
Log in as administrator.	Log on as a user with Administrator privileges.
invalid option.	The option is invalid. Check the option.
change configuration failed. (Perhaps clpevent is not running.)	clpevent may not have been started.
invalid level	The specified level is invalid.
invalid size	The specified size is invalid.
load config file failed.	Non-clustered server.
initialize xml library failed.	Check if the memory or OS resources are sufficient.
print current configuration failed.	clpevent may not be started yet.

Types that can be specified for the -t option (y=yes, n=no)

	Medule	
Туре	Module	Description
alert	clpaltinsert.exe	Alert
apicl	clpapicl.dll	API client library
apisv	clpapisv.dll	API server
appli	clpappli.dll	Application resource
appliw	clpappliw.dll	Application monitor resource
armdrive	armdrive.exe	Drive letter setting command
bmccnf	clpbmccnf.exe	BMC information update command
cfctrl	clpcfctrl.exe	Cluster generation, cluster information and backup command
cl	clpcl.exe	Cluster startup and stop command
clpdnld	clpdnld.exe	Downloader
clpgetsvcstat	clptrnsv.exe	Transaction server
clpshmstat	clpshmstat.dll	Node status management library
clsv	clpclsv.dll	Client server
commcl	clpcommcl.dll	Common communication client library
comnp	clpcomnp.dll	COM network partition resolution resource
cpufreq	clpcpufreq.exe	CPU frequency control command
diskagcl	clpdiskagcl.dll	Disk agent communication client
diskagent	clpdiskagent.exe	Disk agent
diskfltr	clpdiskfltr.dll	Disk filtering library
disknp	clpdisknp.dll	DISK network partition resolution resource
diskutil	clpdiskutil.dll	Mirror disk/disk shared library
diskw	clpdiskw.dll	Disk RW monitor resource
down	clpdown.exe	Server shutdown command
event	clpevent.dll	Event log
exping	clpexpng.dll	PING execution management
fip	clpfip.dll	Floating IP resource
fipw	clpfipw.dll	Floating IP monitor resource
genw	genw.dll	Custom monitor resource
grp	clpgrp.exe	Group startup, stop and move command
hblog	clplanhb.dll	Kernel-mode LAN heartbeat resource
hd	clphd.dll	Hybrid disk resource
hdadmn	clphdadmn.dll	Hybrid disk management library
hdapi	clphdapi.dll	Hybrid disk internal API
hddac	clphddac.dll	Hybrid disk control library
hdfunc	clphdfunc.dll	Hybrid disk function library
hdnm	clphdnm.dll	Hybrid disk node management
hdsnapshot	clphdsnapshot.exe	Hybrid disk snapshot backup command
	h 11 mp	, and a separate of the separa

Туре	Module	Description	
hdtw	clphdtw.dll	Hybrid disk TUR monitor resource	
hdw	clphdw.dll	Hybrid disk monitor resource	
ipw	clpipw.dll	IP monitor resource	
lankhb	clplanhb.dll	Kernel-mode LAN heartbeat resource	
Icns	clplcns.dll	License library	
ledctrl	clpledctrl.exe	Chassis identify control command	
logc	clplogcc.exe	Log collection library	
logcc	clplogcc.exe	Collect logs command	
logcf	clplogcf.exe	Log level and size modification command	
logcmd	clplogcmd.exe	Alert producing command	
majonp	clpmajnp.dll	Majority network partition resolution resource	
md	clpmd.dll	Mirror disk resource	
mdadmn	clpmdadmn.dll	Mirror disk management library	
mdclose	mdclose.exe	Mirror disk resource close command	
monctrl	clpmonctrl.exe	Monitor resource control command	
mdfunc	clpmdfunc.dll	Mirror disk function library	
mdnw	clpmdnw.dll	Mirror connect monitor resource	
mdopen	mdopen.exe	Mirror disk resource open command	
mdw	clpmdw.dll	Mirror disk monitor resource	
miiw	clpmiiw.dll	NIC Link Up/Down monitor resource	
monctrl	clpmonctrl.exe	Monitor resource control command	
mtw	clpmtw.dll	Multi target monitor resource	
nm	clpnm.exe	Node map management	
oldapi	clpoldapi.exe	Compatible API	
oldapi_cnf	clpoldapi.exe	Compatible API	
oldapi_evt	clpoldapi.exe	Compatible API	
oldapi_if	clpoldapi.exe	Compatible API	
oldapi_sts	clpoldapi.exe	Compatible API	
pingnp	clppingnp.dll	Compatible API	
oldapi_cnf	clpoldapi.exe	Compatible API	
pingnp	clppingnp.dll	PING network partition resolution resource	
pm	clppm	Process management	
pmsvc	clppmsvc.exe	Process management	
ptun	clpptun.dll	Parameter tuning	
ptunlib	clpptun.dll	Parameter tuning	
rc	clprc.exe	Group and group resource management	
rc_ex	clprc.exe	Group and group resource management	
<sub>I</sub> –			

Туре	Module	Description
regsyncw	clpregsync.dll	Registry synchronization monitor resource
resdllc	clpresdllc.dll	Resource control library
rm	clprm.dll	Monitor management
script	clpscript.dll	Script resource
scrpc	clpscrpc.exe	Script
scrpl	clpscrpl.ece	Script
sd	clpsd.dll	Disk resource
sdadmn	clpsdadmn.dll	Disk management library
sddknp	clpsddknp.dll	DISK network partition resolution resource
sdfunc	clpsdfunc.dll	Disk function library
sdw	clpsdw.dll	Disk TUR monitor resource
sem	clpsem.dll	Semaphore library
service	clpservice.dll	Service resource
servicew	clpservicew.dll	Service monitor resource
shmcm	clpshmcm.dll	Shared memory library
shmevt	clpshmevt.dll	Event library
shmnm	clpshmnm.dll	Shared memory library
shmrm	clpshmrm.dll	Shared memory library
spool	clpspool.dll	Print spool resource
spoolw	clpspoolw.dll	Print spool monitor resource
starup	clpstartup.exe	Startup
stat	clpstat.exe	Status display command
stdn	clpstdn.exe	Cluster shutdown command
toratio	clptoratio.exe	Time-out ratio modification command
trncl	clptrncl.dll	Transaction library
trnreq	clptrnreq.exe	Inter-cluster processing request command
trnsv	clptrnsv.exe	Transaction server
vcom	clpvcom.dll	Virtual computer name resource
vcomw	clpvcomw.dll	Virtual computer name monitor resource
vip	clpvip.dll	Virtual IP resource
vipw	clpvipw.dll	Virtual IP monitor resource
webalert	clpaltd.exe	Alert synchronization
webmgr	clpwebmc.exe	WebManager
xml	xlpxml.dll	XML library

#### Default log levels and log file sizes

Type	Level		Size (byte)
alert	4	1000000	0.20 (3)10)
apicl	4	5000000	
apisv	4	5000000	
appli	4	1000000	
appliw	4	1000000	
armdrive	4	1000000	
bmccnf	4	1000000	
cfctrl	4	1000000	
cifs	4	1000000	
cl	4	1000000	
clpdnld	4	1000000	
clpgetsvcstat	4	1000000	
clpshmstat	4	1000000	
clsv	4	1000000	
commcl	4	1000000	
comnp	4	1000000	
cpufreq	4	1000000	
diskagcl	4	1000000	
diskagent	4	1000000	
diskfltr	4	1000000	
disknp	4	1000000	
diskutil	4	1000000	
diskw	4	1000000	
down	4	1000000	
event	4	1000000	
exping	4	1000000	
fip	4	1000000	
fipw	4	1000000	
genw	4	1000000	
grp	4	1000000	
hblog	4	1000000	
hd	4	1000000	
hdadmn	8	1000000	
hdapi	8	1000000	
hddac	4	4000000	
hdfunc	8	8000000	
hdnm	8	4000000	
hdsnapshot	8	2000000	

Туре	Level	Size (byte)
hdtw	4	1000000
hdw	4	2000000
ipw	4	1000000
lankhb	4	1000000
Icns	4	1000000
ledctrl	4	1000000
logc	4	1000000
logcc	4	1000000
logcf	4	1000000
logcmd	4	1000000
majonp	4	1000000
md	4	1000000
mdadmn	4	1000000
mdclose	4	1000000
mdctrl	4	1000000
mdfunc	4	2000000
mdnw	4	1000000
mdopen	4	1000000
mdw	4	1000000
miiw	4	1000000
monctrl	4	1000000
mtw	4	1000000
nas	4	1000000
nasw	4	1000000
nm	4	2000000
oldapi	4	1000000
oldapi_cnf	4	1000000
oldapi_evt	4	1000000
oldapi_if	4	1000000
oldapi_sts	4	1000000
pingnp	4	1000000
pm	4	1000000
pmsvc	4	2000000
ptun	4	1000000
ptunlib	4	1000000
rc	4	2000000
rc_ex	4	2000000
regsync	4	1000000
regsyncw	4	1000000

Туре	Level	Size (byte)
resdllc	4	2000000
rm	4	2000000
script	4	1000000
scrpc	4	1000000
scrpl	4	1000000
sd	4	1000000
sdadmn	4	1000000
sddknp	4	1000000
sdfunc	4	1000000
sdw	4	1000000
sem	4	1000000
service	4	1000000
servicew	4	1000000
shmcm	4	1000000
shmevt	4	1000000
shmnm	4	1000000
shmrm	4	1000000
spool	4	1000000
spoolw	4	1000000
stat	4	1000000
stdn	4	1000000
toratio	4	1000000
trncl	4	2000000
trnsv	4	2000000
trnreq	4	1000000
vcom	4	1000000
vcomw	4	1000000
vip	4	1000000
vipw	4	1000000
webalert	4	1000000
webmgr	4	1000000
xml	4	1000000
	Total	141000000 * 2

#### Monitoring Agent Types that can be specified for the -t option

Туре	Module	Description
db2w	clp_db2w.dll	DB2 Monitor (Database Agent)
ftpw	clp_ftpw.dll	FTP Monitor (Internet Server Agent)
httpw	clp_httpw.dll	HTTP Monitor (Internet Server Agent)
imap4w	clp_imap4w.dll	IMAP4 Monitor (Internet Server Agent)
odbcw	clp_odbcw.dll	ODBC Monitor (Database Agent)
oracleasw	clp_oracleasw.dll	OracleAS Monitor (Application Server Agent)
oraclew	clp_oraclew.dll	Oracle Monitor (Database Agent)
oscw	clposcw.dll	OfficeScan CL Monitor (Anti-Virus Agent)
ossw	clp_ossw.dll	OfficeScan SV Monitor (Anti-Virus Agent)
otxw	clp_otxw.dll	WebOTX Monitor (Application Server Agent)
pop3w	clp_pop3w.dll	POP3 Monitor (Internet Server Agent)
psqlw	clp_psqlw.dll	PostgreSQL Monitor (Database Agent)
smtpw	clp_smtpw.dll	SMTP Monitor (Internet Server Agent)
sqlserverw	clp_sqlserverw.dll	SQL Server Monitor (Database Agent)
tuxw	clp_tuxw.dll	Tuxedo Monitor (Aplication Server Agent)
wasw	clp_wasw.dll	Websphere Monitor (Aplication Server Agent)
wlsw	clp_wlsw.dll	Weblogic Monitor (Aplication Server Agent)

#### Monitoring Agent Default Values of Log Level/Log File Size

Туре	Level	Size (byte)
db2w	4	1000000
ftpw	4	1000000
httpw	4	1000000
imap4w	4	1000000
odbcw	4	1000000
oracleasw	4	1000000
oraclew	4	1000000
oscw	4	1000000
ossw	4	1000000
otxw	4	1000000
pop3w	4	1000000
psqlw	4	1000000
smtpw	4	1000000
sqlserverw	4	1000000
tuxw	4	1000000
wasw	4	1000000
wlsw	4	1000000
_	Total	17000000 * 2

# Mirror-related commands Mirror status display commands

**clpmdstat:** the clpmdstat command displays status related to mirroring and configuration information.

#### **Command line:**

```
clpmdstat --mirror mirrordisk-alias
clpmdstat --active mirrordisk-alias
clpmdstat --detail mirrordisk-alias
clpmdstat --list
```

Description	This command displays the status related to mirroring.	
	This command displays mirror disk resources configuration information.	

Option	mirror	Displays mirror disk resource status.
	active	Displays status of mirror disk activation.
	detail	Displays mirror disk resources configuration information.
	list	Displays a list of mirror disk resources.
Parameter	mirrordisk-alias	Specifies a mirror disk resource name.

Return value	0	Success
	Other than 0	Failure

<b>Notes</b> Run this command as	a user with Administrator privileges.
----------------------------------	---------------------------------------

Example display after	An example of the display after running this command is provided in the next section.
running this command	

#### **Error Messages**


Message	Cause/Solution
clpmdstat failed. An internal error occurred.	Check if the memory or OS resources are sufficient.
clpmdstat failed. A network error occurred.	Check the connection status of the interconnect.
clpmdstat failed. The resource name is invalid.	Specify the valid mirror disk resource name.
clpmdstat failed in the internal processes(%2). The error code is %3.	Reboot the local server.

# Example display after running the mirror status display command

◆ Displaying the status of mirror disk resource

The status of specified mirror disk resource is displayed by specifying the --mirror option. There are three types of display depending on the status of mirror disk resource:

• When the status of mirror disk resource is Normal:



#### Explanation of each item

Item	Description		
Mirror Status	Status of mirror disk resource		
	Status	Description	
	Normal	Normal	
	Recovering	Mirror is recovering	
	Abnormal	Abnormal	
	No Construction	Initial mirror construction is not done	
Mirror Color	Status of mirror disk on each server		
	Status	Description	
	GREEN	Normal	
	YELLOW	Mirror is recovering	
	RED	Abnormal	
	GRAY	Being stopped, Unknown status	
	BLUE	Both disks are active	

When the status of mirror disk resource is abnormal

## Explanation of each item

Item	Description	
Mirror Status	Status of mirror disk resource *1	
Mirror Color	Status of mirror disk on each server *1	
Lastupdate Time	Last time when the data was updated on the server.	
Break Time Time when mirror break has occurred		
Disk Error	Status of disk I/O	

Item	Description		
	Status	Description	
	ОК	Normal	
	ERROR	Error (No I/O)	
		Unknown	
Difference Percent	Percentage of differences in the data on each server.		

<sup>\*1</sup> Refer to. "When the status of mirror disk resource is Normal:"

#### During mirror recovery

Mirror Status: Recovering

md1	server1	server2
Mirror Color	YELLOW	YELLOW

Recovery Status Value

Recovering

Direction: server1 -> server2

15%

Lercent:
Used Time:
Remain T' 00:00:21 00:01:59

### Explanation of each item

Item	Description	
Mirror Status	Status of mirror disk resource *1	
Mirror Color	Status of mirror disk on each server *1	
Status	Status of mirror	recovery
	Status	Description
	Preparing	Preparing for copy
		(This status may last for a while if I/O load is high when resource is getting started during recovery)
	Recovering	Being recovered
	Completing	Recovering is being completed
	Nothing	Canceling recovery
Direction	Direction of mirror recovery	
	Display either [source server] -> [destination server] , or	
	[destination server] <- [source server]	
Percent	Percentage of how much data is already recovered	
Used Time	Elapsed time since recovering has started	
Remain Time	Estimated time to complete recovering the remaining data. It is estimated by the speed of already recovered data. The time may be different depending on server load.	

<sup>•\*1</sup> Refer to ."When the status of mirror disk resource is Normal:".

#### ◆ Displaying active status of mirror disk resource

Active status of the specified mirror disk resource is displayed when the --active option is specified:

#### Status of mirror partition device

Active Status	Description	
Active	Active	
Inactive	Not active	
	Unknown	

### Displaying mirror disk resource information

Configuration information of the specified mirror disk resource is displayed when the --detail option is specified:

### Explanation of each item

Item	Description
Mirror Name	Mirror disk resource name
Server Name	Server name
Mount Point	Mount point
Drive Letter	Data partition drive letter
NMP/Disk Size(MB)	NMP: the smaller size of data partition of servers
	Disk Size: actual data partition size

◆ Displaying the list of mirror disk resources

The list of mirror disk resources is displayed when the --list option is specified.

Mirror Name	Server Name	Drive Letter
md1	server1	F:
	server2	F:
md2	server1	G:
	server2	G:

## Explanation of each item:

Item	Description
Mirror Name	Mirror disk resource name
Server Name	Server name
Drive Letter	Data partition drive letter

# Mirror disk resource operation command

clpmdctrl: the clpmdctrl command operates mirror disk resources.

#### **Command line:**

```
clpmdctrl --active mirrordisk-alias
clpmdctrl --deactive mirrordisk-alias
clpmdctrl --force recovery-source-servername mirrordisk-alias
clpmdctrl --recovery mirrordisk-alias
clpmdctrl --cancel mirrordisk-alias
clpmdctrl --rwait mirrordisk-alias [-timeout time] [-rcancel]
```

#### Note:

Do not use the --active, and --deactive options when the ExpressCluster service is started. If you use them, there will be an error.

Description	This command activates/deactivates mirror disk resource and recovers
	mirror.

	T	
Option	active	Activates the mirror disk resource on the local server.
		If the status of mirror disk resource is normal, mirroring is performed.
		If the status of mirror disk resource is not normal, mirroring will not be performed.
	deactive	Deactivates the activated mirror disk resource on the local server.
	break	Stops mirroring of the mirror disk and makes the data status not to be the latest on the server where the command is executed. The status of the mirror disk resource on the server that the command is executed becomes abnormal. The status of the mirror disk resource remains the same as long as the command is not executed on the server.
		Mirroring restarts when mirror recovery is ececuted. The mirror data is not synchronized until mirror recovery is executed if mirror writing occurs.
	force	Forcefully performs mirror recovery for the specified mirror disk resource.
	recovery	Performs either full mirror recovery or differential mirror recovery for the specified mirror disk resource.
		Whether to perform full or differential mirror recovery is determined automatically.
	cancel	Cancels mirror recovery.
	rwait	Waits the completion of the mirror recovery of the specified mirror disk resource.
	-timeout time	Specifies the timeout period of mirror recovery completion (second). This option can be omitted. When this option is omitted, timeout is not executed and waits for the completion of mirror recovery.

	-rcancel	Intermits mirror recovery when the timeout of waiting of mirror recovery completion occurred. This option can be set when "-timeout option" is set. When this optin is omitted, the mirror recovery continues even after the timeout occurrence.
Parameter	recovery-source- servername	Specify a server name of the copy source.
	mirrordiisk-alia	Specify a mirror disk resource name.

Return Value	0	Success
	1	Invalid parameter
	3	Other error
	4	Target mirror disk is not configuring mirror, or the mirror configuring failed on the process.  (Only when "rwait option" is specified, including the case when mirror recovery is interrupted by -rcancel.)
	5	Timeout of mirror recovery of target mirror disk occurs (Only whenrwait -timeout option is specified)

Notes	Run this command as a user with Administrator privileges.
	When performing forced mirror recovery only for the local server while the remote server is not running, specify the server that is forcefully mirror recovered as a copy source.
	When performing mirror recovery again after mirror recovery failed, specify the same server you used last time for mirror recovery as a copy source.
	To resume the forced mirror recovery that was suspended by selecting <b>Cancel</b> , use this command for forced mirror recovery.

Example of	<b>Example 1:</b> When activating the mirror disk resource md1:	
command execution	# clpmdctrlactive md1	
CACCULION	<md1@server1>: active successfully</md1@server1>	
	<b>Example 2:</b> When deactivating the mirror disk resource md1:	
	# clpmdctrldeactive md1	
	<md1@server1>: deactive successfully</md1@server1>	
	<b>Example 3:</b> When mirror recovering the mirror disk resource md1:	
	# clpmdctrlrecovery md1	

## **Error Messages**

Message	Cause/Solution
clpmdctrl failed. An internal error occurred.	Check if the memory or OS resources are sufficient.
clpmdctrl failed. The resource is busy.	Try again later.
clpmdctrl failed. A network error occurred.	Check the connection status of the interconnect.
clpmdctrl failed. Cannot establish the mirror disk connection.	Check if the cluster configuration data is valid.
clpmdctrl failed. The resource name is invalid.	Specify the valid mirror disk resource name.
clpmdctrl failed. The status is invalid.	Check the mirror disk status.
clpmdctrl failed. The resource is not initialized.	Check if the partition is allocated and the disk can be identified by OS. Check also that the cluster configuration data is valid.
clpmdctrl failed. The resource has not performed initial mirror construction.	Initial mirror configuration is necessary.
clpmdctrl failed. Cannot lock the mirror disk.	Check if the memory or OS resources are sufficient.
clpmdctrl failed. The license is not registered.	Register the license.
clpmdctrl failed. The trial version has expired.	Register the license.

Message	Cause/Solution	
clpmdctrl failed. The license authentification failed.	Register the license.	
clpmdctrl failed. Cannot find the history folder.	Check if the cluster configuration data is valid.	
clpmdctrl failed. The partition size between servers does not match.	Check the partition size of the mirror disk.	
clpmdctrl failed. The mirror connect is not initialized.	Check the connection status of the mirror connect. Check also that the cluster configuration data is valid.	
clpmdctrl failed. Cannot find the partition specified for the cluster partition.	Check if the partition is allocated and the disk can be identified by OS.	
clpmdctrl failed. Cannot find the partition specified for the data partition.	Check if the partition is allocated and the disk can be identified by OS.	
clpmdctrl failed. Cannot change the drive letter for the cluster partition.	Check the drive letter specified to the cluster configuration data. Check if the drive letter has already been used by other partition.	
clpmdctrl failed. Cannot change the drive letter for the data partition.	Check the drive letter specified to the cluster configuration data. Check if the drive letter has already been used by other partition.	
clpmdctrl failed. The server name is invalid.	Specify the valid server name.	
clpmdctrl failed. %2 is running.	Execute while ExpressCluster Server is being stopped.	
clpmdctrl failed. The mirror disk [MD resource name] can not be controlled on this server.	Check the mirror disk status.	
clpmdctrl failed. The mirror disk [MD resource name] is not copying.	Check the mirror disk status.	
clpmdctrl failed in the internal processes(%2). The error code is %3.	Reboot the local server.	
[MD resource name] status is invalid.	Target mirror disk is not configuring mirror, or the mirror configuring failed on the process.	
[MD resource name] mirror recovery timed out.	Check if the specified timeout period is appropriate, or if the disk I/O or communication delay is not occurring due to heavy loads.	

# Partition size tuning command

clpvolsz: the clpvolsz command enlarges and shrinks the disk partition size.

#### Command line:

clpvolsz drive-letter [size]

**Description** This command checks the sizes of data partitions mirrored by mirror disk

resource. If the partitions are not of the same size, the command adjusts

the sizes.

**Parameter** drive-letter Specify the drive letter of the target partition

drive.

size Specify the partition size by byte. If nothing

is specified, the current size is displayed.

**Return value** 0 succeeded in displaying the size

1 succeeded in changing the size

2 or greater abnormal

**Notes** Run this command as a user with Administrator privileges.

You cannot extend the partition size by this command.

Shrinking the partition size by using this command may cause the change of the drive latter. After shrinking the partition size, make sure to use **Disk Management**. (Navigate from **Control Panel** to

Administrative Tools, Computer Management, Disk Management) to rescan the disk and check the drive letter and

configure as necessary.

When the target partition has been registered as data partition/cluster partition in the cluster configuration information of the mirror disk resource, delete the mirror disk resource before shrinking the partition size and register again after shrinking and reconfiguration of drive

letter.

The partition size is coordinated by MBR. Typically, it is a multiple of

512 bytes.

**Examples** Example 1 : When checking the Z drive size

# clpvolsz z:

Drive <z:> 8,587,160,064

Example 2: When shrinking the Z drive size to **8,587,159,552Byte** 

# clpvolsz z: 8587159552

Drive <z:> 8,587,160,064 -> 8,587,159,552

Execute it? [Y/N] ->y

#### **SUCCESS**

#### Error messages

Message	Causes/Solution
ERROR:invalid parameter.	The parameter is incorrect. Check the number of arguments and formats are set correctly.
ERROR:larger than partition size.	The value larger than the current partition size is set. Specify a smaller value.
ERROR:drive not found.	The specified drive is not found. Check if you have specified the right drive.
ERROR:drive open failed.	The specified drive cannot be opened. Check if the drive can be accessed.
ERROR:partition not found.	The partition number on the specified drive cannot be found. Check if you have checked the right driver.
ERROR:partition size zero.	The partition size of the specified server is 0. Check if the target partition is basic volume in the MBR format.
ERROR:device layout info.	Acquiring disk partition configuration information has failed. Check if the target partition is in the MBR format.
ERROR:device geometry info.	Acquiring the disk geometry information has failed. Check if the disk device is working properly.
ERROR:device no info.	Acquiring Device No. / Partition No has failed. Check the target partition is basic volume in the MBR format.
ERROR:set device info.	Configuration of partition information has failed on the disk. Check if writing to disks is not prohibited.
ERROR:memory alloc error.	Reserving the resource has failed. Check if the memory or OS resource is enough.

# Snapshot backup command of hybrid disk resource

 $clphdsnapshot: {\it the\ } {\it clphdsnapshot} is\ used\ for\ operating\ hybrid\ disk\ resource\ snapshot.$ 

#### **Command line:**

clphdsnapshot -- open hybriddisk-alias clphdsnapshot --close hybriddisk-alias

#### **Description**

This command interrupts the mirroring of hybrid disk resource and cancels the data partition access restriction to allow collection of snapshot backup, and then resumes ordinary status by resuming mirroring.

Option	open	Interrupts mirroring and allows collecting the snapshot backups on the server on which the command is executed by cancelling the data partition access restriction, and then resumes mirroring. When the auto mirror recovery is set to be enabled, this setting is made to disable temporarily.
	close	Restricts access to the data partition. If the auto mirror recovery is set to be enabled, the disablement is canceled and then, mirroring is resumed.
Parameter	hybriddisk-alias	Specifies the hybrid disk resource name.
Return Value	e 0	The command is successfully executed.
	1	Invalid parameter.
	2	The target resource is not mirrored. (Only when using theopen option)
	3	The target resource is already in the snapshot status on other server, or forcibly activated (Only when usingopen option.)
	4	The target resource is already in the snapshot status (only when using theopen option)
	5	The target resource is not in the snapshot status. (Only when using theclose option.)
	6	The target resource is now on mirror recovery.
	7	The target resource does not exist in local server.
	8	The command is executed on the active server group.
	9	Other errors


#### **Notes**

This command must be executed by the user with administrator privilege.

This command should be executed on one of the standby server group which works as a copy destination of mirroring for the active hybrid disk resource that is properly mirrored. This command cannot be executed on a server in active server group (i.e., server in the same group as the server whose resources are activated.)

# Example of command execution

The following shows how backup of the Z drive which is mirrored at the hybrid disk resource hd\_Z is collected.



- 1. Execute the command below on the server 3 in the standby server group.
  - # clphdsnapshot --open hd\_Z
    Command succeeded.
- 2. Collect backup of the Z drive at the server 3 by using the backup tool.
- 3. Execute the command below on the server 3.
  - # clphdsnapshot --close hd\_Z
    Command succeeded.
- 4. When the auto mirror recovery is set to be disabled, run the mirror recovery manually.

#### **Error Messages**

Message	Cause/Solution
Invalid parameter.	The parameter is invalid. Check if there is any error in its format or parameter.
%1 is not mirroring, or not active.	Snapshot backup cannot be performed on a hybrid disk resource which is deactivated or is not mirrored. Try again after activating the resource on another server group and while the mirroring is performed.
%1 is busy on %2	Check that the target resource is already in the snapshot status on another server in the same server group, or is not forcefully activated.
%1 has already opened.	The command is executed by specifying theopen option for the resource that is already been in the snapshot status. Check the execution procedures.

ExpressCluster X 2.1 for Windows Reference Guide

%1 has already opened.	The command is executed with theclose option for the resource that is not in snapshot status by the – open option.  Make sure that the command with theopen option has been executed successfully.
%1 is copying.	A snapshot backup cannot be performed for the hybrid disk resource in the process of mirror recovery. Try again after the mirror recovery has been completed.
%1 is not available to %2.	Snapshot backups cannot be collected on a server on which the target resource cannot be activated. Execute it on a server on which the failover group containing this resource can be started.
Don't execute at active server group.	Snap shot back cannot be performed on a hybrid disk resource that is already activated in another serer in the same server group. Execute it on a server in the standby server group.
Internal error. %1	Check the status of the cluster partition/data partition of the target resource. Make sure that memory or OS resource is sufficient.

# Hybrid disk status display command

**clphdstat**: the clphdstat command displays the status and configuration information on hybrid disk.

#### **Command line**

clphdstat --mirror *hybriddisk-alias* clphdstat --active *hybriddisk-alias* clphdstat --config

**Description** This command displays various status on hybrid disk and the

configuration information on hybrid disk resource.

**Option** --mirror Displays the status of hybrid disk resource.

--active Displays the activation status of hybrid disk

resource.

--config Displays the configuration information on hybrid

disk resource.

**Parameter** *hybriddisk-alias* Specifies the hybrid disk resource name.

**Return Value** 0 Success

Other than 0 Failure

**Notes** This command must be executed by the user with administrator

privilege.

Example of command display

See the next section for command display examples.

#### **Error Message**

Message	Cause/Solution
Invalid parameter.	The parameter is invalid. Check if there is any error in its format or parameter.
All servers are down.	Check that at least one server having the target hybrid disk resource is operating, and then execute the command again.
Internal error. %1	Restart the local server.


# Display examples of hybrid disk status display command

Hybrid disk resource status display

When the --mirror option is specified, the status of the specified hybrid disk resource is displayed.

There are two types of hybrid disk resource status display depending on the hybrid disk resource status.

When the hybrid disk resource status is other than Recovering



Description on each item

Item Name	Description	
Status	Hybrid disk resource status	
	Status	Description
	Normal	Normal
	Recovering	Mirror is being recovered
	Abnormal	Abnormal
	No Construction	Mirror initial construction has not been performed
	Uncertain	Unknown status or undefined of new/old

Mirror Color	Mirror Color Hybrid disk status in each server		
	Status	Description	
	GREEN	Normal	
	YELLOW	Mirror is being recovered	
	RED	Abnormal	
	ORANGE	Undefined of new/old	
	GRAY	Stopped or Unknown	
	BLUE	Both systems are active	
Lastupdate Time	Time when the data was last updated on the server		
Break Time	Time when mirror break occurred		
Difference Percent	Percentage of difference data on servers		
Disk Error	Disk I/O status		
	Status	Description	
	NO ERROR	Normal	
	ERROR	Abnormal (Unable to I/O)	
		Unknown	
	1		
DP Error	Whether or not there is data partition I/O error in servers		
CP Error	Whether or not there is cluster partition I/O error in servers		

## • When the hybrid disk resource status is Recovering

Status:	Recovering			
hd01	svg01 svg02			
Mirror Color	YELLOW	-> 40%	YELLOW	
Recovery Status				
Source Server Destination Server Used Time Remain Time	server1 server3 00:00:28 00:00:14			

## Description on each item

Item Name	Description	
Mirror Status	Hybrid disk resource status *1	
Mirror Color	Hybrid disk status in servers *1	
	Copy direction of mirror recovery is shown with an arrow.  -> : Copy from the left server group to the right	

	server group	
	Or	
	<- : Copy from the right server group to the left server group	
	Progress of copying is shown as xx%.	
Source Server	Copy source server name	
Destination Server	Copy destination server name	
Used Time	Time passed since copying started	
Remain Time	Estimated time required to complete copying	
	Because it is estimated from the copy rate of the finished part, the value may vary due to load status of the servers or other factors.	

<sup>\*1</sup> See "•. When the status of mirror disk resource is Normal".

## ♦ Hybrid disk resource active status display

When the --active option is specified, active status of the specified hybrid disk resource is displayed.

HD Resource Name:	hd01	
Server Name	Active Status	Current Server
svg01 server1 server2	Active Inactive	CURRENT 
svg02 server3 server4	Force Active Inactive	CURRENT 
Server group	p name	

#### Active status

Active Status	Description
Active	Active
Inactive	Inactive
Force Active	Forced activation
	Unknown

#### Current server

Currrent Server	Description
CURRENT	Current server
	Non-current server

♦ Hybrid disk resource configuration information display

When the --config option is specified, configuration information on all hybrid disk resources are displayed.

HD Resource Name: Syncmode:	hd01 Sync	
Config	svg01	svg02
Drive Letter Disk Size Server Name	Z: 1027MB server1 server2	Z: 1027MB server3 server4

## Description on each item

Item Name	Description
HD Resource Name	Hybrid disk resource name
Syncmode	Synchronization mode
Drive Letter	Drive letter of the data partition
Disk Size	Data partition size
Server Name	Member server of each server group

# Hybrid disk resource operation command

clphdctrl: the clphdctrl command operates hybrid disk resource.

#### **Command line**

```
clphdctrl --active hybriddisk-alias -n
clphdctrl --active hybriddisk-alias -f
clphdctrl --deactive hybriddisk-alias
clphdctrl --break hybriddisk-alias -n
clphdctrl --break hybriddisk-alias -f
clphdctrl --force hybriddisk-alias
clphdctrl --recovery hybriddisk-alias [-f or -a] [dest -servername]
clphdctrl --cancel hybriddisk-alias
clphdctrl --rwait hybriddisk-alias [-timeout time] [-rcancel]
```

**Note:** Make sure that the ExpressCluster service has been stopped when you use the --active or --deactive option.

**Description** Activates/deactivates hybrid disk resource and recovers mirror.

Option	active	Activates hybrid disk resource on the local server.
		If the status of hybrid disk resource is normal, mirroring is performed.
		If the status of hybrid disk resource is not normal, mirroring will not be performed.
	-n	Specifies normal activation for activation mode.
	-f	Specifies forced activation for activation mode.
	deactive	Deactivates the activated hybrid disk resource on the local server.
	break	Stops mirroring of the hybrid disk resource and makes the data status not to be the latest on the server where the command is executed. The data is not synchronized until mirror recovery is completed even if writing on the hybrid disk takes place.
	-n	Specifies the degeneration mode as normal degeneration. In the case of normal degeneration, mirroring is intermitted and the server becomes not the latest status only when the mirroring is executed normally on

the hybrid disk.

	-f	Specifies the degeneration mode as forced degeneration mode. In the case of forced degeneration, mirroring is intermitted and the server becomes not the latest status even if the mirroring target server/server group status is abnormal or unknown.
	force	Performs forced mirror recovery on the specified hybrd disk resource.
	recovery	Performs either full mirror recovery or differential mirror recovery for the specified hybrid disk resource with the local server as copy source.
	-f	Specifies full copy for recovery mode. This cannot be specified when -a is specified.
	-a	Automatically selects the recovery mode. When the difference can be identified, differential copy is performed. When the difference cannot be identified, full copy is performed. This cannot be specified when -f is specified. When neither -f or -a is specified, the recovery mode is automatically selected.
	cancel	Cancels mirror recovery.
	rwait	Waits for the completion of the specified disk resource mirror recovery.
	-timeout time	Specifies the time of mirror recovery completion timeout (second). This option can be omitted. When this option is omitted, timeout is not executed and waits for the completion of mirror recovery.
	-reancel	Intermits mirror recovery when waiting for the mirror recovery completion is timed out. This option can be set when -timeout option is set. When this optin is omitted, the mirror recovery continues even after the timeout takes place.
Parameter	hybriddisk-alias	Specifies the hybrid disk resource name.
	dest-servername	Specifies the copy destination server name. When you omit this, the copy destination server is automatically determined from another server group.
Return Value	. 0	Success
	Other than 0	Failure
	101	Invalid parameter
	102	Invalid status including the case whenrwait option is specified and mirror recovery is intermitted by -rcancel.
	103	Operations for the same resource are executed
		Evarage Cluster Y 2.1 for Windows Pafarance Gu

	simultaneously from other servers.
104	Operations for the same resource were executed simultaneously from the own server.
106	The server that command is executed does not have the target resource.
107	I/O error occured on the cluster partition or on the data partition.
109	Waiting for the completion of Mirror recovery of the target hybrid disk is timed out. (Only whenrwait -timeout option is specified)
110	Other errors

#### **Notes**

This command must be executed by the user with administrator privilege.

When performing mirror recovery again after mirror recovery failed, specify the same server you used last time for mirror recovery or another server in the same server group which this server belongs to as a copy source.

To resume mirror recovery that was suspended by selecting **Cancel**, use this command for forced mirror recovery.

# Example of command execution

Example 1: When activating hybrid disk resource hd1

# clphdctrl --active hd1 Command succeeded.

Example 2: When deactivating hybrid disk resource hd1

# clphdctrl --deactive hd1 Command succeeded.

Example 3: When recovering mirror for hybrid disk resource hd1

# clphdctrl --recovery hd1 Command succeeded.

### **Error Message**

Message	Cause/Solution	
Invalid parameter.	The parameter is invalid. Check if there is any error in its format or parameter.	
The status of [HD_resource_name] is invalid.	Check the status and execute the command again.	
This command is already run in another server.	After finishing the command which is currently executed, execute the command again.	
This command is already run in the local server.	After finishing the command which is currently executed, execute the command again.	

[copy_destination_serve_name] is down.	Start the server which has been specified as copy destination, or specify another server as copy destination to execute the command again.
[local_server_name] is not included in Servers that can run the Group of [HD_resource_name].	Execute the command from the server where the target HD resource can be started.
Disk error.	Check if there is not HW failure in the disk or disk path where cluster partition or data partition exists.
Mirror recovery of [HD resource name] is timed out.	Check if the specified timeout time is appropriate, or if the disk I/O or communication delay is not occurring due to heavy load.
Internal error. [error_code]	Restart the local server.

# Message output command

clplogcmd: the clplogcmd command registers the specified text into alert.

#### **Command line:**

clplogcmd -m message [--alert] [-i ID] [-l level]

#### Note:

Generally, it is not necessary to run this command for constructing or operating the cluster. You need to write the command in the script resource script.

Description	Write this command in the script resource script and output messages you want to send to the destination.	
	Messages are produced in the following format:	
	[ID] message	

Options	-m message	Specifies text to be produced in message. This option cannot be omitted. The maximum size of message is 498 bytes.
		You may use alphabets, numbers, and symbols. See below (*) for notes on them.
	alert	This parameter can be omitted. You can specify only alert as the output destination of this command.
		See "Directory structure of ExpressCluster" in Chapter 10, "The system maintenance information" for more information on output destinations.
	-i ID	Specify message ID.
		This parameter can be omitted. The default value 1 is set for the ID when the parameter is omitted.
	-l level	Select a level of alert output from ERR, WARN, or INFO. The icon on the alert view of the WebManager is determined according to the level you select here.
		This parameter can be omitted. The default value INFO is set to level when the parameter is omitted.
		See "Checking alerts using the WebManager" on page 56 for more information.

Return Value	0	Success
	Other than 0	Failure

Notes	Run this command as a user with Administrator privileges.	
	The specification of the —i option is different from that of the Linux version. The event ID that is displayed in alert is fixed and unchangeable in the Windows version	

# Example of command execution

**Example 1**: When specifying only message

When the following is written in the script resource script, text is produced in alert.

clplogcmd -m test1

The following is displayed in the alert view of the WebManager:

	Receive Time	Time <b>▽</b>	Server Name	Module Name	Event ID	Message
<b>(i)</b>	2004/09/01 14:00:00	2004/09/01 14:00:00	server1	logcmd	1	test1

**Example 2**: When specifying message, message ID, and level:

When the following is written in the script resource script, the text is produced in alert.

clplogcmd -m test2 -i 100 -l ERR

The following alert is displayed on the alert view of the WebManager:

	Receive Time	Time <b>▽</b>	Server Name	Module Name	Event ID	Message
*	2004/09/01 14:00:00	2004/09/01 14:00:00	server1	logcmd	3601	[100] test2

#### \* Notes on using symbols in text:

The symbols below must be enclosed in double quotes (""):

& | < >

(For example, if you specify "&" in the message, & is produced.)

The symbols below must have a backslash  $\setminus$  in the beginning:

(For example, if you specify \\ in the message, \ is produced.)

When there is a space in text, it must be placed in enclosed in double quotes ("").

The symbol % cannot be used in text.

# Controlling monitor resources (clpmonctrl command)

clpmonctrl: the clpmonctrl command controls the monitor resources.

#### **Command line:**

```
clpmonctrl -s [-m resource name ...] [-w wait time]
clpmonctrl -r [-m resource name ...] [-w wait time]
```

#### Note

This command must be run on all servers that control monitoring because the command controls the monitor resources on a single server.

Description	This <b>command</b> suspends and/or resumes monitor resources on a single
Description	server.

Option	-s,suspend	Suspends monitoring
	-r,resume	Resumes monitoring
	-m,	Specifies one or more monitor resources to be controlled.
	monitor	This option can be omitted. All monitor resources are controlled when the option is omitted.
		Waits for control monitoring on a monitor resource basis. (in seconds)
		This option can be omitted. The default value 5 is set when the option is omitted.

Return Value	0	Normal termination	
	1	Privilege for execution is invalid	
	2	The option is invalid	
	3	Initialization error	
	4	The cluster configuration data is invalid	
	5	Monitor resource is not registered.	
	6	The specified monitor resource is invalid	
	10	The cluster is not activated	
	11	The ExpressCluster service is suspended	
	12	Waiting for cluster synchronization	
	90	Monitoring control wait time-out	
	128	Duplicated activation	
	255	Other internal error	

# Example command execution

of

Monitor resource configuration

In the examples 1 through 4 below, the monitor resources of the server1 are controlled.

To control the monitor resources of the server2, run this command in the server2.

**Example 1:** When suspending all monitor resources:

```
# clpmonctrl -s
Command succeeded.
# clpstat -m
=== MONITOR RESOURCE STATUS ===
           Cluster: cluster
              *server0 : server1
               server1: server2
            Monitor0 [ipw1 : Caution]
               server0 [o] : Suspend
              server1 [o] : Online
              Monitor1 [miiw1: Caution] I
              _____
             server0 [o] : Suspend ____
               server1 [o] : Online
             Monitor2 [userw: Caution]
             | _server() [o] _: _ Suspend_ _ _ |
               server1 [o] : Online
```

```
Example 2: When resuming all monitor resources:
 # clpmonctrl -r
 Command succeeded.
 # clpstat -m
 === MONITOR RESOURCE STATUS ===
             Cluster: cluster
                *server0 : server1
                 server1: server2
                Monitor0 [ipw1 : Normal]
                 server0 [o] : Online
server1 [o] : Online
                Monitor1 [miiw1: Normal]
                 ______
                 server0[o] : Online _ _ _
                 server1 [o] : Online
                 -----,
                Monitor2 [userw: Normal]
                 server0 [o] : Online
server1 [o] : Online
Example 3: When suspending only the IP monitor resource (ipw1):
 # clpmonctrl -s -m ipw1
 Command succeeded.
 # clpstat -m
 === MONITOR RESOURCE STATUS ===
             Cluster: cluster
                 *server0 : server1
                 server1: server2
                Monitor0 [ipw1: Caution]
                server0 [o] : Suspend server1 [o] : Online
                Monitor1 [miiw1: Normal]
                 server0 [o] : Online
                 server1 [o] : Online
                Monitor2 [userw: Normal]
                 server0 [o] : Online
                 server1 [o] : Online
Example 4: When resuming only the IP monitor resource (ipw1):
 # clpmonctrl -r -m ipw1
 Command succeeded.
 # clpstat -m
```

```
=== MONITOR RESOURCE STATUS ===
Cluster : cluster
    *server0 : server1
    server1 : server2

    Monitor0 [ipwl : Normal]

    server0 [o] : Online
    server1 [o] : Online

    Monitor1 [miiwl: Normal]

    server0 [o] : Online
    server1 [o] : Online

    server1 [o] : Online

    server1 [o] : Online

    server1 [o] : Online

    server1 [o] : Online

    server1 [o] : Online

    server1 [o] : Online

    server1 [o] : Online
```

#### Remarks

If you suspend a monitor resource that is already suspended or resume that is already resumed, this command terminates successfully without changing the status of the monitor resource.

#### **Notes**

Run this command as a user with Administrator privileges.

Check the status of monitor resource by using the status display command or WebManager.

Before you run this command, use the clpstat command or WebManager to verify that the status of monitor resources is in either "Online" or "Suspend."

In the case of a monitor resource of which monitor timing is "Active", if a target resource stops temporarily in the active status, and then the target resource or the group which the target resource belongs to is activated, the monitor resource which has been stopped temporarily cannot detect an error. This is because the monitor resource does not start monitoring.

The following are examples of the case described above:

- 1. Stops an application monitor that is monitoring application resource temporarily.
- 2. Reactivate the application resource or the group that the application resource belongs to.

This reactivation procedure applies both manual and automatic when a monitor resource detects an error and reactivates an application by the recovery operation.

## **Error Messages**

Message	Causes/Solution	
Command succeeded.	The command ran successfully.	
You are not authorized to run the command. Log in as Administrator.	You are not authorized to run this command. Log in as a user with Administrator privileges.	
Initialization error. Check if memory or OS resources are sufficient.	Check if the memory or OS resource is sufficient.	
Invalid cluster configuration data. Check it by using the Builder.	The cluster configuration data is invalid. Check the cluster configuration data by using the Builder.	
Monitor resource is not registered.	The monitor resource is not registered.	
Specified monitor resource is not registered. Check the cluster	The specified monitor resource is not registered.	
configuration information by using the Builder.	Check the cluster configuration data by using the Builder.	
The cluster has been stopped. Check	The cluster has been stopped.	
the active status of the cluster service by using the command such as ps command.	Check the activation status of the ExpressCluster service by using the ps command.	
The cluster has been suspended. The cluster service has been suspended. Check activation status of the cluster service by using a command such as the ps command.	The ExpressCluster service has been suspended. Check the activation status of the ExpressCluster service by using a command such as ps command.	
Waiting for synchronization of the cluster. The cluster is waiting for	Synchronization of the cluster is awaited.	
synchronization. Wait for a while and try again.	Try again after synchronization of the cluster is completed.	
Monitor %1 was unregistered, ignored. The specified monitor resources %1is not registered, but continues processing. Check the cluster configuration data by using the	There is an unregistered monitor resource in the specified monitor resources, but it is ignored and the process is continued  Check the cluster configuration data by	
Builder. %1: monitor resource name	using the Builder.	
	%1: Monitor resource name	
The command is already executed. Check the execution state by using the "ps" command or some other command.	The command has already been run. Check the status by using the ps command.	
Internal error. Check if memory or OS resources are sufficient.	Check if the memory or OS resource is sufficient.	

# Controlling group resources (clprsc command)

clprsc: the clprsc command controls group resources

#### **Command line:**

```
clprsc -s resource_name [-h hostname] [-f]
clprsc -t resource_name [-h hostname] [-f]
```

**Description** This command starts and stops group resources.

**Option** -s Starts group resources.

-t Stops group resources.

-h Requests processing to the server specified by the

hostname.

When this option is skipped, request for processing is made to the following servers.

• When the group is offline, the command execution server (local server) .

• When the group is online, the server where group is

activated.

When the group resource is online, all group resources that the specified group resource depends starts up.

When the group resource is offline, all group resources that the specified group resource depends stop.

**Return Value** 0 success

-f

Other than 0 failure

**Example** Group resource configuration

# clpstat

====== CLUSTER STATUS =======

Cluster : cluster

<server>

\*server1 .... : Online
lankhb1 : Normal
lankhb2 : Normal
pingnp1 : Normal
server2 ... : Online
lankhb1 : Normal
lankhb2 : Normal
pingnp1 : Normal

```
<group>
   ManagementGroup .....: Online
     current
                                : server1
     ManagementIP
                                : Online
   failover1.....:Online
     current
                                : server1
     fip1
                                : Online
     md1
                                : Online
                                : Online
     script1
   failover2....: Online
     current
                                : server2
     fip2
                                : Online
     md2
                                : Online
     script1
                                : Online
<monitor>
   fipw1
                                 : Normal
                                 : Normal
   fipw2
   ipw1
                                 : Normal
   mdnw1
                                 : Normal
   mdnw2
                                 : Normal
   mdw1
                                 : Normal
   mdw2
                                 : Normal
```

**Example 1:** When stopping the resource (fip1) of the group (failover 1)

```
# clprsc -t fip1
Command succeeded.
#clpstat
====== CLUSTER STATUS ======
<abbreviation>
<group>
   ManagementGroup .....: Online
     current
                              : server1
     ManagementIP
                              : Online
   failover1.....:Online
     current
                              : server1
                              : Offline
     fip1
     md1
                              : Online
     script1
                              : Online
   failover2.....: Online
     current
                              : server2
```

fip2 : Online md2 : Online script1 : Online

<abbreviation>

**Example 2:** When starting the resource (fip1) of the group(failover 1)

# clprsc -s fip1

Command succeeded.

#clpstat

====== CLUSTER STATUS =======

<Abbreviation>

<group>

ManagementGroup .....: Online current : server1 ManagementIP : Online failover1 .....: Online current : server1 fip1 : Online md1 : Online : Online script1 failover2.....: Online current : server2 : Online fip2 md2 : Online script1 : Online

<Abbreviation>

Notes Run this command as a user with Administrator privileges.

Check the status of the group resources by the status display or the WebManager.

When there is an active group resource in the group, the group resources that are offline cannot be started on another server.

#### Error Messages

Message	Causes/Solution	
Log in as Administrator.	Run this command as a user with Administrator privileges.	
Invalid cluster configuration data. Check it by using the Builder.	The cluster construction information is not correct. Check the cluster construction information by Builder.	
Invalid option.	Specify a correct option.	
Could not connect server. Check if the cluster service is active.	Check if the ExpressCluster is activated.	

Invalid server status. Check if the cluster service is active.  Check if the ExpressCluster is activated.  Check if the ExpressCluster is activated.  Check if the ExpressCluster is activated.  Check if the ExpressCluster is activated.  Check if the ExpressCluster is activated.  Check if the ExpressCluster is activated.  Specify a correct server name in the cluster.  Connection was lost. Check if there is a server where the cluster service is stopped in the cluster.  Internal communication timeout has occurred in the cluster server. If it occurs frequently, set the longer timeout.  The group resource is busy. Try again later.  Timeout has occurred in internal communication in the ExpressCluster.  Set the internal communication timeout longer if this error occurs frequently.  The group resource is busy. Try again later.  Because the group resource is in the process of starting or stopping, wait for a while and try again.  Check the group resource status by using the WebManager or the clpstat command.  Wait till the other server starts or the wait time times out, then start the group resource on the local server.  The group resource has already been started on the other server. To start the group resource on the local server.  The group resource has already been started on the other server. To start the group resource on the local server, stop the group resource.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the W	Message	Causes/Solution
Invalid server name. Specify a valid server name in the cluster.  Connection was lost. Check if there is a server where the cluster service is stopped in the cluster.  Connection was lost. Check if there is a server where the cluster service is stopped in the cluster.  Check if there is any server with ExpressCluster service stopped in the cluster.  Check if there is any server with ExpressCluster service stopped in the cluster.  Check if there is any server with ExpressCluster service stopped in the cluster.  Check if there is any server with ExpressCluster service stopped in the cluster.  Check if there is any server with ExpressCluster service stopped in the cluster.  Check if there is any server with ExpressCluster service stopped in the cluster.  Check if there is any server with ExpressCluster service is connected in the cluster.  Set the internal communication timeout longer if this error occurred on the ExpressCluster.  Set the internal communication timeout longer if this error occurred on group resource.  Check the group resource status by using the webManager or the clustat command.  Check there is a processable group resource on the local server.  Check there is a processable group resource on the local server.  Check the group resource status by using the webManager or depstat command.  Check the group resource status by using the webManager or depstat command.  Check the group resource status by using the webManager or depstat command.  Check the group resource status by using the webManager or depstat command.  Check the group resource status by using the webManager or depstat command.  Check the group resource status by using the webManager or depstat command.  Check the group resource status by using the webManager or depstat command.  Check the group resource status by using the webManager or depstat command.  Check the group resource status by using the webManager or depstat command.  Check the group resource status by using the webManager or depstat command.  Check the group resource status		Check if the ExpressCluster is activated.
Connection was lost. Check if there is a server where the cluster service is stopped in the cluster.  Check if there is any server with ExpressCluster service stopped in the cluster.  Check if there is any server with ExpressCluster service stopped in the cluster.  Check if there is any server with ExpressCluster service stopped in the cluster.  Timeout has occurred in internal communication in the cluster server. If it occurs frequently, set the longer timeout.  The group resource is busy. Try again later.  Set the internal communication timeout longer if this error occurs frequently.  Because the group resource is in the process of starting or stopping, wait for a while and try again.  Check the group resource status by using the WebManager or the clpstat command.  Check the group resource status by using the webManager or the clpstat command.  Wait till the other server starts or the wait time times out, then start the group resource on the specified server.  Check there is a processable group resource on the specified server.  Check the group resource status by using the WebManager or dipstat command.  Check the group resource status by using the WebManager or dipstat command.  Check the group resource status by using the WebManager or dipstat command.  Check the group resource status by using the WebManager or dipstat command.  Check the group resource status by using the WebManager or dipstat command.  Check the group resource status by using the WebManager or dipstat command.  Check the group resource status by using the WebManager or dipstat command.  Check the group resource status by using the WebManager or dipstat command.  Check the group resource status by using the WebManager or dipstat command.  Check the group resource status by using the WebManager or dipstat command.  Check the group resource status by using the WebManager or dipstat command.  Check the group resource status by using the WebManager or dipstat command.  Check the group resource status by using the WebManager or dipstat command.		Check if the ExpressCluster is activated.
where the cluster service is stopped in the cluster.  Internal communication timeout has occurred in the cluster server. If it occurs frequently, set the longer timeout.  The group resource is busy. Try again later.  Because the group resource is in the process of starting or stopping, wait for a while and try again.  An error occurred on group resource. Check the status of group resource. Try it again after the other server is started, or after the Wait Synchronization time is timed out.  No operable group resource exists in the server.  The group resource has already been started on the local server.  The group resource has already been started on the local server, stop the group resource.  The group resource has already been stopped.  The group resource has already been stopped.  The group resource has already been stopped.  The group resource has already been stopped.  The group resource has already been stopped.  The group resource has already been stopped.  The group resource has already been stopped.  The group resource has already been stopped.  The group resource has already been stopped.  The group resource has already been stopped.  The group resource has already been stopped.  The group resource has already been stopped.  The group resource has already been stopped.  The group resource status by using the WebManager or clostat command.  The group resource has already been stopped.  The group resource status by using the WebManager or clostat command.  The group resource has already been stopped.  The group resource status by using the WebManager or clostat command.  The group resource has already been stopped.  The group resource status by using the WebManager or clostat command.  The group resource is not offline. Check the status of group resource status by using the WebManager or clostat command.  The group resource is not offline. Check the status of the depended group resource or specify the foption.  Depending resource is not offline. Check the status of the depended group resource or specify		Specify a correct server name in the cluster.
Internal communication timeout has occurred in the cluster server. If it occurs frequently, set the longer timeout.  Set the internal communication timeout longer if this error occurs frequently.  The group resource is busy. Try again later.  Because the group resource is in the process of starting or stopping, wait for a while and try again.  An error occurred on group resource. Check the status of group resource. Try it again after the other server is started, or after the Wait Synchronization time is timed out.  No operable group resource exists in the server.  The group resource has already been started on the local server.  The group resource has already been started on the local server, stop the group resource on the local server, stop the group resource.  The group resource has already been started on the local server, stop the group resource on the local server.  The group resource has already been started on the local server, stop the group resource.  The group resource has already been started on the local server, stop the group resource.  Check the group resource status by using the WebManager or clpstat command.  Stop the group to start the group resources on the local server.  Check the group resource status by using the WebManager or clpstat command.  Failed to start group resource. Check the status of group resource.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Because the status of the depended group resource or specify the -f option.  Depending resource is not online. Check the status of the depended group resource or specify the -f option.  Depending resource is not online. Check the status of the depended group resource or specify the -f option.  Invalid group resource name in the cluster.  The group resource is not registered.  The group resource is not registered.  The group resource on Security the -f opti	where the cluster service is stopped in the	
Set the internal communication timeout longer if this error occurs frequently.  The group resource is busy. Try again later.  Because the group resource is in the process of starting or stopping, wait for a while and try again.  An error occurred on group resource. Check the starting or stopping, wait for a while and try again.  Could not start the group resource. Try it again after the other server is started, or after the Wait Synchronization time is timed out.  No operable group resource exists in the server.  The group resource has already been started on the local server.  The group resource has already been started on the other server. To start the group resource on the local server, stop the group resource.  Check the group resource status by using the WebManager or clpstat command.  Stop the group resource status by using the WebManager or clpstat command.  Stop the group resource status by using the WebManager or clpstat command.  Failed to start group resource. Check the status of group resource.  Check the group resource status by using the WebManager or clpstat command.  Failed to start group resource. Check the status of group resource status by using the WebManager or clpstat command.  Failed to stop resource. Check the status of group resource is not offline. Check the group resource status by using the WebManager or clpstat command.  Failed to stop resource. Check the status of group resource is not offline, the group resource status by using the WebManager or clpstat command.  Because the status of the depended group resource or specify the -f option.  Depending resource is not online. Check the status of the depended group resource or specify the -f option.  Depending resource name. Specify a valid group resource is not registered.  The group resource is not registered.  The server is suspended. (Rebooting after down)  Internal error. Check if memory or OS resources.	the cluster server. If it occurs frequently, set the	
An error occurred on group resource. Check the status of group resource is in the server. To start the group resource on the local server. To start the group resource.  The group resource has already been started on the other server. To start the group resource on the local server, stop the group resource.  The group resource has already been started on the other server. To start the group resource on the local server, stop the group resource.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Stop the group resource status by using the WebManager or clpstat command.  Stop the group resource status by using the WebManager or clpstat command.  The group resource. Check the status of group resource.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Because the status of the depended group resource is not offline, the group resource cannot be stopped. Stop the depended group resource or specify the -f option.  Depending resource is not online. Check the status of the depended group resource or specify the -f option.  Depending resource is not online. Check the status of the depended group resource or specify the -f option.  The group resource cannot be started. Start the depended group resource or specify the -f option.  Invalid group resource name in the cluster.  Server is isolated.  The server is suspended. (Rebooting after down)  Not enough memory space or OS resource.		
Status of group resource.  Could not start the group resource. Try it again after the other server is started, or after the Wait Synchronization time is timed out.  No operable group resource exists in the server.  The group resource has already been started on the local server. To start the group resource on the specified server.  The group resource has already been started on the other server. To start the group resource on the local server. To start the group resource on the local server, stop the group resource.  The group resource has already been stopped.  The group resource has already been stopped.  The group resource has already been stopped.  Check the group resource status by using the WebManager or clpstat command.  Stop the group to start the group resources on the local server.  Check the group resource status by using the WebManager or clpstat command.  Failed to start group resource. Check the status of group resource.  Failed to stop resource. Check the status of group resource.  Failed to stop resource. Check the status of group resource is not offline. Check the status of group resource is not offline. Check the status of fresource is not offline. Check the status of resource is not offline. Check the status of the depended group resource or specify the —f option.  Depending resource is not online. Check the status of the depended group resource or specify the —f option.  Depending resource is not online. Check the status of the depended group resource or specify the —f option.  Because the status of the depended group is not online, the group resource cannot be started. Start the depended group resource or specify the —f option.  Invalid group resource name. Specify a valid group resource is not registered.  The server is suspended. (Rebooting after down)  Internal error. Check if memory or OS resources.	The group resource is busy. Try again later.	
after the other server is started, or after the Wait Synchronization time is timed out.  No operable group resource exists in the server.  The group resource has already been started on the local server.  The group resource has already been started on the other server. To start the group resource on the local server, stop the group resource.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Stop the group to start the group resources on the local server.  The group resource has already been stopped.  Check the group resource status by using the WebManager or clpstat command.  Failed to start group resource. Check the status of group resource.  Failed to stop resource. Check the status of group resource is not offline. Check the status of resource.  Depending resource is not offline. Check the status of resource is not offline. Check the status of resource is not offline. Check the status of resource is not offline. Check the status of resource is not offline. Check the status of resource is not offline. Check the status of resource is not offline. Check the status of the depended group resource or specify the -f option.  Depending resource is not online. Check the status of the depended group resource or specify the -f option.  Depending resource name. Specify a valid group resource is not registered.  The group resource is not registered.  The group resource is not registered.  The server is suspended. (Rebooting after down)  Internal error. Check if memory or OS resources		
the specified server.  The group resource has already been started on the local server.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Stop the group to start the group resources on the local server.  The group resource has already been stopped.  Check the group resource status by using the WebManager or clpstat command.  Failed to start group resource. Check the status of group resource.  Failed to stop resource. Check the status of group resource.  Failed to stop resource. Check the status of group resource is not offline. Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Because the status of the depended group resource is not offline, the group resource cannot be stopped. Stop the depended group resource or specify the -f option.  Depending resource is not online. Check the status of the depended group is not online, the group resource or specify the -f option.  Depending resource name. Specify a valid group resource is not registered.  The group resource is not registered.  The server is suspended. (Rebooting after down)  Internal error. Check if memory or OS resources  Not enough memory space or OS resource.	after the other server is started, or after the Wait	
the local server.  WebManager or clpstat command.  The group resource has already been started on the other server. To start the group resource on the local server, stop the group resource.  Check the group resource status by using the WebManager or clpstat command.  Stop the group to start the group resources on the local server.  The group resource has already been stopped.  Check the group resource status by using the WebManager or clpstat command.  Failed to start group resource. Check the status of group resource.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Depending resource is not offline. Check the status of the depended group resource is not offline, the group resource cannot be stopped. Stop the depended group resource or specify the -f option.  Depending resource is not online. Check the status of the depended group resource or specify the -f option.  Depending resource is not online. Check the status of the depended group resource or specify the -f option.  The group resource cannot be started. Start the depended group resource or specify the -f option.  The group resource is not registered.  The group resource is not registered.  The server is suspended. (Rebooting after down)  Internal error. Check if memory or OS resources  Not enough memory space or OS resource.	No operable group resource exists in the server.	
the other server. To start the group resource on the local server, stop the group resource.  WebManager or clpstat command.  Stop the group to start the group resources on the local server.  The group resource has already been stopped.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Failed to stop resource. Check the status of group resource.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Because the status of the depended group resource is not offline, the group resource or specify the -f option.  Depending resource is not online. Check the status of the depended group resource or specify the -f option.  Because the status of the depended group is not online, the group resource cannot be started. Start the depended group resource or specify the -f option.  Invalid group resource name. Specify a valid group resource name in the cluster.  Server is isolated.  The server is suspended. (Rebooting after down)  Internal error. Check if memory or OS resources  Not enough memory space or OS resource.		
The group resource has already been stopped.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Depending resource is not offline. Check the status of the depended group resource is not offline, the group resource cannot be stopped. Stop the depended group resource or specify the -f option.  Depending resource is not online. Check the status of resource is not online, the group resource or specify the -f option.  Depending resource is not online. Check the status of the depended group is not online, the group resource cannot be started. Start the depended group resource or specify the -f option.  Invalid group resource name. Specify a valid group resource is not registered.  The group resource is not registered.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Check the group resource status by using the WebManager or clpstat command.  Because the status of the depended group resource or specify the -f option.  The group resource cannot be started.  Start the depended group resource or specify the -f option.  The group resource is not registered.  The server is suspended. (Rebooting after down)  Internal error. Check if memory or OS resources.	the other server. To start the group resource on	WebManager or clpstat command.
Failed to start group resource. Check the status of group resource. Check the status of group resource. Check the status of group resource. Check the status of group resource. Check the status of group resource is not offline. Check the status of the depended group resource is not offline. Check the status of the depended group resource is not offline, the group resource cannot be stopped. Stop the depended group resource or specify the -f option.  Depending resource is not online. Check the status of the depended group resource or specify the -f option.  Depending resource is not online. Check the status of the depended group is not online, the group resource cannot be started. Start the depended group resource or specify the -f option.  Invalid group resource name. Specify a valid group resource name in the cluster.  Server is isolated.  The server is suspended. (Rebooting after down)  Not enough memory space or OS resource.		
of group resource.  Failed to stop resource. Check the status of group resource. Check the status of webManager or clpstat command.  Depending resource is not offline. Check the status of resource.  Depending resource.  Because the status of the depended group resource is not offline, the group resource cannot be stopped. Stop the depended group resource or specify the -f option.  Depending resource is not online. Check the status of the depended group is not online, the group resource cannot be status of resource.  Because the status of the depended group is not online, the group resource cannot be started. Start the depended group resource or specify the -f option.  Invalid group resource name. Specify a valid group resource name in the cluster.  The group resource is not registered.  Server is isolated.  The server is suspended. (Rebooting after down)  Not enough memory space or OS resource.	The group resource has already been stopped.	
group resource.  Depending resource is not offline. Check the status of resource is not offline, the group resource cannot be stopped. Stop the depended group resource or specify the -f option.  Depending resource is not online. Check the status of the depended group resource or specify the -f option.  Depending resource is not online. Check the status of the depended group is not online, the group resource cannot be started. Start the depended group resource or specify the -f option.  Invalid group resource name. Specify a valid group resource name in the cluster.  Server is isolated.  The server is suspended. (Rebooting after down)  Internal error. Check if memory or OS resources  Not enough memory space or OS resource.		
resource is not offline, the group resource cannot be stopped. Stop the depended group resource or specify the -f option.  Depending resource is not online. Check the status of the depended group is not online, the group resource cannot be started. Start the depended group resource or specify the -f option.  Invalid group resource name. Specify a valid group resource name in the cluster.  Server is isolated.  The server is suspended. (Rebooting after down)  Internal error. Check if memory or OS resources  Not enough memory space or OS resource.		
status of resource.  online, the group resource cannot be started. Start the depended group resource or specify the -f option.  Invalid group resource name. Specify a valid group resource name in the cluster.  Server is isolated.  The group resource is not registered.  The server is suspended. (Rebooting after down)  Internal error. Check if memory or OS resources  Not enough memory space or OS resource.		resource is not offline, the group resource cannot be stopped. Stop the depended group resource or
group resource name in the cluster.  Server is isolated.  The server is suspended. (Rebooting after down)  Internal error. Check if memory or OS resources  Not enough memory space or OS resource.		online, the group resource cannot be started. Start the depended group resource or specify the
Internal error. Check if memory or OS resources Not enough memory space or OS resource.		The group resource is not registered.
	Server is isolated.	The server is suspended. (Rebooting after down)

# Network warning light switch off command

clpdn1000s: the clpdn1000s commsswtiches off the network warning light.

#### **Command line:**

clpdn1000s -h host\_name

This command switches off the network warning light corresponding to the **Description** 

specified server.

**Option** -h Specify the target server whose network warning light you host\_name

want to switch off.

This must be configured.

Return 0 Completed successfully. value

> Other than 0 Terminated due to a failure.

Notes This command must be executed by a user with the administrator

privilege.

# **CPU frequency control command**

## clpcpufreq

The clpcpufreq command controls CPU frequency.

#### **Command line:**

clpcpufreq --high [-h hostname] clpcpufreq --low [-h hostname] clpcpufreq -i [-h hostname] clpcpufreq -s [-h hostname]

**Description** This command enables/disables power-saving mode by CPU frequency control.

**Option** --high Sets CPU frequency to the highest.

--low Sets CPU frequency to the lowest.-i Switch to automatic control by cluster.

-s Displays the current CPU frequency level.

high: Frequency is the highest

low: Frequency is lowered and it is in power-saving mode

-h Requests the server specified in hostname for processing.

If this is omitted, it requests the local server for processing.

**Return** Value 0 Completed successfully.

Other than 0 Terminated due to a failure.

**Example** # clpcpufreq -s

high

Command succeeded.(code:0)

# clpcpufreq -- high

Command succeeded.(code:0)

# clpcpufreq --low -h server1

Command succeeded.(code:0)

**Remark** If the **Use CPU frequency control** checkbox is not selected in the power

saving settings in cluster properties, this command results in error.

**Notes** This command must be executed by a user with the administrator

privilege.

When you use CPU frequency control, it is required that frequency is changeable in the BIOS settings, and that the CPU supports frequency

control by Windows OS power management function.

## Error Messages

Message	Cause/Solution
Log in as Administrator.	Log in as a user with Administrator privileges.
This command is already run.	This command has already been run.
Invalid option.	This option is invalid. Check the option.
Invalid mode. Check ifhigh orlow or -i or -s option is specified.	Check if either of thehigh,low, -I or -s option is specified.
Failed to initialize the xml library. Check if memory or OS resources are sufficient.	Check to see if the memory or OS resource is sufficient.
Failed to change CPU frequency settings.	Check the BIOS settings and the OS settings.
	Check if the cluster is started.
	Check if the setting is configured so that CPU frequency control is used.
Failed to acquire CPU frequency settings.	Check the BIOS settings and the OS settings.
	Check if the cluster is started.
	Check if the setting is configured so that CPU frequency control is used.
Failed to create the mutex.	Check if the memory or OS resource is sufficient.
Internal error. Check if memory or OS resources are sufficient.	Check if the memory or OS resource is sufficient.

### **Chassis identify control command**

### clpledctrl

The clpledctrl command controls the chassis identify function.

#### Command line:

clpledctrl -d [-h hostname] [-a] [-w timeout] clpledctrl -i [-h hostname] [-a] [-w timeout]

**Description** This command disables/enables chassis identify function.

**Option** -d Disables the chassis identify function.

> -i Enables the chassis identify function.

-h hostname server which Specifies the name of the

enables/disables the chassis identify function.

Specify -a to omit this.

All servers in the cluster are the targets. -a

The -a option can be omitted. If so, specify –h

-w timeout Specifies the timeout value of the command by the

If the -w option is not specified, it waits for 30

seconds.

Return

Completed successfully. Value

> Other than 0 Terminated due to a failure.

Notes This command must be executed by a user with the administrator

privilege.

Execute this command in the server operating normally in the same cluster

as the one which the target server belongs to.

If you disable the chassis identify function by this command, it is

cancelled when the cluster is restarted or when the target server recovers

the normal status.

**Examples** Example 1: When disabling (i.e. turn off the lamp which is turned on) the

chassis identify function in server1 (specify the command timeout as 60

# clpledctrl -d -h server1 -w 60

Example 2: When disabling chassis identify in all servers in the cluster

# clpledctrl -d -a

Example 3: When enabling the chassis identify function in server1 where the

Section I Detailed functions of ExpressCluster

function was disabled # clpledctrl -i -h server1

The result of command execution is displayed as follows: Detail of the processing Server name: Result (Cause if failed)

### Error messages

Message	Cause/solution	
Log in as Administrator.	Log in as a user with Administrator privileges.	
Invalid option.	The command line option is invalid. Specify the correct option.	
Internal error. Check if memory or OS resources are sufficient.	Check if the memory or OS resource is sufficient.	
Could not connect to all data transfer server. Check if the server has started up.	Could not connect to all the IP addresses specified. Check the IP addresses and the status of the target server.	
Could not connect to the data transfer server. Check if the server has started up.	Could not connect to all the IP addresses specified. Check the IP addresses and the status of the target server.	
Command timeout	The cause may be heavy load on OS and so on. Check this.	
Chassis identify is not setting or active at all server.	Chassis identify is disabled or not used.	
All servers are busy. Check if this command is already run.	This command may be run already. Check it.	
Failed to obtain the list of nodes.  Specify a valid server name in the cluster.	Specify a valid server name in the cluster.	

### Inter-cluster processing request command

### clptrnreq

The clptrnreq command requests a server to execute a process.

#### Command line:

clptrnreq -t request\_code -h IP [-r resource\_name] [-s script\_file] [-w timeout]

**Description** The command issues the request to execute specified process to the server in another cluster.

**Option** -t *request\_code* Specifies the request code of the process to be

executed. The following request codes can be

specified:

GRP\_FAILOVER Group failover

EXEC\_SCRIPT Execute script

-h *IP* Specifies the server to issue the request to execute

the process with IP address. You can specify more than one server by separating by commas. The maximum number of IP addresses you can specify is

32.

When you specify group failover for request code, specify the IP addresses of all the servers in the

cluster.

-r resource\_name Specifies the resource name which belongs to the

target group for the request for process when GRP\_FAILOVER is specified for request code.

If GRP\_FAILOVER is specified, -r cannot be

omitted.

-s script\_file Specifies the file name (within 30 characters) of the

script to be executed (e.g. batch file or executable file) when EXEC\_SCRIPT is specified for request code. The script needs to be created in the

work\trnreq folder in the folder where

ExpressCluster is installed in each server specified

with -h.

If EXEC\_SCRIPT is specified, -s cannot be omitted.

-w *timeout* Specifies the timeout value of the command by the

second. The minimum value is 5 seconds.

If the -w option is not specified, the command waits

for 1 second shorter than script time out.

**Return** 0 Completed successfully.

Other than 0 Terminated due to a failure.

#### **Notes**

This command must be executed by a user with the administrator privilege.

This command cannot be executed when the ExpressCluster Transaction service is not operating on the server with the IP address specified by -h.

When WebManager connection restriction is conducted by the client IP address on this target server, it is required that connection to the address of the server to execute the command is permitted.

It is required that ExpressCluster for Windows of internal version 10.02 or later, or ExpressCluster for Linux of internal version 2.0.2\_1 or later is set up in the server which executes this command and the server with the IP address specified by -h.

### **Examples**

Example 1: When performing a failover on the group having the appli1 resource of another cluster

# clptrnreq -t GRP\_FAILOVER -h 10.0.0.1,10.0.0.2 -r appli1

**GRP\_FAILOVER 10.0.0.1: Success** 

**GRP\_FAILOVER 10.0.0.2:** Group that specified resource (appli1) belongs is offline.

Example 2: When executing the scrpit1.bat script by the server with IP address 10.0.0.1

# clptrnreq -t EXEC\_SCRIPT -h 10.0.0.1 -s script1.bat

EXEC\_SCRIPT 10.0.0.1: Success

#### Error messages

Message	Cause/solution
Log in as Administrator.	Log in as a user with Administrator privileges.
Invalid option.	The command line option is invalid. Specify the correct option.
All servers are busy. Check if this command is already run.	This command may be run already. Check it.
Internal error. Check if memory or OS resources are sufficient.	Check if the memory or OS resource is sufficient.
Command timeout	The cause may be heavy load on OS and so on. Check this.
Failed to obtain the list of nodes. Specify a valid server name in the cluster.	Failed to obtain the list of nodes. Specify a valid IP address.
Could not connect to all data transfer server. Check if the server has started up.	Could not connect to all IP addresses specified. Check the IP addresses and the status of the target server.
Could not connect to the data transfer server. Check if the server has started up.	Could not connect to the IP address specified. Check the IP address and the status of the target server.
GRP_FAILOVER <i>IP</i> : Group that specified resource ( <i>resouce_name</i> ) belongs to is offline.	Failover process is not performed because the group to which the specified resource belongs is not started on the target server.
EXEC_SCRIPT IP: Specified script ( script_file ) does not exist.	The script does not exist on the specified server.
does not exist.	Check it.

EXEC_SCRIPT <i>IP</i> : Specified script ( <i>script_file</i> ) is not executable.	The specified script could not be executed.	
io not executable.	Check that execution is permitted.	
reqest_code IP: This server is not permitted to execute clptrnreq.	The server that executed the command does not have permission. Check that the server is registered to the connection restriction IP list of WebManager.	
regest_code IP : REQEST_TYPE failed in	The execution processing of the request type failed.	
execute.	(Either of a present request type Failover or Script is specified.)	

### **BMC** information change command

### clpbmccnf

The clpbmccnf command changes the information on BMC user name and password.

### **Command line:**

clpbmccnf [-u username] [-p password]

Description

This command changes the user name/password for the LAN access of the baseboard management controller (BMC) which ExpressCluster uses for chassis identify or forced stop.

**Option** -u username Spe

Specifies the user name for BMC LAN access used by ExpressCluster. A user name with Administrator privilege needs to be specified. The -u option can be omitted. Upon omission, when the -p option is specified, the value currently set for user name is used. If there is no option specified, it is configured

interactively.

-p *password* Specifies the password for BMC LAN access used

by ExpressCluster. The -p option can be omitted. Upon omission, when the -u option is specified, the value currently set for password is used. If there is no option specified, it is configured interactively.

Return Value

O Completed successfully.

Other than 0 Terminated due to a failure.

**Notes** 

This command must be executed by a user with the administrator privilege.

Execute this command when the cluster is in normal status.

BMC information update by this command is enabled when the cluster is started/resumed next time.

This command does not change the BMC settings. Use a tool attached with the server or other tools in conformity with IPMI standard to check

or change the BMC account settings.

**Examples** 

When you changed the IPMI account password of the BMC in server1 to mypassword, execute the following on server1:

# clpbmccnf -p mypassword

Alternatively, enter the data interactively as follows:

# clpbmccnf

New user name: <- If there is no change, press **Return** to skip

ExpressCluster X 2.1 for Windows Reference Guide

New password: \*\*\*\*\*\*\*

Retype new password: \*\*\*\*\*\*\*

Cluster configuration updated successfully.

### Error messages

Message	Cause/solution	
Log in as Administrator.	Log in as a user with Administrator privileges.	
Invalid option.	The command line option is invalid. Specify the correct option.	
Failed to download the cluster configuration data. Check if the cluster status is normal.	Downloading the cluster configuration data has been failed. Check if the cluster status is normal.	
Failed to upload the cluster configuration data. Check if the cluster status is normal.	Uploading the cluster configuration data has been failed. Check if the cluster status is normal.	
Invalid configuration file. Create valid cluster configuration data by using the Builder.	The cluster configuration data is invalid. Check the cluster configuration data by using the Builder.	
<pre>tmp_dir already exists. Please delete it and try again.</pre>	The folder to store temporary file already exists.  Delete the folder and execute the command again.	
Can not remove directory: tmp_dir.	Deleting the folder to store temporary file failed. Delete the folder separately.	
Internal error. Check if memory or OS resources are sufficient.	Check if the memory or OS resource is sufficient.	

### Shutdown hook configuration command

### clphookctrl

The clphookctrl command configures the shutdown hook function.

#### **Command line:**

clphookctrl -s [-m *mode*] clphookctrl -m *mode* clphookctrl -t

#### **Description**

This command configures the function which hooks the OS shutdown process to execute node shutdown or restart of ExpressCluster. By using this function, OS shutdown or restart can be performed after successfully terminating or moving the operating failover group when OS shutdown is performed by other than ExpressCluster.

**Option** -s Enables the shutdown hook function.

-t Disables the shutdown hook function.

-m *mode* Configures the process to be executed after the OS

shutdown hook. Specify either of the following for

mode:

SHUTDOWN Server shutdown (preset value)

REBOOT Server restart

Return Value

0 Completed successfully.

Other than 0 Terminated due to a failure.

**Notes** 

This command must be executed by a user with the administrator

privilege.

The configuration by the -s option is enabled when the ExpressCluster Server service is started next time. Configuration by other options are enabled immediately.

Shutdown hook function cannot be used in Windows Server 2008.

**Examples** 

If there is a possibility that OS shutdown is executed by the application or middleware other than ExpressCluster, you can cancel the OS shutdown to perform ExpressCluster server shutdown by executing the following command in each cluster server.

# clphookctrl -s

Note that in this case although OS restart is executed, it is shut down so that the server is not restarted. Upon restarting the OS, it is required to execute the following command to change the operation settings in advance.

### # clphookctrl -m REBOOT

### Error messages

Message	Cause/solution	
Invalid option.	The command line option is invalid. Specify the correct option.	
Failed to open/edit the registry.	Registry operation has been failed. Check if it is executed with Administrator privilege and ExpressCluster is installed correctly.	

# Chapter 5 Compatible command reference

This chapter describes compatible commands.

### This chapter covers:

Compatible command overview	336
Note on compatible commands	336
Compatible commands	336
Displaying the messages on ExpressCluster clients (armbcast command)	338
Registering the messages on a log file or an alert log (armlog command)	
Starting the applications or services (armload command)	340
Terminating the application or service (armkill command)	
Waiting for the start or stop of groups (armgwait command)	349
Exclusive control between servers command (armcall command)	
Retrieving the cluster wide variable or local variable (armgeted command)	352
Setting the cluster wide variable or local variable (armsetcd command)	353
Monitoring errors on the connection to the shared resources (armwhshr commar	nd)354
Controlling the applications or services started by the armload command (E	ExpressCluster
Task Manager)	
Shutting down the server (armdown command)	
Moving or failing over a group (armfover command)	
Starting a group (armgstrt command)	
Stopping a group (armgstop command)	
Starting or stopping the application or service, suspending or resuming the	
(armloadc command)	
Suspending the script execution until the user's direction (armpause command)	
Suspending the script execution for the specified time (armsleep command)	
Starting the network sharing of the directory (armnsadd command)	
Stopping the network sharing of the directory (armnsdel command)	
Setting the IP address returned by gethostbyname() (armwsset command)	
Setting or displaying the start delay time (armdelay command)	
Setting or displaying operations at the occurrence of the emergency shute	
command)	
Shutting down the whole cluster (armstdn command)	
Returning the server with the status of "Suspension (isolated)" (armmode comm	
Permitting an access to the mirror disk (mdopen command)	
Prohibiting an access to the mirror disk (mdclose command)	
Permitting an access to the shared disk (sdopen command)	
Prohibiting an access to the shared disk (sdclose command)	380

### Compatible command overview

Compatible commands have compatibility with commands used in ExpressCluster Ver8.0 or earlier in functions. This section explains how to use compatible commands.

### Note on compatible commands

The following is the note on compatible commands.

◆ To use a compatible command, the name of a cluster, server and group needs to be configured according to the naming rules of the conventional version.

### **Compatible commands**

Commands that can be used only in scripts		
command	Description	
armbcast.exe	Displays a default or optional message on the client on which the ExpressCluster client is running.	
armlog.exe	Registers log messages to the log file.	339
armload.exe	Starts an application. The application started by the armload.exe can be stopped by the armkill.exe in any position of a script.	340
armkill.exe	Stops the application started by the armload.exe.	
armgwait.exe	Waits for the start or stop of groups	349
armcall.exe	Executes a command specified as a parameter or a program exclusively on nodes.	350
armgetcd.exe	Retrieves the value specified to the desired variable by the armsetcd.exe command. This command can be used for branch conditions of scripts.	352
armsetcd.exe	Sets the value to the desired variable. This value can be referred by the armgetcd.exe command.	353
armwhshr.exe	Monitors errors on the connection to the shared name.	354

Commands that can be used both in and outside scripts.			
command	Description	Page	
armaswth.exe	Starts or stops the application or service, or suspends or resumes the monitoring or the application or service that is started by the armload.exe command.		
armdown.exe	Shuts down a server when you want to fail over a group intentionally, such as when starting or stopping the application or service fails.		
armfover.exe	Moves or fails over groups.	362	
armgstrt.exe	Starts groups.	363	
armgstop.exe	Stops groups.	364	
armloadc.exe	Start or stop the application or service, or suspends or resumes the monitoring.	365	
armpause.exe	Suspends scripts. This command can be used as a debugger.	367	
	Permit the interaction with desktop. You can configure the setting for the interaction with desktop on the <b>Service</b> of <b>Administrative Tools</b> on <b>Programs</b> .		
armsleep.exe	Suspends the script execution for a specified time.		
armnsadd.exe	Starts sharing a network drive. This command functions in the same way as the net share shared_name=path_name.		
armnsdel.exe	Releases the network sharing forcibly specified by the net share shared_name=path_name.		
armwsset.exe	Sets the IP address returned by executing gethostbyname() on the local server to the specific application.		
	an be used only outside scripts		
command	Description	Page	
armdelay.exe	Sets or refers to the delay time of the ExpressCluster service startup on the NEC Express5800/ft series or servers that have equivalent fault-tolerant functions.	373	
armem.exe	Sets or refers to the mode at emergency shutdown. 37		
armstdn.exe	Shuts down a cluster.	375	
armmode.exe	Returns servers to a cluster.	376	
mdopen.exe	Permits an access to the mirror disk.	377	
mdclose.exe	Prohibits an access to the mirror disk. 378		

### Important:

The installation directory contains executable-format files and script files that are not listed in this guide. Do not execute these files other than ExpressCluster. Any problems caused by not using ExpressCluster will not be supported.

# Displaying the messages on ExpressCluster clients (armbcast command)

 $armbcast.exe: \ \ \text{the armbcast.exe} \ command \ displays \ the \ messages \ on \ ExpressCluster \ clients.$ 

### **Command line:**

```
Format 1 armbcast.exe /ID n /S group\_name Format 2 armbcast.exe /MSG msg\_strings [/A | /S group\_name]
```

Description	This command displays the default or optional messages on monitors of clients.	
-------------	--	--

Parameter	/ID n	Displays a message that corresponds to the ID specified in <i>n</i> . You need to register this message in advance.
		This parameter cannot be specified with /MSG.
	/MSG msg_strings	Displays a character string <i>msg_strings</i> on clients. The maximum size of a string is 127 bytes.
		When the character string includes spaces, enclose it in double quotation marks. When you use double quotation marks in the string, describe them as \".
		This parameter cannot be specified with /ID.
	/A	Displays a message on all clients.
	/S group_name	Displays a message on all clients that use the group specified in <i>group_name</i> .
		When using a Format 1, you cannot omit this parameter.
		When using a Format 2, you cannot specify this parameter with /A. You can omit /A and /S. When omitted, /A is assumed to be specified.

Return Value	0	Success
	7	The ExpressCluster Server service has not been started.
	9	The parameter is invalid.

Notes	This command cannot be used when recovering servers to a cluster (when	
	the environment variable of start script "CLP_EVENT" is "RECOVER").	

Remarks	This command can be used only in scripts.
---------	---

# Registering the messages on a log file or an alert log (armlog command)

armlog.exe: The armlog exe command registers the messages on a log file or an alert log.

### **Command line:**

armlog.exe log\_strings [/arm]

Description	This command registers specified messages to a log file or an alert log.
	The messages are registered on the log file (arm.log) of the server on which this command is run. They are also displayed on the Alert view of the WebManager.

Parameter	log_strings	Specifies a message string to be registered.
		The maximum size of a string is 128 bytes (when a string is displayed on the Alert view, the size is 111 bytes).
		When the character string includes spaces, enclose it in double quotation marks. When you use double quotation marks in the string, describe them as \".
	/arm	Displays a message on the Alert view of the WebManager.
		When this parameter is omitted, a message is registered only to a log file.

Return Value	0	Success	
	1 Logs were not registered due to an error.		
	8	The ExpressCluster Server service has not been started.	
	9	The parameter is invalid.	

Remarks	This command can be specified only in scripts.
	Time command can be specified only in scripts.

[/INT time]

### Starting the applications or services (armload command)

armload.exe: the armload.exe command starts applications or services.

Description	This command starts applications or services.
	A failover or restart occurs when the started application or service fails (when specified as a monitoring target). Monitoring failures continues until the application or service is terminated by ARMKILL.
A failure is a loss of a process for the application, and a service sto (SERVICE_STOPPED) and abnormal termination for the service.	

Parameter	watchID	ID for monitoring.
		This ID is used for terminating the application or service by the ARMKILL command. Be aware of the following notes when using this parameter:
		* The same IDs cannot be specified within a cluster.
		* You cannot use IDs starting with "NEC" since those are already allocated (IDs of "NEC_product_name+ something extra" are used for the product programs of NEC).
		* Specify the ID with alphanumeric characters of up to 255 bytes (case-sensitive).


/U user-no	ame Specifies the year account result that must the
70 4301 14	Specifies the user account name that runs the application.
	This parameter is optional. When omitted, the application is started with the local system account.
	* This parameter cannot be specified in Format 2.
	* When specifying this parameter, refer to (3) on Note.
/WINDO	Specifies the window size of an application. The following can be specified to <i>size</i> .
	maximum The application or service starts with windows of a maximum size.
	normal The application or service starts with windows of a size specified by the application.
	hide The application or service starts with hidden windows.
	This parameter is optional. When omitted, the application or service starts with windows of a minimum size.
	* This parameter cannot be specified in Format 2.
/C [CMD]	Specifies the format to pass the parameter-n to the application or service. Specify this option when the parameter-n ends with an escape character (\). Refer to the following examples to specify the parameter-n.
	Example 1) when the command passes "c:\" to app.exe.  ARMLOAD WatchID /C app.exe c:\ Example 2) when the command passes "c:\Program Files\" to app.exe. Enclose "c:\Program Files\" in double quotation marks, and add escape characters for the number of escape characters in the end. armload WatchID /C app.exe  "c:\Program Files\\"
	* Specify "CMD" as well when specifying this parameter and the type of application is command.
/WIDKE	Starts or stops the application or service with no monitoring parameter (/M, /R) specified by using the ExpressCluster Task Manager or the ARMLOADC command.
	* This option is ignored when /W, /M or /R is specified.
/W	Waits until the execution of the application is terminated. When this parameter is specified, controls are not returned from this command until the application terminates. This parameter is optional.
	* This parameter cannot be specified with /M or /R.
	* This parameter cannot be specified in Format 2.

/M	Monitors the application or service. This parameter is optional. When omitted, monitoring is not performed.
	* This parameter cannot be specified with /W or /R.
	* When you use this parameter without specifying /FOV, servers are shut down at failure.
/R retry	Monitors the application or service and specifies the threshold of the restart count. This parameter is optional. When omitted, monitoring is not performed.
	* The value from 1 through 9 can be specified.
	* This parameter cannot be specified with /M or /W.
/H hour	Specifies the time to reset the restart count of the application or service to 0. The value indicates the time from the group startup. The time can be specified by the hour. This parameter is optional.
	* The value from 1 through 24 can be specified.
	* Restart count is not reset if this parameter is omitted with the parameter /R specified.
/SCR	When this parameter is specified, the application or service is restarted by scripts. This parameter is optional.
	* The application or service is restarted by itself if this parameter is omitted with the parameter /R specified.
/FOV	Fails over groups when the restart count threshold is exceeded on the application or service monitoring. This parameter is optional.
	* Servers are shut down if this parameter is omitted with the parameter /M or /R specified.
/CNT count	A failover is not performed when the number of failovers already performed exceeds the count specified by this option. This is to avoid servers from repeating failing over endlessly. The number of failovers is counted for each server.
	The value from 1 through 255 can be specified.
	When omitted, 8 is specified.
	The failover count is reset to 0 on a specific server when:  the normal status continues more than 1 hour the server is restarted
exec-name	the failover group is activated
	Specifies an executable file name.  * This parameter cannot be specified in Format 2
parameter-n	* This parameter cannot be specified in Format 2.
	Passed to an executable file. This parameter is optional.
/S	Specifies that the target to be started is a service.
	* This parameter cannot be specified in Format 1.

T .	/ <b>A</b> 1	
	/A	Specify this parameter when you want to specify the service as a monitoring target even though it is already started.
		This parameter is optional.
		* This parameter cannot be specified in Format 1.
	WAIT time	Specifies the time to wait for the completion of a service startup by the second. When this parameter is specified, this command does not return controls while waiting for the service to complete startup (SERVICE_RUNNING) or within the wait time. This parameter is optional. When omitted, the command does not wait for the completion of a startup.
		* This parameter cannot be specified in Format 1.
		* The value from 0 through 3600 can be specified. When 0 is specified, the command waits for the completion of a startup endlessly.
7	INT time	Specifies restart interval of the application or service, or scripts by the second. This parameter is optional When omitted, 0 (second) is specified to the restart interval.
		* This parameter is valid when /R or /R and /SCR options are specified.
		* The value from 0 through 3600 can be specified.
S	service-name	Specifies the service name.
		* This parameter cannot be specified in Format 1.
		For service-name, specify one of the following:
		(1) Specify the service name that is displayed on the <b>Services</b> on the <b>Administrative Tools</b> .
		(2) Specify xxxx that matches with the service name displaying "DisplayName", the key of xxxx of the following registry in <b>Services</b> on <b>Administrative Tools</b> .
		HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Services\xxxx
		Example) For FTP service of IIS
		Name displayed on the <b>Service</b> window
		FTP Publishing Service
		Name displayed on the registry
		\Services\MSFTPSVC DisplayName:REG_SZ: FTP Publishing Service
		Format: armload WatchID /S "FTP Publishing Service"
		or armload WatchID /S MSFTPSVC

Return Value	0	Success (the target application or service has started)	
	1	Cannot start the target application or service	
	2	Cannot perform process monitoring	
	3	The specified watchID is already used.	
	4	Time-out occurred while waiting for the service to complete startup (the service is starting up).	
	8	The ExpressCluster Server service is not started.	
	9	The parameter is invalid.	

### Remarks (1) This command can be used only in scripts. (2) Multiple parameters can be specified for a command that is passed to an executable file. (3) The figure below indicates operations performed when the application or service started by ARMLOAD fails. 1. The application or service is started by ARMLOAD 2. A failure occurs 3. Threshold check 4. When the threshold is not exceeded, the application or service is restarted by scripts. 4.-1: Stop script execution 4-2: Start script execution 5. When the threshold is exceeded, a failover occurs or a server shuts down 5-1: Stop script execution 5-2: Fails over to another ExpressCluster server



#### **Notes**

- (1) This command can be specified only in scripts.
- (2) When you start the application with GUIs without specifying an account, select Allow service to interact with desktop on the ExpressCluster Server service. When not selected, GUIs of the application are not displayed.
- (3) When you specify a user account, it should have "local logon" permission. For information on the user permissions, see the help of the domain user administrator.

When you specify the domain of an account explicitly, specify the following. Note that the domain name and the user name should be within 15 characters.

When the account is a local administrator: armload watchid /u administrator ap.exe When the account is a domain\administrator: armload watchid /u domain\administrator ap.exe

(4) When you use the monitoring function (/M option) of the ARMLOAD command, specify Dr. Watson (DRWTSN32.EXE) as a default debugger used by the operating system.

To check this setting, go to the registry
\\HKEY\_LOCAL\_MACHINE\Software\Microsoft\\
Windows NT\CurrentVersion\AeDebug
and find the value with the name "Debugger" or "Auto."
Check if the value of "Auto" is set to 1, and "Debugger" to "DRWTSN32."

When the setting values are different from those, change the settings to use Dr.Watson in addition to the default debugger you are using. For this setting, start Dr.Watson by running the drwtsn32 –i command on the command prompt.

At OS installation, the value of "Auto" is set to 1, and "Debugger" to "DRWTSN32."

- (5) Applications not suitable for ARMLOAD monitoring function The applications whose processes do not stay resident persistently are not suitable for the process monitoring (\*). Since the process monitoring is assumed to monitor processes that stay persistently and do not terminate by themselves, it determines that an error occurs on an application when the started process is terminated.
  - (\*) The following applications are examples: An application whose process started by ARMLOAD does not stay resident persistently An application whose process started by ARMLOAD starts its child process, and the process started first does not stay resident persistently (ARMLOAD only monitors the process it started)
- (6) The application that requires GUIs may be terminated when it is started by the ARMLOAD command and logged off. To prevent the application from being terminated, start it with an account (/U option).

### Limitations

- (1) The ARMLOAD command with an account cannot be used in a batch program that is run with an account.
- (2) The application that is run with an account (including a child process) cannot use the LogonUser() function.
- (3) Do not execute a 16-bits application since it cannot be terminated by the ARMKILL command.
- (4) When including spaces in a parameter, enclose it in quotation marks.
  - Example) ARMLOAD Wid1 "\Program Files\Application.exe"
- (5) Only the process that is started by the ARMLOAD command can be terminated by the ARMKILL command.
- (6) Do not run the applications (XXXX.EXE) that ExpressCluster provide.
- (7) The ARMLOAD command may terminate abnormally (return value 1: Cannot start the target application or service) if the application with an account is started while it cannot access the domain controller (due to a failed server or network disconnection, etc.).

# Terminating the application or service (armkill command)

armkill.exe: the armkill exe command terminates the application or service.

### **Command line:**

armkill.exe watchID [/C | /T time]

Description	This command terminates the application or service that was started up by the ARMLOAD command.
	When one service is operated (monitoring target) with several ARMLOAD commands (when several ARMLOAD commands with /A option operate one service), the service is not terminated until ARMKILL is run for all <i>watchID</i> .

Parameter	watchID	Specifies the monitoring ID of the application or service you want to terminate.
		Use the ID specified when the application or service was started up by the ARMLOAD command.
	/C	Cancels the monitoring of the application or service but does not terminate the application or service.
		This parameter is optional. When omitted, the application or service is terminated. This parameter cannot be specified with the /T parameter.
	/T time	Sets the termination wait time of the application or service. The range that can be specified is from 0 to 3600 seconds. If 0 is specified, the command waits for the completion of termination of the application or service endlessly. This parameter is optional. When omitted, the wait time is set to 40 seconds. This parameter cannot be specified with the /C parameter.

Return Value	0	Success (the target application or service was terminated).	
	1	The application or service has already been terminated.	
	2	The application or service was not terminated.	
		(The application or service is being terminated.)	
	8	The ExpressCluster Server service has not been started.	
	9	The parameter is invalid.	

### Remarks

- (1) This command can be specified only in scripts.
- (2) To terminate the application, this command sends the WM\_CLOSE message to it. If the application does not terminate within the specified time (/T time), this command executes the TerminateProcess() for the target application to forcibly terminate the application process.
- (3) To terminate the service, the requirement to stop the service is sent to the service control manager (SCM). When terminating the service has not been completed within the specified time (/T time), the return value of 2 is returned.
- (4) If /C is specified on this command, the application or service cannot be terminated by ARMKILL.

# Waiting for the start or stop of groups (armgwait command)

armgwait.exe: the armgwait.exe command waits for the start or stop of groups.

### **Command line:**

armgwait.exe group\_name [time-out] [/stop]

Description	This command waits for the start or stop of groups.
	This command waits until the status of a group becomes active (when waiting for activation) or inactive (when waiting for termination), or until the specified time is exceeded.

Parameter	group_name	Specifies a name of the group whose completion of start or stop the command waits for.
	time-out	Specifies the time-out by the second.  When this parameter is omitted, the time-out value is set to default (120 seconds).
	/stop	Waits until the group is terminated.  When this parameter is omitted, this command waits for the startup of the group.

Return Value	0	The status of the failover group is active or inactive.	
	1	The time-out has elapsed.	
	7	The ExpressCluster Server service has not been started.	
	8	The specified group does not exist.	
	9	The parameter is invalid.	

Notes	Do not run this command directly from the start or stop script. When
	using this command from those scripts, prepare the batch file on which
	the command is described, and then run the batch file on the start or stop
	script by writing "START batch_file_name" on it.

Remarks	This command can be run only in scripts. Follow the process on Note
	when using this command on the start or stop script.

# Exclusive control between servers command (armcall command)

armcall.exe: the armcall. exe command runs commands or programs exclusively on nodes.

### **Command line:**


armcall.exe [/L lockname] exec\_name [parameter ...]

Description	This command executes a program from a script without terminating it,
	and returns the control to the script that is invoked again. This program is
	executed exclusively between nodes.

Parameter	/L lockname	Specifies the lock name. When this option is omitted, "Default" is specified for the name.  The commands are run exclusively for each lock name specified by this parameter.
	exec_name	Specifies the command or program to be run.
	parameter	Specifies the command line information required to run the program specified in <i>exec_name</i> .

Return Value	0	Success
	8	The program was not run due to an error.
	9	The parameter is invalid.

Remarks	This command can be run only in scripts.
---------	--



# Retrieving the cluster wide variable or local variable (armgeted command)

armgetcd.exe: the armgetcd.exe command retrieves the cluster wide variable or local variable.

### **Command line:**

Remarks

armgetcd.exe [/C] variable

Description	This command retrieves the setting value of the cluster wide variable or local variable specified by the armsetcd command.		
Parameter	/C		Retrieves the setting value of the cluster wide variable. When this parameter is omitted, the value of the local variable is retrieved.
	variable		Specifies the variable name set by the ARMSETCD command.
Return Value	The value could not be retrieved due to an error.		
	1-255 The value set by the ARMSETCD command is returned.		

This command can be specified only in scripts.

command, 0 is returned.

If you specify the variable name which is not set by the armseted

# Setting the cluster wide variable or local variable (armsetcd command)

armsetcd.exe: The armsetcd.exe sets the cluster wide variable or local wide variable.

### **Command line:**

armsetcd.exe [/C] variable value

Description	This command sets the cluster wide variable or the local variable.
	The setting value of the variable set by this command can be referred by using the armgeted command on the same or other scripts.
	The cluster wide variable is shared between servers in a cluster. The variable set by the armsetcd command on one server can be referred or changed on another server.
	The local variable is valid only on the server on which the armseted command is run.

Parameter	/C	Sets the variable as a cluster wide variable.
	When this parameter is omitted, the variable is set local variable.	
	variable Specifies the name of the variable to be set. Specify the name with up to 127 alphanumeric characters.  (The name is case-sensitive.)	
	value Specifies the value to be set to the variable on variation in integers from 1 through 255.	

Return Value	0	Success	
	8 The variable was not set due to an error.		
	9	The parameter is invalid.	

Remarks	This command can be run only in scripts.
	Variable names are controlled separately for the cluster wide variable and the local variable. Thus, you can set both variables with one variable name. In this case, those are operated as two different variables.
	The local variable is valid until the ExpressCluster Server service of the server on which this command was run is terminated.
	The cluster wide variable is valid until the ExpressCluster Server services of all servers in a cluster are terminated.

# Monitoring errors on the connection to the shared resources (armwhshr command)

armwhshr.exe: the armwhshr.exe command monitors errors on the connection to the shared name.

### **Command line:**

armwhshr.exe share-name ip-addr [/INT time] [/LOG log-strings]


[/PROC exec-name parameter-1 parameter-2 ... parameter-n]

Description	This command monitors errors on the connection to the shared name.
	It checks if the ping is reached to the specified shared name server or monitors the connection error to the shared name. It registers the event
	log (ID:3514) when the ping is reached normally and an error occurred
	while connecting to the shared name.
	However, the event log is not registered when the connection error is already detected. It is registered when the status of connection changes from normal to error.
	With options, this command sends messages to the WebManager and starts specified executable files.

Parameter	share-name	Specifies a shared name (UNC name).
	ip-addr	Specifies the IP address of a server that possesses shared name.
	/INT time	Specifies monitoring interval (by the second). The range which can be specified is from 30 through 86400. This parameter is optional. When omitted, 180 (sec) is set for the interval.
	/LOG log-strings	Specifies the character string to be reported to the WebManager when an error occurs on the connection to a shared name. It is reported to the WebManager every time an error on the connection to the shared name is detected. Maximum of 111 bytes can be specified for the string. If the string includes spaces, enclose it in double quotation marks. When you use the double quotation marks in the strings, describe them with \ (\"). This parameter is optional.
	/PROC exec-name	Specifies the name of an executable file that is started when an error occurs on the connection to the shared name. The executable file is started when the status of shared name connection changes from normal to abnormal. This parameter is optional.
	parameter-n	This parameter is passed to the executable file. This parameter is optional.

Return Value	0	Success
	1	The parameter is invalid.
	2	Insufficient memory
	8	The ExpressCluster Server service has not been started.

How to use	When using the ARMWHSHR command, configure the following settings.			
	(1) Registering the user account Register the user account with an administrator right.			
	(2) Describing the ARMWHSHR command in scripts Create a new failover group for monitoring errors on the connection to the shared name(*), and describe the ARMWHSHR command in scripts.			
	* Setting a failover group  1. Add only one server to the <b>Servers that can run the Group</b> by clicking the <b>Startup Server</b> tab on the <b>Group Properties</b> .			
	For example, to monitor errors on the connection to the shared name (temp) of the server (server name: server public LAN IP address: 100.100.100.1), describe the following in the start script:			
	(Lines in the script that is run when CLP_EVENT is START) ARMLOAD watchID /U Administrator ARMWHSHR \\server\temp 100.100.100.1			
	Describe the following in the stop script (Lines in the script that is run when CLP_EVENT is START) ARMKILL watchID			



Server Information:		
	Server1	Server2
Server name	server1	server2
Public LAN IP address	100.100.100.1	100.100.100.2
Shared name	(1)share1	(1)share2
	(2)share3	
Script example		
(1) Start.bat of Server 1 IF "%CLP_EVENT%" == 'GOTO EXIT :NORMAL ARMLOAD W1 /U Admini :EXIT EXIT  (2) Stop.bat of Server 1 ARMKILL W1 EXIT		
(3) Start.bat of Server 2 IF "%ARMS_EVENT%" = GOTO EXIT :NORMAL ARMLOAD W2 /U Admini ARMLOAD W3 /U Admini :EXIT EXIT	istrator ARMWHSHR \\ser	ver1\share1 100.100.100.1
(4) Stop.bat of Server 2 ARMKILL W2 ARMKILL W3 EXIT		

Notes	This command can be specified only in scripts.
-------	--

# Controlling the applications or services started by the armload command (ExpressCluster Task Manager)


armaswth.exe: the armaswth.exe command lists applications or services started by the armload command in GUI.

#### **Command line:**

armaswth.exe

Description	This command lists the applications or services started by the armload command in GUI. In addition, it can start or stop the applications or services, and suspend or resume the monitoring in the same way as the armload command.	
Remarks	This command can be specified both in and outside scripts.	

### Screen image



#### Description:

Application/Service Name

Displays the names of applications or services started by the ARMLOAD command. Icons indicate the following status:

A: Application that is not monitored

Application that is being monitored

: Application that is not a monitoring target

S: Service that is not monitored

Service that is being monitored

Service that is not a monitoring target

Background colors of icons indicate the following status:

: Started / Being started

: Stopped / Being stopped

• Failover Group Name

Displays the group names that the started applications or services belong to

Type

Displays the types (application or service)

Running Status

Started: Application or service has started Stopped: Application or service has not started Starting: Application or service is being started

Stopping: Application or service is being stopped

• Monitoring status

Monitoring: Application or service is being monitored

Not monitoring: Application or service is not being monitored

Not monitored: Application or service is not a monitoring target (is not set as a monitoring target but started by the ARMLOAD command)

#### Sort


Click the fields of "Application/service name," "Failover group name," "WatchID," "Type," "Start status" and "Monitoring status" to sort the lists of each item (ascending / descending).

### Operation

Same as the ARMLOADC command, four operations of monitoring stop, monitoring resume, stop, start can be performed. Operations that can be performed vary depending on the status of the application or service start and the monitoring. For details, see "ARMLOADC command."


Select the application on the list (you cannot select multiple applications), and operate it by one of the following ways:

- Operation menu
- Toolbar
- Shortcut menu displayed by right-clicking the application name (shown below)



### Settings

To configure the settings, click **Settings** on the **Option** menu or on the toolbar.



### **Update Interval of Application/Service List**

Specify the interval to automatically update the application or service list by the second. The value from 0 through 3600 can be specified. When 0 is set, the list is not updated automatically. The default is 10 (seconds).

### **Timeout to stop Application/Service**

Specify the wait time to stop when stopping the application or service by the second. The value from 0 through 3600 can be specified. When 0 is set, the termination of the application or service is waited endlessly. The default is 40 (seconds). If the application or service is not stopped after the stop time is exceeded, the application is forcibly stopped. This setting is used only when the application or service is stopped by the ExpressCluster Task Manager.

### Shutting down the server (armdown command)

 $armdown.exe: \ \ \text{the armdown.exe} \ \ \text{command shuts down the server}.$ 

#### **Command line:**

armdown.exe [reboot | off | stop]

Description	This command stops the ExpressCluster service of the server on which
	this command is run, and shuts down the server.

Parameter	No parameter	Shuts down the server and turns off the power.
	reboot	Shuts down the server and reboots it. This parameter cannot be specified with "off" or "stop" parameter.
	off	Shuts down the server and turns off the power. This parameter cannot be specified with "off" or "stop" parameter.
	stop	Stops the ExpressCluster Server service without shutting down the server.
		This parameter cannot be specified with "reboot" or "off" parameter.

Return Value	0	Success (The server shutdown has started).	
	8 The ExpressCluster Server service is not running.		
	9	The parameter is invalid.	

Notes	Do not run this command directly from the start or stop script. When using this command from those scripts, prepare the batch file on which	
	the command is described, and then run the batch file on the start or stop script by writing "START <i>batch_file_name</i> " on it.	

Remarks	This command can be specified both in and outside scripts. When running this command on the start or stop script, follow the steps on Notes.
	To shut down whole cluster normally, run the armstdn command.

### Moving or failing over a group (armfover command)

armfover.exe: the armfover.exe command moves or fails over a group

#### **Command line:**

armfover.exe [/F] group\_name

Description	This command moves or fails over a group.
	A group is moved or failed over to a server other than the current one that is operating normally and has the highest priority.

Parameter	/F	Fails over a group.
		When this parameter is omitted, a group is moved.
		When a group is failed over, "FAILOVER" is set to the environment value of the start script "CLP_EVENT" on the destination server.
		When a group is moved, "START" is set to the environment value of the start script "CLP_EVENT" on the destination server.
	group_name	Specifies the name of the group to be moved or failed over.

Return Value	0	O Success (the group was moved or failed over).	
	7	The specified group has not been started.	
	8 The ExpressCluster Server service has not been started.		
	9	The parameter is invalid.	

Notes	Do not run this command directly from the start or stop script. When using this command from those scripts, prepare the batch file on which
	the command is described, and then run the batch file on the start or stop script by writing "START <i>batch_file_name</i> " on it.

Remarks	This command can be specified both in and outside scripts. When		
	running this command on the start or stop script, follow the steps on		
	Notes.		

### Starting a group (armgstrt command)

armgstrt.exe: the armgstrt.exe command starts a group

#### **Command line:**

armgstrt.exe group\_name [host\_name]

Description	This command starts a group on a specified server
-------------	---

Parameter	group_name	Specifies the name of a group to be started
	host_name	Specifies the name of a server on which a group is started. When this parameter is omitted, the server is determined according to a group failover policy.

Return Value	0	Success			
	1	The status on which the specified operation is not available. (checking if the shared disk is powered on or not)			
	7	The specified group has already been started.			
	8	The ExpressCluster Server service has not been started.			
	9	The parameter is invalid.			

Notes	Do not run this command directly from the start or stop script. When using this command from those scripts, prepare the batch file on which
	the command is described, and then run the batch file on the start or stop script by writing "START <i>batch_file_name</i> " on it.

Remarks	This command can be specified both in and outside scripts. When
	running this command on the start or stop script, follow the steps on
	Notes.

### **Stopping a group (armgstop command)**

 $armgstop.exe\hbox{: the armgstop.exe command stops a group}$ 

#### **Command line:**

armgstop.exe group\_name

Description	This command stops a group.						
Parameter	group_name Specifies the name of a group to be stopped.						
	1	T					
<b>Return Value</b>	0	Success					
	7	The specified	group has not been started.				
	8	The ExpressCluster Server service has not been started.					
	9	The parameter is invalid.					
	•						
Notes	Do not run this command directly from the start or stop script. When using this command from those scripts, prepare the batch file on which the command is described, and then run the batch file on the start or stop script by writing "START batch_file_name" on it.						
	•						
Remarks	This command can be specified both in and outside scripts. When running this command on the start or stop script, follow the steps on Notes.						

# Starting or stopping the application or service, suspending or resuming the monitoring (armloadc command)

armloadc.exe: the armloadc.exe command starts or stops the application or service, or suspends or resumes the monitoring.

#### **Command line:**

armloadc.exe watchID /W mode [/T time]

Description	This command starts or stops the application or service, or suspends or resumes the monitoring.
	This command terminates when the operations of starting or stopping the application or service is completed.

Parameter	watchID	This ID is for monitoring. Specify the ID used when the application or service is started by the ARMLOAD command.				
	/W mode	Controls the monitoring.  The following values can be specified for <i>mode</i> .				
		pause	Suspends the monitoring of the application or service.			
		continue	Resumes the monitoring of the application or service. When the application or service has terminated, the monitoring is resumed after a startup.			
		start	Starts the application or service.			
		stop	Terminates the application or service. When the application or service is being monitored, it is terminated after suspending the monitoring.			
	/T time	is specified When "co mode:  Specified parameter 0 through specified service omitted the control of the control	neter is valid when "continue," "start" or "stop" It to <i>mode</i> of /W <i>mode</i> .  Intinue" or "start" is specified to <i>mode</i> of /W less the wait time to start the service (this ter is invalid for the application). The value from gh 3600 (seconds) can be specified. When 0 is led, the command waits for the startup of the endlessly. This parameter is optional. When the command only starts the service and returns the trol without waiting for completion of start.			
		Specific from 0 0 is spe the app optiona	p" is specified to <i>mode</i> of /W <i>mode</i> : es the wait time to stop the service. The value through 3600 (seconds) can be specified. When cified, this command waits for the termination of lication or service endlessly. This parameter is l. When omitted, the command waits for am of 40 seconds.			

Return Value	0	Success			
	1	The status is invalid.			
	2	he application or service was not stopped.			
		(The application or service is being started or stopped)			
	7	An error occurred in WIN32API.			
	9	The parameter is invalid.			

Remarks	(1) This command can be specified both in and outside scripts.
	(2) To terminate the application, send WM_CLOSE message to the application. When the application is not terminated within the specified time (/T time), run TerminateProcess() to forcibly terminate the application process.
	(3) To start or stop the service, send requests for start or stop of the service to the service control manager (SCM). When the start or stop has not been completed within the specified time (/T time), the return value of 2 is returned.
	(4) Refer to the table below for the values that can be specified in <i>mode</i> . If <i>mode</i> is invalid, the return value of 1 is returned.

N	lotes	Before stopping the service (mode = stop), suspend the monitoring of watchID (mode=pause) which is monitoring the same service name, if
		any. A service error is detected (event ID=3506 - 3510) if the service is
		stopped without suspending the monitoring.

#### Application/Service specification matrix

Status	Monitoring				Suspending monitoring			
Mode	Started	Starting	Terminating	Terminated	Started	Starting	Terminating	Terminated
pause	0	0	Х	-	Х	Х	Х	Х
continue	Х	Х	Х	-	0	0	O (*2)	O (*2)
start	Х	Х	Х	-	Х	Х	Х	0
stop	O (*1)	0	Х	-	0	0	X	X

O: Executable X:Not executable (Invalid status) :This combination does not exist.

- (\*1) When "stop" is executed, monitoring of the application or service is suspended, and the application and service is stopped.
- (\*2) When "continue" is executed, the application and service is started, and monitoring of the application or service is resumed.

## Suspending the script execution until the user's direction (armpause command)

armpause.exe: the armpause.exe command displays the message box, and suspends the script execution until the user clicks the  $\mathbf{OK}$  button.

#### **Command line:**

armpause.exe msg\_strings

Description	This command displays the message box and suspends the script execution. When the user clicks the <b>OK</b> button on the message box, the script execution is resumed.					
Parameter	msg_stri	ings	Specifies the character string to be displayed on the message box. Maximum of 128 bytes can be specified.			
Return Value	0	Displaying the message was terminated.				
	9	The message cannot be displayed.  The parameter is invalid.				
Notes	To use this command in scripts, select <b>Allow service to interact with desktop</b> on the properties of the ExpressCluster Server service.					
Remarks	This command can be specified both in and outside scripts.					

## Suspending the script execution for the specified time (armsleep command)

armsleep.exe: the armsleep.exe command suspends the script execution until the specified time is exceeded.

#### **Command line:**

 $\verb|armsleep.exe| seconds| [/NOLOG]|$ 

Description	This command suspends the script execution until the specified time is
	exceeded.

Parameter	seconds	Specifies the time to suspend the script execution by the second.
	/NOLOG	When this parameter is specified, the execution of this command is not registered to the log file (arm.log).

Return Value	0	Success	
9		The parameter is invalid.	

Remarks	This command can be specified both in and outside scripts.
---------	--

## Starting the network sharing of the directory (armnsadd command)

armnsadd.exe: the armnsadd.exe command starts the network sharing of the directory.

#### **Command line:**

armnsadd.exe share\_name path

Description	This command starts the network sharing of the directory. This is the	
	same function as "net share shared_name=path_name."	

Parameter	share_name	Specifies the shared name of the network sharing to be started.
	path	Specifies the directory to be shared by entering full path.

Return Value	0	Success	
	1	The parameter is invalid.	
	2	The path name cannot be found.	
	3	The shared name is invalid.	
	5	No access right.	
	7	Insufficient memory.	
	8	Already shared by the same shared name.	
	9	Other error	

Remarks	This command can be specified both in and outside scripts.	
	When using the net share command, it waits for the entry on the console when the shared name of more than 8 characters is specified. Thus, it is not suitable to be used in scripts. In such a case, use this command instead of the net share command.	

## Stopping the network sharing of the directory (armnsdel command)

armnsdel.exe: the armnsdel.exe command starts the network sharing of the directory.

#### **Command line:**

armnsdel.exe share\_name

Description	This command stops the network sharing of the directory. This is the same function as "net share <i>shared_name</i> /delete."		
Parameter	share_name	Specifies the shared name of the network sharing to be stopped.	

Return Value	0	Success	
	1	1 The parameter is invalid.	
	5	The access was denied.	
	8	Insufficient memory	
	2310 The shared name cannot be found.		

Remarks	This command can be specified both in and outside scripts.		
	The net share command waits for the entry on the console depending on the status of connection to the clients when the network sharing is stopped. In such a case, use this command instead of the net share command. This command stops the network sharing regardless of the status of connection to the clients.		

## Setting the IP address returned by gethostbyname() (armwsset command)

armwsset.exe: the armwsset.exe command sets the IP address returned by the gethostbyname() executed on the local server.

#### **Command line:**

```
Format1 armwsset.exe [/P] path [ip_address ...]
Format2 armwsset.exe /L
Format3 armwsset.exe /DEL
```

Description	This command sets the IP address returned by the gethostbyname() executed on the local server.	
	Use this command when you want to return the virtual IP address as a local server's IP address that the application retrieves.	

	1	
Parameter	/P	If this parameter is specified, settings are not deleted at system reboot. The settings are maintained after the system is restarted.
		When this parameter is omitted, settings are deleted at system reboot.
	path	Specifies the full path to the executable file of the target application.
	ip_address	Specifies the IP address returned by the gethostbyname().
		More than one IP address can be specified by separating them by spaces.
		When multiple addresses are specified, those are set in the array returned by gethostbyname()in the described order.
		When this parameter is omitted, the settings of the application specified by <i>path</i> are deleted.
	/L	Lists the current settings.
	/DEL	Deletes all current settings.

Return Value	0	Success
	1	Failed to configure the settings.

#### Notes

The settings by this command function only when the application downloads wsock32.dll directly as a socket library. They do not function when the application uses ws2\_32.dll.

Run this command before starting the application.

To use this command, execute the following steps for each application in advance.

- (1) Copy wsock32.dll that is included with OS and stored in %SystemRoot%\system32 to the stored directory for the application program, and change the name to "wsock\_\_.dll."
- (2) Copy wsock32.dll stored in the **accessories** folder under the ExpressCluster installation directory to the stored directory of the application program.
- (3) Execute the steps above on all servers that run the application.

#### Remarks

This command can be specified both in and outside scripts.

## Setting or displaying the start delay time (armdelay command)

armdelay.exe: the armdelay.exe command sets or displays the delay time at the ExpressCluster service startup.

#### **Command line:**

armdelay.exe /N [seconds]

Description	This command sets or displays the delay time at startup of the
	ExpressCluster Server service or the ExpressCluster Disk Agent service.

Parameter	Parameter /N [seconds]	Sets or displays the delay time at startup of the ExpressCluster Server service or the ExpressCluster Disk Agent by the second. These services are started after the delay time is exceeded.
		For <i>seconds</i> , the value from 0 through 3600 can be specified.
		When <i>seconds</i> is omitted, the current setting values are displayed.

Return Value	0	Success	
	7 An error occurred in WIN32API.		
	9	The parameter is invalid.	

Remarks	This command can be specified only outside scripts.	
	The default value of the delay time immediately after the installation is 0 second.	
	The delay time specified by this command is valid until the ExpressCluster Server is uninstalled.	
	The delay time must be set for each server. The setting values are valid only on the server on which this command was run.	
	Normally, changing the delay time is not required. Setting the delay time is needed when using the ExpressCluster on the fault-tolerant servers such as NEC Express5800/ft series.	

## Setting or displaying operations at the occurrence of the emergency shutdown (armem command)

**armem.exe:** the armem.exe command sets or displays the operation mode at the occurrence of emergency shutdown.

#### **Command line:**

armem.exe /M [shutdown | reboot | poweroff]

Description	This command sets or displays the operation mode at the occurrence of
	the emergency shutdown.

Parameter	/M	Displays the current operation mode.
	/M shutdown	This parameter is for compatibility. It functions in the same way as the poweroff parameter.
	/M reboot	Reboots the server after shutdown.
	/M poweroff	Powers off the server after shutdown.

Return Value	0	Success	
	7	An error occurred in WIN32API.	
	9	The parameter is invalid.	

Remarks	This command can be specified only outside scripts.
	The default value of the operation mode immediately after the installation is "shutdown."
	The operation mode specified by this command is valid until the ExpressCluster Server is uninstalled.
	The operation mode must be set for each server. The setting values are valid only on the server on which this command was run.

## Shutting down the whole cluster (armstdn command)

armstdn.exe: the armstdn.exe command shuts down the whole cluster.

#### **Command line:**

armstdn.exe [reboot | off | stop]

Description	This command stops the ExpressCluster service in the whole cluster, and shuts down all servers.	
	shuts down an servers.	ı

Parameter	No parameter	Powers off the server after shutdown.
	reboot	Reboots the server after shutdown.
		This parameter cannot be specified with the <i>off</i> or <i>stop</i> parameter.
	off	Powers off the server after shutdown.
		This parameter cannot be specified with the <i>reboot</i> or <i>stop</i> parameter.
	stop	Stops only the ExpressCluster Server service without shutting down the server.
		This parameter cannot be specified with the <i>reboot</i> or <i>off</i> parameter.

Return Value	0	Success	
	8	The ExpressCluster Server service is not running.	
	9	The parameter is invalid.	

Notes	Servers which cannot be communicated from the server on which this command was run are not shut down.
	Do not run this command while activating a group. Since a group cannot be inactivated while being activated, an emergency shutdown is executed.

Remarks	This command can be specified only outside scripts.
---------	---

## Returning the server with the status of "Suspension (isolated)" (armmode command)

armmode.exe: the armmode.exe command returns the server whose status is "Suspension (isolated)" to the normal status.

#### **Command line:**

armmode.exe [/F]

Description	This command returns the server whose status is "suspension (isolated)" to the normal status.
	Run this command on the server whose status is "suspension (isolated)."

Parameter	No parameter	Returns the server
	/F	This parameter is for compatibility.
		When specified, the command functions in the same way when no parameter is specified.

Return Value	0	Success
	1	The status of the server is not "Suspension (isolated)."
	8	The ExpressCluster Server service is not running.
	9	The parameter is invalid.

Remarks	This command can be specified only outside scripts.
	When the server did not shut down normally, the status of the server becomes "Suspension (isolated)" at the next server startup. On the server of that status, activating a group is prohibited. Activating a group becomes possible after returning the server to the normal status by this command.

## Permitting an access to the mirror disk (mdopen command)

mdopen.exe: the mdopen.exe command permits an access to the mirror disk.

#### **Command line:**

mdopen.exe mirrordisk\_alias

Description	Normally, the mirror disk is accessible only when the resource is activated. In other cases the access is prohibited.	
	This command permits the access to the inactivated mirror disk.	

Parameter	_	Specifies the mirror disk resource name to which
		you want to permit the access.

Return Value	0	Success
	1	The parameter is invalid.
	2	The mirroring is in progress. The access cannot be permitted.
	3 or	Other error (possible causes are described below)
	larger	The Replicator/Replicator DR is not used.
		There is a task accessing the target mirror disk resource.
		Internal error

Notes	When accessing the mirror disk is permitted by using this command, be sure to prohibit the access using the mdclose command before recovering
	the mirror.

Remarks	This command can be specified only outside scripts.
	This command is available only when the Replicator/Replicator DR is used.
	This command is for executing the snapshot backup by a batch processing. For details on the snapshot backup, see "Section III Maintenance" in this guide.

## Prohibiting an access to the mirror disk (mdclose command)

mdclose.exe: the mdclose.exe command prohibits an access to the mirror disk.

#### **Command line:**

mdclose.exe mirrordisk\_alias

Description	This command prohibits the access to the mirror disk that is permitted by the mdopen command.
	Do not run this command when there is no task accessing the specified mirror disk resource.

Parameter	mirrordisk_alias	Specifies the name of a mirror disk resource to
		which you want to prohibit the access.

Return Value	0	Success	
	<ol> <li>The parameter is invalid.</li> <li>or Other error (possible causes are described below)</li> </ol>		
	larger	The Replicator/Replicator DR is not used.	
		There is a task accessing the target mirror disk resource.	
		Internal error	

Notes	When accessing the mirror disk is permitted using the mdopen command, be sure to prohibit the access using this command before recovering the mirror.
	recovering the minor.

Remarks	This command can be specified only outside scripts.	
	This command is available only when the Replicator/Replicator DR is used.	
This command is for executing the snapshot backup by a batch processing. For details on the snapshot backup, see "Section III Maintenance" in this guide.		

## Permitting an access to the shared disk (sdopen command)

sdopen.exe: the sdopen.exe command permits an access to the shared disk

#### **Command line:**

sdopen.exe disk\_resource\_name

Description	In general, the shared disk is accessible only when the disk resource is activated. In other cases the access is prohibited.
	This command permits the access to the inactivated disk resource.

Parameter	disk_resource_name	Specifies the disk resource name to which you
		want to permit the access.

Return Value	0	Success
	1	The parameter is invalid.
	3 or	Other error (possible causes are described below)
	larger	Invalid HBA settings
		Invalid drive letter settings
		Internal error

Notes	Make sure that the disk resource is inactivated before using this command. If this command is executed in the state that the disk resource is activated, data on the shared disk may be corrupted.
	When access to the shared disk is permitted by using this command, be sure to prohibit the access by using the sdclose command before activating the disk resource. If the disk resource us activated in the state where the access is not prohibited, data on the shared disk may be corrupted.

Remarks	This command can be used only outside scripts.
---------	--

## Prohibiting an access to the shared disk (sdclose command)

sdclose.exe: the sdclose command prohibits an access to the shared disk

#### **Command line:**

sdclose.exe disk\_resource\_name

Description	This command prohibits accesses to the disk resource that are permitted	
	by the sdopen command.	

Parameter	disk_resource_name	Specifies the disk resource name to which you	
		want to prohibit the access.	

Return Value	0	Success
	1	The parameter is invalid.
	3 or larger	Other error (possible causes are described below)  • Invalid HBA settings
		Internal error

Notes	When accessing the disk resource is permitted by using the sdopen command, be sure to prohibit the access by using this command before activating the disk resource.
-------	--

Remarks	This command can be used only outside scripts.
---------	--

### Error messages of the compatible commands

Message	Description	Solution
armbcast succeeded.	armbcast succeeded.	-
armbcast has received an invalid parameter.	armbcast received an invalid parameter.	Specify the valid input parameter.
armbcast failed in the internal processes (1%03d). The error code is 0x%x.	armbcast T failed in the internal processing.	Check if the memory is sufficient and/or OS is stable.
Cannot execute armbcast.	armbcast cannot be executed.	armbcast cannot be used when the arms_event of the start script is in the recover status. This is because the server is recovering the cluster.
armcall succeeded. command name=%.16s.	armcall succeeded.	-
armcall has received an invalid parameter.	armcall received an invalid parameter.	Specify an valid input parameter.
armcall failed to lock the file.	armcall failed to acquire the privilege to write lock for exclusive access control.	Check if the memory is sufficient and/or OS is stable.
armcall received a console close signal. The server will be shut down.	The server was shut down because the armcall console window was closed by a user's request.	-
armcall failed in the internal processes ("%03d"). The error code is 0x%x.	armcall failed in the internal processing.	Check if the memory is sufficient and/or OS is stable.
armcall failed to execute the command line. The error code is 0x%x.	Execution of exec-name specified in the command line of armcall failed.	Check if the valid values are specified for the path name, file name and parameter-n in the command lines.
armdown succeeded. option=%s.	armdown succeeded.	-
armdown has received an invalid parameter. option=%s.	armdown received an invalid parameter.	Specify an valid input parameter.
armdown shuts down the server. option=%s.	armdown started a server shutdown.	-
armdown cannot execute specified action. option=%s	armdown cannot be executed.	The server may have failed. Check it.
armdown failed in the internal processes (%03d). The error code is 0x%x.option=%s	armdown failed in the internal processing.	Check if the memory is sufficient and/or OS is stable.
armem succeeded.mode=%s.	armem succeeded.	-
armem has received an invalid parameter.	armem received an invalid parameter.	Specify a valid input parameter.
armdown failed in the internal processes (%04d). The error code is 0x%x.option=%s	armem failed in the internal process.	Check if the memory is sufficient and/or OS is stable.
armforver succeeded. option=%s group-name=%s	armforver succeeded.	-
armforver has received an invalid parameter. option=%s group-name=%s	armforver received an invalid parameter.	Specify a valid input parameter.
Cannot execute armfover . option=%s group-name=%s	armforver cannot be executed.	Check if the failover group is being stopped or is already stopped.

Message	Description	Solution
armfover failed in the internal processes (1%03d). The error code is 0x%x.option=%s.group-name=%s.	armforver failed in the internal process.	Check if the memory is sufficient and/or OS is stable.
armgetcd succeeded.	armgetcd succeeded.	-
armgetcd has received an invalid parameter.	armgetcd received an invalid parameter.	Specify a valid input parameter.
armgetcd received a consol close signal. The server will be shut down.	The server was shut down. This is because the console window of armgetcd was closed by a user's request.	-
armgetcd failed in the internal processes ("%03d"). The error code is 0x%x.	armgetcd failed in the internal process.	Check if the memory is sufficient and/or OS is stable.
armgstrt succeeded. group-name=%s.server-name=%s.	armgstrt succeeded.	-
armgstrt has received an invalid parameter.group-name=%s.server-name=%s.	armgstrt received an invalid parameter.	Specify a valid input parameter.
armgstrt failed in the internal processes (1%03d). The error code is 0x%x.group-name=%s.server-name =%s.	armgstrt failed in the internal process.	Check if the memory is sufficient and/or OS is stable.
armgstrt cannot execute the specified operation. group-name=%s server=%s	armgstart is not in the status to execute the specified operation.	The failover group is being started or it has been started, or the server may not be operating successfully. Check them.
armgstop succeeded. group-name=%s	armgstop succeeded.	-
armgstop has received an invalid parameter. group-name=%s	armgstop received an invalid parameter.	Specify a valid input parameter.
armgwait succeeded.	armgwait succeeded.	-
armgwait has received an invalid parameter.	armgwait received an invalid parameter.	Specify a valid input parameter.
armgwait timed out.	armgwait timed out.	Check the target failover group name.
armgwait failed to run the internal processes (1%03d). The error code is 0x%x.	armgwait failed in the internal process.	Check if the memory is sufficient and/or OS is stable.
armkill (WID="%0.16s") succeeded.	armkill succeeded.	-
armkill has received invalid WID ("%0.10s") as a parameter.	armload is not executed by the specified WID.	Check the command line (watcID) of the armload.
armkill has received an invalid parameter.	armkill received an invalid parameter.	Specify a valid input parameter.
armkill (WID="%0.16s") forcefully terminated application.	The application was forcefully terminated because it did not end within a designated time period.	Examine the application to find why it did not terminate within the designated time period.
armkill (WID="%0.16s") could not forcefully terminated application.	The application was forcefully terminated, because it did not end within a designated time period. However the forced termination failed.	Same as above
armkill (WID="%0.16s") could not stop the service.	The service did not end within the specified time period.	Examine the service to find why it did not end within the specified time period.

Message	Description	Solution
armkill (WID="%0.16s") has failed in the internal processes (3%03d). The error code is 0x%x.	armkill failed in the internal process.	When the "internal process" is 3060, the application is already closed. Examine the application to find why it ended.  If not above, check if the memory is sufficient and/or OS is stable.
armkill (WID="%0.32s") failed to stop the service. Detailed information:%0.160s	Armkill failed to stop the service.	The request to stop the service that was asked to the service control manager failed. Investigation needs to be conducted in the service.
armload (WID="%0.16s") succeeded.	armload succeeded.	-
armload has received invalid WID ("%0.16s") as an invalid parameter.	WID is overlapped.	Specify a unique WID.
armload has received an invalid parameter.	armload received an invalid parameter.	Specify an valid input parameter.
armload (WID="%0.16s") has reached the maximum number of processes that can be run simultaneously.	An attempt to start up applications/services more than executable number of applications/servers (256) was made	Create scripts to make the number of running applications/ services within 256.
armload has received WID ("%0.16s") that exceeds the maximum character count as a parameter.	The character string of WID has more than 256 characters	Make the character string of WID to have up to 255 characters.
armload(WID="%0.16s") detected the service starting time-out.	The service did not end within a designated time period.	Examine the service to find why it did not end within the designated time period.
armload (WID="%0.16s") failed in the internal processes(1%03d). The error code is 0x%x.	armload failed in the internal processes.	Check if the memory is sufficient and/or OS is stable.
armpoll has received an invalid parameter.	Command monitoring process received an invalid parameter.	Check if the memory is sufficient and/or OS is stable.
armpoll (WID="%0.16s") detected extinction of the application. The stop code is %d.	Command monitor process did not detect any application.	Detected an application termination. Examine the application to find why it ended.
armload (WID="%0.16s") couldn't log on to user ("%0.32s"). The error code is 0x%x.	Failed to log on to the user account.	Check user account registration information (user ID, password), and if the domain name is indicated, also check the domain name in NEC ExpressCluster manager.
armload (WID="%0.16s") failed to execute the command line. The error code is 0x%x.	Failed to start the application.	Check if the valid path name and file name are specified in the exec-name of the armload command line. Check if a valid value is specified to the parameter-n.
armload (WID="%0.16s") could not log on to user ("%0.32s"). The error code is 0x%x.	Failed to acquire a password of a user account.	Check if the user account registration is done in NEC ExpressCluster manager .
armload (WID="%0.16s") could not log on to user ("%0.32s"). The error code is 0x%x.	Command monitoring process failed in internal processing.	Check if the memory is sufficient and/or OS is stable.
Command monitor process (WID="%0.16s") detected a failure in the services. The stop code is %d & %d.	Command monitor process detected a failure of the service.	Detected service termination. Examine the service to find it terminated.

Message	Description	Solution
Command monitor process (WID="%0.16s") failed to get the environmental variable name.	Command monitor process failed in acquiring an environmental variable name.	It may have been started from outside of the scripts Start from outside of script is not supported.  If not above, check if memory is sufficient, and/or OS is stable.
Command monitor process (WID="%0.16s") restarted script.	Command monitor process restarted scripts.	Due to detection of application/service termination, the scripts restarted.
Command monitor process (WID="%0.16s") restarted application.	Command monitor process restarted the application.	Due to detection of termination of the application, the application restarted.
Command monitor process (WID="%0.16s") restarted Service	Command monitor process restarted the service	Due to detection of termination of the service, the restarted.
Command monitor process (WID="%0.16s") completed the failover of the group ("%0.10s").	Command monitor process performed a failover to the group.	Due to detection of application/service termination, the failover group failed over.
Command monitor process (WID="%0.16s") shut down the server.	Command monitor process shut down the server.	Due to detection of application/service termination, the server shut down.
armpoll (WID="%0.16s") has received an invalid service name ("%0.10s") as a parameter.	armload received an invalid service name as a parameter.	In the armload command line, check if the valid service name is specified for service-name. Check if the valid value is designated for parameter-n as well.
armload (WID=""%0.16s"") failed to get user (""%0.32s"") information. The user name may be incorrect. The error code is 0x%x.	Failed to acquire a domain name from the user name.	Check if the user name is registered in the system.
armpoll (WID="%0.16s") detected extinction of the application.	Command monitor process did not detect any application (Failed to acquire the application termination code of the application).	Detected termination of an application. Examine the application to find why it terminated.
armload (WID="%0.16s") failed to start the service. The error code is 0x%x.	Failed to start the service.	Examine the service to find why it failed to start.
Command monitor process (WID="%0.16s") failed to fail over the group(%s). The error code is 0x%x.	Command monitor process failed to failover the group.	Check if the failover destination server is operating successfully as a cluster.
Command monitor process (WID="%0.32s") failed to stop the service. Detailed information:%0.160s	Command monitor process failed to stop the service.	The service stop request for the service control manager failed. Examine the service.
Command monitor process (WID="%0.16s") forcefully terminated the application.	Command monitor process forced to finish the application.	The application was forcefully terminated by TerminateProcess() because it could not end within the specified time period. Check the application.
Command monitor process (WID="%0.16s") failed to forcefully terminate the application.	Command monitor process failed to finish the application.	The application could not end within the specified time period due to the WM_CLOSE message. An attempt to forcefully terminate by the TerminateProcess() was made. However it did not end. Check the application.

Message	Description	Solution
Command monitor process (WID="%0.16s") failed to stop Service.	Command monitor process failed to stop Service.	Service did not end within the specified time period. Check the Service.
armloadc succeeded.WatchID=%0.16s.mode =%s.time=%s.	armloadc succeeded.	-
armloadc received an invalid parameter. WatchID=%0.16s.mode=%s.time=%s.	armloadc received an invalid parameter.	Specify a valid input parameter.
Cannot execute armloadc. WatchID=%0.16s.mode=%s.time= %s.	armloadc cannot be executed.	Check "startup state" and "monitoring state" by NEC ExpressCluster task manager. Check whether or not armloadc can be executed by referring to application/service specification matrix of command reference (armloadc).
armloadc detected time-out while waiting to start/stop the application/service. WatchID=%0.16s mode=%s time=%s	Application/service did not end within the designated time period.	Examine the application/service to find why it did not end within the designated time period.
armloadc Win32API error.WatchID=%0.16s.mode=%s.ti me=%s.	armloadc failed in the internal processing.	Check if the memory is sufficient and/or OS is unstable.
armmode succeeded.option=%s.	armmode succeeded.	-
armloadc received an invalid parameter. WatchID=%0.16s.mode=%s.time= %s.	armloadc received an invalid parameter.	Specify a valid input parameter.
armmode cannot execute the specified action (%03d). option=%s.	armmode cannot execute the specified operation.	Force-return (/F) :
		Some servers are not isolated. Check the servers. Server isolation (/I):
		The local server is not operating successfully in the cluster. Or there are no two or more servers that are working successfully in the cluster. Check the servers.  Server isolation (/I):
		The local server is not operating successfully in the cluster. Check the server.
armmode failed in the internal processes(%03d).The error code is 0x%x.option=%s.	armmode failed in the internal processing.	Check if the memory is sufficient and/or OS is stable.
armnsadd succeeded (share=%.80s,path=%.80s).	armnsadd succeeded.	-
armnsadd has received an invalid parameter.	armnsadd received an invalid parameter.	Specify a valid input parameter.
armnsadd failed to run the internal processes (1%03d). The error code is 0x%x.	armnsadd failed in the internal processing.	If the internal process is 1020, the shared name has more than 80 characters. Specify it within 80 characters.

Message	Description	Solution
Message	Description	If the internal process is 1040, the path name is invalid. Check the path name.  If the internal process is 1050, the shared name is invalid. Check if you did not use characters that cannot be specified for shared names.  If the internal process is 1060, you do not have the privilege to access the path name. Check the access privilege.  If the internal process is 1090, the same name is already used. Specify a shared name that does not overlap with others.  If not above, check if the memory is sufficient, and/or OS
		is stable.
armnsdel succeeded (share=%.80s).	armnsdel succeeded.	-
armnsdel has received an invalid parameter.	armnsdel received an invalid parameter.	Specify a valid input parameter.
armnsdel failed to run the internal processes (1%03d). The error code is 0x%x.	armnsdel failed in the internal processing.	If the internal process is 1030, you do not have the privilege to access the shared name. Check the access privilege.  If the internal process is 1060, the shared name cannot be found. Check the name.  If not above, check if the memory is sufficient, or OS is stable.
armpause succeeded.	armpause succeeded.	-
armpause has received an invalid parameter.	armpause received an invalid parameter.	Specify a valid input parameter.
armpause cannot display the message.	armpause cannot display dialog messages.	Check if the memory is sufficient and/or OS is stable.
armsetcd succeeded.	armsetcd succeeded.	-
armsetcd has received an invalid parameter.	armsetcd received an invalid parameter.	Specify a valid input parameter.
armsetcd received a consol close signal. The server will be shut down.	server shutdown was executed because armsetcd console window was closed by user's request.	-
armsetcd failed in the internal processes ("%03d"). The error code is 0x%x.	armsetcd failed in the internal processing.	Check if the memory is sufficient And/or OS is stable.
armsleep succeeded.	armsleep succeeded.	-
armsleep has received an invalid parameter.	armsleep received an invalid parameter.	Specify a valid input parameter.
armstdn failed in the internal processes(%03d).The error code is 0x%x.option=%s.	armstdn failed in the internal processing.	Check if the memory is sufficient and/or OS is stable.
armstdn succeeded.cmd=%s	armstdn succeeded.	-
Failed to shut down the cluster. The server is not operating as a cluster.	Failed to acquire a cluster name.	The server is not operating as cluster. Check it.

Message	Description	Solution
Failed to shut down the cluster. The error code is 0x%x.	armwhshr failed in internal processing.	Check if the memory is sufficient and/or OS is stable.
Failed to shut down the cluster. ExpressCluster Server Service is not started.	"The ExpressCluster Server" service is not started.	"The ExpressCluster Server" service is not started. Check it.
armwhshr has received an invalid parameter.	armwhshr received an invalid parameter.	Specify a valid input parameter.
armwhshr failed in the internal processes(1%03d). The error code is 0x%x.	armwhshr failed in the internal processing.	Check if the memory is sufficient and/or OS is stable.
armwhshr detected connection error to share-name(%.48s).The error code is 0x%x.	armwhshr detected error in connection to the shared name.	The shared name cannot be used. Recover devices that are associated to the shared name.  1.OS is unstable. Check it.
		Make sure that power is supplied to the devices.
		3. Make sure that the devices and the servers are connected properly.
armwhshr detected connection recovery to shared name(%.48s). The error code is 0x%x.	rmwhshr detected recovery of connection to the shared name.	-
mdopen failed. An internal error occurred.	mdopen failed. An internal error occurred.	Check if the memory is sufficient and/or OS is stable.
mdopen failed. The resource is busy.	mdopen failed. The resource is busy.	Retry later.
mdopen failed. A network error occurred.	mdopen failed. A network error occurred.	Check how the interconnect is connected.
mdopen failed. Cannot establish the mirror disk connection.	mdopen failed to establish the communication of the mirror disk.	Check if the cluster configuration data is valid.
mdopen failed. The resource name is invalid.	mdopen failed. The resource name is invalid.	Check if the cluster configuration data is valid.
mdopen failed. The status is invalid.	mdopen failed. The status is invalid.	Mirror recovery is required.
mdopen failed. The resource is not initialized.	mdopen failed. The resource is not initialized.	Check if the partition is allocated, the disk is recognized by OS and the cluster configuration data is correct.
mdopen failed. The resource is not performed first mirror construction.	mdopen failed. Initial mirror construction is not done for resources.	Initial mirror construction is required.
mdopen failed. Cannot lock the mirror disk.	mdopen failed to lock the mirror disk.	Check if the memory is sufficient and/or OS is stable.
mdopen failed. The license is not registered.	mdopen failed. The license is not registered.	Register the license.
mdopen failed. The trial version has expired.	mdopen failed. The trial version has expired.	Register the license.
mdopen failed. The license authentification failed.	mdopen failed. The license authentification failed.	Register the license.
mdopen failed. Cannot find the history folder.	mdopen failed. The history folder cannot be found.	Check if the cluster configuration data is correct.
mdopen failed. The mirror connect is not initialized.	mdopen failed. The mirror connect is not initialized.	Check the connection status of the mirror connect. Check if the cluster configuration data is correct.

Message	Description	Solution
mdopen failed. Cannot find the partition specified for the cluster partition.	mdopen failed. The partition specified for the cluster partition cannot be found.	Check if the partition is allocated and the disk is recognized by OS.
mdopen failed. Cannot find the partition specified for the data partition.	mdopen failed. The partition specified for the data partition cannot be found.	Check if the partition is allocated and the disk is recognized by OS.
mdopen failed. Cannot change the drive letter for the cluster partition.	mdopen failed. The drive letter for the cluster partition could not be changed.	Check the specification of the drive letter of the cluster configuration data. Make sure that the drive letter is not used by any other partitions.
mdopen failed. Cannot change the drive letter for the data partition.	mdopen failed. The drive letter for the data partition could not be changed.	Check the specification of the drive letter of the cluster configuration data. Make sure that the drive letter is not used by any other partitions.
mdopen failed. The server name is invalid.	mdopen failed. The server name is invalid.	Check if the cluster configuration data is correct.
mdopen has received an invalid parameter.	mdopen received an invalid parameter.	Specify a valid input parameter.
mdopen failed in the internal processes(%2). The error code is %3.	mdopen failed in the internal processing.	Check if the memory is sufficient and/or OS is stable.
mdopen succeeded. The mirror disk resource is %2.	mdopen succeeded.	-
mdclose failed. An internal error occurred.	mdclose failed. An internal error occurred.	Check if the memory is sufficient and/or OS is stable.
mdclose failed. The resource is busy.	mdclose failed. The resource is busy.	Retry it later.
mdclose failed. A network error occurred.	mdclose failed. A network error occurred.	Check the connection status of the interconnect.
mdclose failed. Cannot establish the mirror disk connection. mdclose failed. The resource name is invalid.	mdclose failed to establish the mirror disk connection. mdclose failed. The resource name is invalid.	Check if the cluster configuration data is correct.  Check if the cluster configuration data is correct.
mdclose failed. The status is invalid.	mdclose failed. The status is invalid.	Mirror recovery is required.
mdclose failed. The resource is not initialized.	mdclose failed. The resource is not initialized.	Check if the partition is allocated, if the disk is identified by OS and if the cluster configuration data is correct.
mdclose failed. The resource has not performed initial mirror construction.	mdclose failed. The initial mirror construction has not been done for the resource.	Initial mirror construction is required.
mdclose failed. Cannot lock the mirror disk.	mdclose failed to lock the mirror disk.	Check if the memory is sufficient and/or OS is stable.
mdclose failed. The license is not registered.	mdclose failed. The license is not registered.	Register the license.
mdclose failed. The trial version has expired.	mdclose failed. The trial version has expired.	Register the license.
mdclose failed. The license authentification failed.	mdclose failed. The license authentification failed.	Register the license.
mdclose failed. Cannot find the history folder.	mdclose failed to find the history folder.	Check if the cluster configuration data is correct.
	Everone Cluster V 2 2	1 for Windows Reference Guide

Message	Description	Solution
mdclose failed. The mirror connect is not initialized.	mdclose failed. The mirror connect is not initialized.	Check the connection status of the mirror connect. Check if the cluster configuration data is correct.
mdclose failed. Cannot find the partition specified for the cluster partition.	mdclose failed to find the partition specified for the cluster partition.	Check if the partition is allocated and if the disk is identified by OS.
mdclose failed. Cannot find the partition specified for the data partition.	mdclose failed to find the partition specified for the data partition.	Check if the partition is allocated and if the disk is identified by OS.
mdclose has received an invalid parameter.	mdclose received an invalid parameter.	Specify a valid input parameter.
mdclose failed in the internal processes(%2). The error code is %3.	mdclose failed in the internal processing.	Check if the memory is sufficient and OS is stable.
mdclose succeeded. The mirror disk resource is %2.	mdclose succeeded.	-
sdopen succeeded. (%2)	sdopen succeeded.	-
sdopen failed. Internal error occurred. (%1)	sdopen failed. Internal error occurred.	Check if the memory and/or the resource of OS are sufficient.
sdopen failed. Failed to load cluster configuration data. (%1)	sdopen failed to load cluster configuration data.	Check if the cluster configuration data exists in the place it should be.
sdopen failed. Failed to unload cluster configuration data. (%1)	sdopen failed to unload cluster configuration data.	Check if the cluster configuration data exists in the place it should be.
sdopen failed. Failed to get cluster configuration data. (%1)	sdopen failed to acquire the cluster configuration data.	Check if the cluster configuration data is correct.
sdopen failed. Failed to allocate memory. (%1)	sdopen failed to allocate memory.	Check if the memory and/or the resource of OS are sufficient.
sdopen failed. Failed to activate resource. (%1)	sdopen failed to activate resource.	Check if the setting of HBA is correct.
sdopen failed. Failed to create thread. (%1)	sdopen failed to create thread.	Check if the memory and/or the resource of OS are sufficient.
sdopen failed. Timeout occurred on thread. (%1)	sdopen failed. Timeout occurred on thread.	Check if the memory and/or the resource of OS are sufficient.
sdopen failed. Failed to dismount the partition specified by the resource. (%1)	sdopen failed to dismount the partition specified by the resource.	The partition may be being used. Check it.
sdopen failed. Failed to lock the partition specified by the resource. (%1)	sdopen failed to lock the partition specified by the resource	The partition may be being used. Check it.
sdopen failed. Server does not exist in cluster configuration data. (%1)	sdopen failed. The server does not exist in cluster configuration data.	Check if the server exists in the cluster configuration data.
sdopen failed. Resource does not exist in cluster configuration data. (%1)	sdopen failed. The resource does not exist in cluster configuration data.	Check if the resource exists in the cluster configuration data.
sdopen failed. Cannot find the specified partition. (%1)	sdopen failed to find the specified partition.	Check if the specified partition is recognized by OS.
sdopen failed. Cannot change the drive letter. (%1)	sdopen failed to change the drive letter.	Check if the specified drive letter is not used in other partitions.
sdclose succeeded. (%2)	sdclose succeeded.	-
sdclose failed. Internal error occurred. (%1)	sdclose failed. Internal error occurred.	Check if the memory and/or the resource of OS are sufficient.

Message	Description	Solution
sdclose failed. Failed to load cluster configuration data. (%1)	sdclose failed to load cluster configuration data.	Check if the cluster configuration data exists in the place it should be.
sdclose failed. Failed to unload cluster configuration data. (%1)	sdclose failed to unload cluster configuration data.	Check if the cluster configuration data exists in the place it should be.
sdclose failed. Failed to get cluster configuration data. (%1)	sdclose failed to acquire the cluster configuration data.	Check if the cluster configuration data is correct.
sdclose failed. Failed to allocate memory. (%1)	sdclose failed to allocate memory.	Check if the memory and/or the resource of OS are sufficient.
sdclose failed. Failed to deactivate resource. (%1)	sdclose failed to deactivate resource.	Check if the setting of HBA is correct.
sdclose failed. Failed to create thread. (%1)	sdclose failed to create thread.	Check if the memory and/or the resource of OS are sufficient.
sdclose failed. Timeout occurred on thread. (%1)	sdclose failed. Timeout occurred on thread.	Check if the memory and/or the resource of OS are sufficient.
sdclose failed. Failed to dismount the partition specified by the resource. (%1)	sdclose failed to dismount the partition specified by the resource.	The partition may be being used. Check it.
sdclose failed. Failed to lock the partition specified by the resource. (%1)	sdclose failed to lock the partition specified by the resource.	The partition may be being used. Check it.
sdclose failed. Server does not exist in cluster configuration data. (%1))	sdclose failed. Server does not exist in cluster configuration data.	Check if the server exists in the cluster configuration.
sdclose failed. Resource does not exist in cluster configuration data. (%1)	sdclose failed. The resource does not exist in cluster configuration data.	Check if the resource exists in the cluster configuration.
sdclose failed. Cannot find the specified partition. (%1)	sdclose failed to find the specified partition.	Check if the specified partition is recognized by OS.

### Section II Resource details

This section provides detailed information on the resources that constitute a cluster.

- Chapter 6 Group resource details
- Chapter 7 Monitor resource details
- Chapter 8 Heartbeat resources
- Chapter 9 Details on network partition resolution resources
- Chapter 10 Other monitor settings

### **Chapter 6 Group resource details**

This chapter provides information on group resources that constitute a failover group. For overview of group resources, see Chapter 2, "Design a system configuration" in the *Installation and Configuration Guide*.

#### This chapter covers:

•	Group resources ·····	.394
•		. 395
•	Displaying and changing the settings of group properties	·412
•	Displaying and changing the settings of group resources	417
•		427
•		439
•	Understanding mirror disk resources	447
•	Understanding registry synchronization resources	463
•		470
•	Understanding disk resources	499
•	Understanding service resources	. 503
•		. 509
•	Understanding virtual computer name resources	.513
•	Understanding virtual IP resources	. 523
•	Understanding CIFS resources	. 535
•	Understanding NAS resources	. 541
•	Understanding hybrid disk resources	. 5/15

### **Group resources**

Currently supported group resources are as follows:

Group resource name	Abbreviation	Functional overview	
Application resources	appli	Refer to "Understanding application resources" on page 432.	
Floating IP resources	fip	Refer to "Understanding floating IP resources" on page 439.	
Mirror disk resources	md	Refer to "Understanding mirror disk resources" on page 447.	
Registry synchronization resources	regsync	Refer to "Understanding registry synchronization resources" on page 463.	
Script resources	script	Refer to "Understanding script resources" on page 470.	
Disk resources	sd	Refer to "Understanding disk resources" on page 499.	
Service resources	service	Refer to "Understanding service resources" on page 503.	
Print spooler resources	spool	Refer to "Understanding print spooler resources" on page 509.	
Virtual computer name resources	vcom	Refer to "Understanding virtual computer name resources" on page 513.	
Virtual IP resources	vip	Refer to "Understanding virtual IP resources" on page 523.	
CIFS resources	cifs	Refer to "Understanding CIFS resources" on page 535.	
NAS resources	nas	Refer to "Understanding NAS resources" on page 541.	
Hybrid disk resource	hd	Refer to "Understanding hybrid disk resources" on page 545.	

### What is a group?

A group is a unit to perform a failover. Up to 128 group resources can be registered for each group. Rules regarding to operations at failover (failover policies) can be set per group.

The properties that can be set on each group are described below:

#### Servers that can run the Group

Select and set the servers that can run the group from the servers that configure a cluster. Specify the order of priority to the servers that can run the group for running the group.

#### **Startup Attribute**

Sets the startup attribute of a group to the auto startup or manual startup.

In the case of the auto startup, when a cluster is started, a group is started up automatically on the server that has the highest priority among the servers that can run the group.

In the case of the manual startup, a group is not started even when a server is started up. After starting the server, start up the group manually by using the WebManager or the clpgrp command. For details on the WebManager, see Chapter 1, "Functions of the WebManager." For details on the clpgrp command, see Chapter 4, "ExpressCluster command reference."

#### **Failover Exclusive Attribute**

Sets the failover exclusive attribute of the group at failover. The following shows the failover exclusive attributes.

#### Off

Exclusion is not performed at failover. Failover is performed on the server of the highest priority among the servers that can fail over.

#### **Normal**

Exclusion is performed at failover. Failover is performed on the server on which the other normal exclusion groups are not started and which is given the highest priority among the servers that can run the group.

However, if the other normal exclusion groups have already been started on all servers that the failover can be performed, exclusion is not performed. Failover is performed on the server that is given the highest priority among the servers on which failover can be performed.

#### Absolute

Exclusion is performed at failover. Failover is performed on the server on which the other normal exclusion groups are not started and which is given the highest priority among the servers that can run the group.

However, failover is not performed if the other absolute exclusion groups have already been started on all servers on which failover can be performed.

#### Note:

Exclusion is not performed to the normal and absolute exclusion groups. Normal exclusion is performed only among the normal exclusion groups. Absolute exclusion is performed only among the absolute exclusion groups. In either case, exclusion is not performed with the no-exclusion group. For details on the failover exclusive attribute, see "Understanding failover policy."

#### - Failover Attribute

Set either auto failover or manual failover.

In the case of auto failover, failover is automatically performed when a heartbeat is timed out. In the case of manual failover, failover is not automatically performed when a heartbeat is timed out. In that case, perform failover manually by using the WebManager or the clpgrp command. For details on the WebManager, see Chapter 1, "Functions of the WebManager" and for the details of the clpgrp command, see Chapter 4, "ExpressCluster command reference."

#### Note:

Even if the failover attribute is set to the manual failover, the failover is performed automatically when the startup of a group failed or when a monitor resource detected an error. The failover is not performed automatically only when a heartbeat is timed out.

#### - Failback Attribute

Set either auto failback or manual failback.

In the case of the auto failback, failback will be automatically performed when the server that is given the highest priority is started after a failover.

In the case of the manual failback, a failback is not performed even if a server is started. Perform a failback manually by using the WebManager or executing the clpgrp command. For details on the WebManager, see Chapter 1, "Functions of the WebManager, for details on the clpgrp command, see Chapter 4, "ExpressCluster command reference."

A group that registers a mirror disk resource cannot configure the setting of auto failback.

#### - Logical Service

Set the logical service name.

The logical service is the character string that is used as an identifier when using an application which identifies a group by using the compatible API of ExpressCluster Ver8.0 or earlier.

### **Understanding failover policy**

A failover policy is a rule that determines a server to be the failover destination from multiple servers, and it is defined by the properties of a group. When you configure the failover policy, avoid making certain servers more heavily loaded at a failover.

The following describes how servers behave differently depending on failover policies when a failover occurs using example of the server list that can fail over and failover priority in the list.

#### <Symbols and meaning>

Server status	Description
О	Normal (properly working as a cluster)
od	Suspended (not recovered as a cluster yet)
×	Stopped (cluster is stopped)

#### 3-node configuration:

C	Order of server priorities		
Group	1 <sup>st</sup> priority server	2 <sup>nd</sup> priority server	3 <sup>rd</sup> priority server
А	server1	server3	server2
В	server2	server3	server1


#### 2-node configuration:


Group	Order of server priorities	
Group	1 <sup>st</sup> priority server	2 <sup>nd</sup> priority server
A	server1	server2
В	server2	server1

It is assumed that the group startup attributes are set to auto startup and the failback attributes are set to manual failback for both Group A and B. It is also assumed that the servers are configured not to recover automatically from the status of being suspended. Whether to perform auto recovery from the suspended status is set ON/OFF of **Auto Return** on the **Auto Recovery** tab in **Cluster Properties**.

- If groups of different failover exclusive attributes co-exist in a cluster, they do not interfere with each other. For example, a group of full exclusive attributes may start on a server where a group of non-exclusive attributes is active, and vice versa.
- For groups whose failover exclusive attributes are normal or full, the server which they start up or fail over is determined by the failover priority to the server. If a group has two or more servers of the same failover priority, it is determined by the order of numbers, the specific symbols and alphabets of the group name.
- The failover priority of the WebManager group is determined by the server priority. You can specify server priority on the **Master Server** tab in **Cluster Properties**.


#### When the failover exclusive attribute of Group A and B is set to Off:






- 1. Cluster startup
- 2. Cluster shutdown
- 3. Failure of server1: Fails over to the next priority server.
- 4. Server1 power on
- 5. Server1 cluster recovery
- 6. Cluster shutdown
- 7. Move Group A
- 8. Failure of server2: Fails over to the next priority server.
- 9. Failure of server2: Fails over to the next priority server.
- 10. Failure of server3: Fails over to the next priority server
- 11. Failure of server2: Fails over to the next priority server.
- 12. Failure of server2: Fails over to the next priority server.

#### When the failover exclusive attribute for Group A and B is set to Normal:







(6)Cluster shutdown

- 1. Cluster startup
- 2. Cluster shutdown
- 3. Failure of server1: Fails over to a server where no normal exclusive group is active.
- 4. Server1 power on
- 5. Server1 cluster recovery
- 6. Cluster shutdown
- 7. Move group A
- 8. Failure of server2: Fails over to a server where a normal exclusive group is not active.
- 9. Failure of server2: Normal exclusive groups of all servers are active, but the server fails over to a server because there is a server that can start normal exclusive groups.
- 10. Failure of server3: There is no server where a normal exclusive group is not active, but failover to the server because there is a server that can be started.
- 11. Failure of server2: Fails over to a server where a normal exclusive group is not active.
- 12. Failure of server3: Fails over to a server where a normal exclusive group is not active.


#### When the failover exclusive attribute for Group A and B is set to Absolute:






- 1. Cluster startup
- 2. Cluster shutdown
- 3. Failure of server1: Fails over to the next priority server.
- 4. Server1 power on
- 5. Server1 cluster recovery
- 6. Cluster shutdown
- 7. Move group A
- 8. Failure of server2: Fails over to the next priority server.
- 9. Failure of server2: Does not failover (Group B stops).
- 10. Failure of server3: Does not failover (Group A stops).
- 11. Failure of server2: Fails over to the server where no full exclusive group is
  - active.
- 12. Failure of server3: Fails over to the server where no full exclusive group is
  - active.

# ~ For Replicator ~ (two-server configuration) When the failover exclusive attribute for Group A and B is set to Off:





- 1. Cluster startup
- 2. Cluster shutdown
- 3. Failure of server1: Fails over to the standby server of Group A.
- 4. Server1 power on
- 5. Server1 cluster recovery
- 6. Cluster shutdown
- 7. Move group A
- 8. Failure of server2: Fails over to the standby server of Group B.
- 9. Failure of server2
- 10. Failure of server2: Fails over to the standby server.

### Operations at detection of activation and inactivation errors

When an activation or deactivation error is detected, the following operations are performed:

- ♦ When an error in activation of group resources is detected:
  - When an error in activation of group resources is detected, activation is retried.
  - When activation retries fail as many times as the number set to Retry Count at
     Activation Failure, a failover to the server specified in Failover destination takes
     place.
  - If the failover fails as many times as the number set to **Failover Threshold**, the action configured in **Final Action** is performed.
- ♦ When an error in deactivation of group resources is detected:
  - When an error in deactivation of group resources is detected, deactivation is retried.
  - When deactivation retries fail as many times as the number set to **Retry Count at Deactivation Failure**, the action configured in **Final Action** is performed.

#### Note:

Failovers are counted on a server basis. **Failover Threshold** is the maximum failover count on a server.

The failover count is reset in a server where the group activation succeeded and a certain time has passed.

The following describes how an error in activation of group resources is detected:


When the following settings are made:


Retry Count at Activation Failure 3 times


Failover Threshold The same number as the number of severs

(In the following case, 2 times)

Final Action Stop Group







#### Final action

When activation fails even though the failover performed as many times as the number set to **Failover Threshold**, the action configured in **Final Action** is performed. The final action can be selected from the following operations.

#### - No Operation (Activate next resource)

Activates the group resource which depends on the group resource that an activation error is detected.

#### - No Operation (Not activate next resource)

Does not activate the group resource which depends on the group resource that an activation error is detected.

#### - Stop Group

Deactivates all resources in the group which the group resource that an activation error is detected belongs.

#### - Stop cluster service

Stops the ExpressCluster Server service of the server that an activation error is detected.

#### - Stop the cluster service and shutdown OS

Stops the ExpressCluster Server service of the server that an activation error is detected, and shuts down the OS.

#### - Stop cluster service and reboot OS

Stops the ExpressCluster Server service of the server that an activation error is detected, and reboots the OS.

#### - Generating of intentional Stop Error

Generate a stop error intentionally on the server that an activation error is detected.

#### Reboot count limit

If **Stop cluster service and shutdown OS** or **Stop cluster service and reboot OS** is selected as the final action to be taken when any error in activation or deactivation is detected, you can limit the number of shutdowns or reboots caused by detection of activation or deactivation errors.

This maximum reboot count is the upper limit of reboot count of each server.

#### Note:

The maximum reboot count is the upper limit of reboot count of a server because the number of reboots is recorded per server.

The number of reboots that are taken as a final action in detection of an error in group activation or deactivation and those by monitor resources are recorded separately.

If the time to reset the maximum reboot count is set to zero (0), the number of reboots will be unavailable, thus, shutdown/reboot is executed every time at detecting failure regardless of the maximum number of reboot.

The following describes the flow of operations when the limitation of reboot count is set as shown below:

As a final action, **Stop cluster service and reboot OS** is executed once because the maximum reboot count is set to one (1).

If the ExpressCluster Server service is started successfully after rebooting OS, the reboot count is reset after 10 minutes because the time to reset maximum reboot count is set to 10 minutes.


#### Setting example


Retry Count at Activation Failure 0 Failover Threshold 0


Final Action Stop cluster service and reboot OS

Max Reboot Count 1


Max Reboot Count Reset Time 10 minutes







ExpressCluster X 2.1 for Windows Reference Guide



## Resetting the reboot count

Run the clpregctrl command to reset the reboot count. For details on the clpregctrl command, see Chapter 4, "ExpressCluster command reference."

# Displaying and changing the settings of group properties

You can display and change the settings of the group properties by using **Resources** tab of the Builder.

### Renaming a group

#### SuspendResume GroupStopRestart

- 1. In the tree view in the left pane of the Builder, right-click the icon of the group that you want to rename, and then click **Rename Group**.
- 2. The **Change Group Name** dialog box is displayed. Enter a new name.

### Displaying and changing the comment of a group


- 1. In the tree view in the left pane of the Builder, right-click the icon of the group that you want to change its comment, and then click **Properties**. The **Group Properties** dialog box is shown
- 2. On the **Info** tab, the group name and comment are displayed. Enter a new comment.

#### Note:

You cannot change the group name on the **Info** tab. To change the group name, right-click the icon of the group as described in the step 1 above. Click **Rename Group** and enter a new name.

# Displaying and changing the settings of servers that starts up the group

- 1. In the tree view in the left pane of the Builder, right-click the icon of the group with servers whose settings you want to display and change, and then click **Properties**.
- 2. In the Group Properties dialog box, click Startup Server tab. In Servers that can run the Group, servers that can start the group and their priority are shown. In Available Servers, the servers that can be registered with Servers that can run the Group are shown.



3. Set the startup servers by following the procedures below:

#### Add SuspendResume

Use this button to add a server. Select a server that you want to add from **Available Servers**, and then click **Add**. The server is added to **Servers that can run the Group**.

#### Remove SuspendResume

Use this button to remove a server. Select a server that you want to remove from **Servers that** can run the Group, and then click **Remove**. The server is added to **Available Servers**.

#### Up, Down SuspendResume


Use these buttons to change the priority of the servers that can be started. Select a server whose priority you want to change from **Servers that can run the Group**. Click **Up** or **Down** to move the selected row upward or downward.

**Note:** When you configure a server groups, delete servers that do not belong to the server group from **Servers that can run the Group**. Add servers belonging to the server group to **Servers that can run the Group**. Pay extra attention when adding/deleting servers after creating a group or server group.

### Displaying and changing the server group settings

When a group contains a hybrid disk resource, two server groups need to be configured so as to perform disk mirroring between servers.

- In the tree view in the left pane of the Builder, right-click the icon of the group of which you
  want to display / change the settings, and click **Properties**. The **Group Properties** dialog
  box is displayed.
- 2. Server groups that can start groups are displayed in Server Groups that can run the Group. Server groups that can be registered in Server Groups that can run the Group are displayed in Available server groups.



3. Configure the settings of the server groups to be used by following the description below.

#### Add

Use this button to add a server group to **Server Groups that can run the Group**. Select a server group you want to add from **Available server groups** and click **Add**. The server group will be added to **Server Groups that can run the Group**.

#### Delete


Use this button to delete a server group from **Server Groups that can run the Group**. Select a server group you want to delete from **Servers that can run the Group** and click **Delete**. The server group will be added to **Available server group**.

#### Up and Down

Use these buttons to change the priority of the server groups. Select a server group whose priority you want to change from **Available server groups** and click **Up** or **Down**. The selected line will move.

### Displaying and changing the group attribute

- 1. In the tree view in the left pane of the Builder, right-click the icon of the group that you want to show/change its settings of the attribute, and then click **Properties**.
- 2. In the Group Properties dialog box, click the Attribute tab. Specify Startup Attribute, Failover Exclusive Attribute, Failover Attribute, and Failback Attribute of this group by following the procedures on the next page:



#### Startup Attribute SuspendResume

Select whether to automatically start the group from ExpressCluster (auto startup), or to manually start from the WebManager or by using the clpgrp command (manual startup) at the cluster startup.

#### Failover Exclusive Attribute SuspendResume

This attribute determines the server to which ExpressCluster automatically fails over. You can select from Off, Normal, and Absolute.

#### Failover Attribute SuspendResume

Select if the failover is performed automatically when server fails.


#### Failback Attribute SuspendResume

Select if the failback is performed automatically to the group when a server that has a higher priority than other server where the group is active is started. For groups that have mirror disk resources or hybrid disk resources, select manual failback.

For details on the group attribute, see "What is a group?."

### **Displaying and changing Logical Service**

- 1. In the tree view in the left pane of the Builder, right-click the icon of the group of which you want to change the attribute, and click **Properties**. The **Group Properties** dialog box is displayed.
- 2. Click the **Logical Service** tab. Add a logical service to the **Logical Service**.



#### Add

Use this button to add a logical service to the **Logical Service**.


Up to 48 logical service names can be registered within the failover group. The same logical service name can be registered multiple times as long as it is registered with different failover groups.

#### **Delete**

Use this button to delete the selected logical service name from the **Logical Service**.

#### **Edit**

Use this button to display the **Entry of Logical Service Name** dialog box.



**Logical Service Name** Within 31 bytes

Enter the Logical Service Name that you want to add within 31 bytes.

For details on the group attribute, see "What is a group?."

# Displaying and changing the settings of group resources

You can display and change the settings of the group resources by using the **Resource Properties** in the Builder.

## Renaming a group resource

#### SuspendResume GroupStopRestart

- 1. In the tree view in the left pane of the Builder, click the icon of the group to which the group resource that you want to rename belongs. The list of selected group resources is shown on the table view in the right pane of the screen.
- 2. Right-click the name of the group resource that you want to rename, and then click **Rename**Resource
- 3. The **Change Resource Name** dialog box is displayed. Enter a new name.

### Displaying and changing the comment of a group resource

- 1. In the tree view in the left pane of the Builder, click the icon of the group to which the group resource whose comment you want to change belongs. Group resources of the selected group will be listed on the table view in the right pane of the screen.
- 2. Right-click the name of the group resource whose comment you want to display or change, and click Resource Properties.
- 3. On the **Info** tab, the group resource name and comment are shown. Enter new comment (within 127 bytes).

#### Note:

You cannot change the group resource name on the **Info** tab. To change the group name, right-click the icon of the group resource as described in the step 1 above. Click **Rename Group** and enter new name.


# Understanding the settings of dependency among group resources


By specifying dependency among group resources, you can specify the order of activating them.


- ♦ When the dependency among group resources is set:
  - When activating a failover group that a group resource belongs to, its activation starts after the activation of the **Dependent Resources** is completed.
  - When deactivating a group resource, the deactivation of the "Dependent Resources" starts after the deactivation of the group resource is completed.

To display the settings of dependency among group resources, click the icon of the group whose group resources dependency you want to view on the tree view shown in the left pane of the Builder, and then click the **Dependency List** tab on the table view shown in the right pane of the Builder.

The following shows an example of the depth of dependency of resources that belong to a group.







# Displaying and configuring the settings of dependency among group resources

Set the dependent group resources on a group resource basis.

- 1. In the tree view shown in the left pane of the Builder, click the icon of the group to which the group resource whose settings of dependency you want to display or configure belongs.
- 2. In list of group resources shown in the table view in the right pane, right-click the group resource whose dependency settings you want to display and configure. Click **Properties**, and then click the **Dependency** tab.
- 3. Set the dependency as described below:
- ♦ When **Follow the default dependence** is selected:


Default dependency resource type is shown in **Dependent Resources**.

Nothing is shown in Available Resources.

♦ When Follow the default dependence is not selected:

Group resource names and types are shown in **Dependent Resources**.

Group resources that can be added to **Dependent Resources** are listed in **Available Resources**. Group resources whose dependency is looped (that depend on depended group resource) are not shown. Group resources in **Dependent Resources** are not shown either.



Follow the default dependence

SuspendResume

**GroupStopRestart** 

Select if the selected group resource follows the default ExpressCluster dependency.

◆ When Follow the default dependence is selected:

The selected group resource depends on the type(s) of resources.

See "Parameters list" in Chapter 2, "Functions of the Builder" for the default dependency of each resource.

When there is more than one resource of the same type, the selected group resource depends on all resources of that type.

♦ When Follow the default dependence is not selected:

The selected group resource depends on the specified resource.

Add SuspendResume GroupStopRestart

It is used when adding the group resource selected in **Available Resources** to **Dependent Resources**.

Remove SuspendResume GroupStopRestart

It is used when removing the group resource selected in **Dependent Resources** from **Dependent Resources**.

# Displaying and changing the operation settings when a group resource error is detected

You can display and change the operation settings of actions when a group resource error is detected (when group resources are active/inactive) by using the **Settings** tab of the Builder.


- 1. In the tree view shown in the left pane of the Builder, click the icon of the group to which the group resource you want to display or change whose behavior at the time when a group resource error is detected belongs.
- 2. The list of group resources will be shown in the table view on the right pane. Right-click the group resource you want to view or set whose behavior at the time when a group resource error is detected. Click **Properties**, and then click the **Settings** tab.
- 3. Specify the behavior at the time when a group resource error is detected by following the procedures below:
- ♦ When an error in activation of the group resource is detected:

When an error is detected while activating the group resource, try activating it again. When the activation retry count exceeds the number of times set in **Retry Count at Activation Failure**, failover to the server specified in the **Failover Target Server** is executed.

When the group resource cannot be activated even after executing a failover as many times as specified in **Failover Threshold**, the final action is taken.

♦ When an error in deactivation of the group resource is detected:

When an error is detected while deactivating the group resource, try deactivating it again. When the deactivation retry count exceeds the number of times set in **Retry Count at Deactivation Failure**, the final action is taken.



#### Retry Count at Activation Failure (0 to 99) SuspendResume

Enter how many times to retry activation when an activation error is detected. If you set this to zero (0), the activation will not be retried.

#### Failover Target Server SuspendResume

Select a Failover Target Server for the failover that takes place after activation retries upon activation error detection have failed for the number of times specified in **Retry Count at Activation Failure**.

- Stable operation server
   The failover destination is the server where least resource errors have been detected.
   If two or more servers that meet the above condition exist, failover takes place by selecting one of them according to the failover policy of the group.
- Server with the highest priority
  Failover takes place according to the failover policy settings of the group.

#### Failover Threshold (0 to 99) SuspendResume

Enter how many times to retry failover after activation retry fails as many times as the number of times set in **Retry Count at Activation Failure** when an error in activation is detected.

If you set this to zero (0), failover will not be executed.

- Set as many as the number of the servers Set the failover threshold count to the number of servers.
- Specify the count Specify any number for the failover threshold count.

#### Final Action SuspendResume

Select an action to be taken when activation retry failed the number of times specified in **Activation Retry Threshold** and failover failed as many times as the number of times specified in **Failover Threshold** when an activation error is detected.

Select a final action from the following:

- · No Operation (Activate next resource)
- · No Operation (Not activate next resource)
- · Stop Group
- · Stop cluster service
- · Stop cluster service and shutdown OS
- Stop cluster service and reboot OS
- · Generating of intentional Stop Error

For details on the final action, see "Final action."

#### **Execute Script before Final Action**

Select whether script is run or not before executing final action when an activation failure is detected.

- · When selected:
  - A script/command is run before executing final action. To configure the script/command setting, click **Settings**.
- When cleared: Any script/command is not run.

#### Retry Count at Deactivation Failure (0 to 99) SuspendResume

Enter how many times to retry deactivation when an error in deactivation is detected.

If you set this to zero (0), deactivation will not be retried.

#### Final Action SuspendResume

Select the action to be taken when deactivation retry failed the number of times specified in **Retry Count at Deactivation Failure** when an error in deactivation is detected.

Select the final action from the following:

- · No Operation (Deactivate next resource)
- · No Operation (Not deactivate next resource)
- Stop cluster service and shutdown OS
- Stop cluster service and reboot OS
- · Generating of intentional Stop Error

For details on the final action, see "Final action."

#### Note:

If you select **No Operation** as the final action when a deactivation error is detected, group does not stop but remains in the deactivation error status. Make sure not to set **No Operation** in the production environment.

#### **Execute Script before Final Action**


Select whether script is run or not before executing final action when a deactivation failure is detected.

- · When selected:
  - A script/command is run before executing final action. To configure the script/command setting, click **Settings**.
- When cleared: Any script/command is not run.

# Displaying and changing the script when a group resource activation/deactivation failure is detected

You can display and change the setting of a script which is run before executing final action when a group resource failure is detected (when group resources are active/inactive) by using the **Settings** tab of the Builder.

- 1. In the tree view shown in the left pane of the Builder, click the icon of the group to which the group resource you want to view or set whose behavior at the time when a group resource activation/deactivation failure is detected belongs.
- **2.** The list of group resources will be shown in the table view on the right pane. Right-click the group resource which you want to display or set whose behavior at the time when a group resource error is detected. Click **Properties**, and then click the **Settings** tab.
- 3. Click Settings in Recovery Operation at Activation Failure Detection or Recovery Operation at Deactivation Failure Detection to display the Edit Script dialog box. Set the script/command to be run before executing final action.



#### **User Application**

Use an executable file (executable batch file or execution file) on the server as a script. For the file name, specify an absolute path or name of the executable file of the local disk on the server. If you specify only the name of the executable file, you must configure the path with environment variable in advance. If there is any blank in the absolute path or the file name, put them in double quotation marks ("") as follows.

Example:

"C:\Program Files\script.bat"

If you want to execute VBScript, enter a command and VBScript file name as follows.

#### Example:

escript script.vbs

Each executable files is not included in the cluster configuration information of the Builder. They must be prepared on each server since they cannot be edited nor uploaded by the Builder.

#### Script created with this product

Use a script file which is prepared by the Builder as a script. You can edit the script file with the Builder if you need. The script file is included in the cluster configuration information.

File (Within 1023 bytes)

Specify a script to be executed (executable batch file or execution file) when you select **User Application**.

#### View

Click here to display the script file with an editor when you select **Script created with this product**. The information edited and stored with the editor is not reflected. You cannot display the script file if it is currently displayed or edited.

#### **Edit**

Click here to edit the script file with the editor when you select **Script created with this product**. Overwrite the script file to reflect the change. You cannot edit the script file if it is currently displayed or edited. You cannot modify the name of the script file.

#### Replace


Click here to replace the contents of a script file with the contents of the script file which you selected in the file selection dialog box when you select **Script created with this product**. You cannot replace the script file if it is currently displayed or edited. Select a script file only. Do not select binary files (applications), and so on.

#### **Timeout** (0 to 99)

Specify the maximum time to wait for completion of script to be executed. The default value is set as 5.

#### Change

Click here to display the **Change Script Editor** dialog. You can change editor for displaying or editing a script to an arbitrary editor.



#### **Standard Editor**

Select here to use a standard editor (Notepad in Windows) as a script editor.

#### **External Editor**

Select here to specify an arbitrary script editor. Click **Browse** to specify the editor to be used

# Displaying the properties of the whole groups by using the WebManager

1. Startup WebManager (http://FIP\_address\_for\_the\_WebManager\_group:port\_number (the default value is 29003))

2. Click the object for the all groups in the tree view. The following information is displayed in the list view.

Groups Name: Groups		
Group Name	Current Server	Status
ManagementGroup	server1	Online
failover1	server1	Online

Groups Name: Group name


Current Server: Server that the group is currently active

Status: Group status

# Displaying the properties of a certain group by using the WebManager

1. Startup the WebManager (http://FIP\_address\_for\_the\_WebManager\_group:port\_number (the default value is 29003)).

2. Click the object for a certain group in the tree view. The following information is displayed in the list view.



Resource Status		
	Resource Name	Status
appli1		Online
fip1		Online
md1		Online
regsync1		Online
spool1		Online
vcom1		Online

Server name

Name: Group name

Comment: Group comment

Status: Group status

Server Name:

Status: Status of the group on the server Resource Name: Resource name of the group

ExpressCluster X 2.1 for Windows Reference Guide

Status: Status of the resources of the group

If you click **Details** button, the following information is displayed in the pop-up dialog box:

Properties	Value
Type	cluster
Startup Attribute	Auto Startup
Failover Exclusive Attribute	No Exclusion
Failback Attribute	Manual Failback
Failover Attribute	Auto Failover
Servers that can run the Group	server1
	server2

Type: Group type

Startup Attribute: Startup type of the group (auto/manual)

Failover Exclusive Attribute: Startup exclusive attribute

Failback Attribute: Failback attribute of the group (auto/manual)
Failover Attribute: Failover attribute of the group (auto/manual)
Servers that can run the Group: Order of the servers that the group failover


## **Understanding server groups**

This section provides information about server groups.

Server groups are groups of servers that are required when hybrid disk resources are used.

Upon using hybrid disk resources in a shared disk device, servers connected by the same shared disk device are configured as a server group.

Upon using hybrid disk resources in a non-shared disk, a single server is configured as a single server group.



# Displaying / changing the server group settings

You can display and change the settings of the server group by using **Server Group Properties** of the Builder.

## Renaming a server group (Server group properties)

- 1. In the tree view in the left pane of the Builder, right-click the icon of the server group that you want to rename, and then click **Rename Server Group**.
- 2. The Change Server Group Name dialog box is displayed. Enter a new name.

# Displaying and changing the comment of a server group (Server group properties)

1. In the tree view in the left pane of the Builder, right-click the icon of the server group that you want to change its comment, and then click **Properties**. The **Server Group Properties** dialog box is shown.

2. On the **Info** tab, the server group name and comment are displayed. Enter or modify the comment within 127 bytes.


#### Note:

You cannot change the server group name on the **Info** tab. To change the group name, right-click the icon of the group as described in the step 1 above. Click **Rename Server Group** and enter a new name.

# Displaying and changing the settings of servers belonging to a server group (Server group properties)

You can change the servers that belong to a server group.

- 1. In the tree view in the left pane of the Builder, right-click the icon of the server group that you want to display and change the settings, and then click **Properties**. The **Server Group Properties** dialog box is shown.
- **2.** Click the **Server Group** tab.
- **3.** In **Servers that can run the Group**, servers that can start the group and their order are shown. The smaller the number, the higher priority the server has. In **Available Servers**, the servers that can be registered with **Servers that can run the Group** are shown.



**4.** Configure the server group settings according to the following explanation.

#### Add

Use **Add** to add a server that can run the group. Select the server you want to add from **Available Servers** list and then click **Add**. The selected server is added to the **Servers that can run the Group**.

#### Remove

Use **Remove** to remove a server that can run the group. Select the server you want to remove from the **Servers that can run the Group** list and then click **Remove**. The selected server is added to **Available Servers**.

#### Up & Down

Use **Up** and **Down** to change the priority of a server that can run the group. Select the server whose priority you want to change, and then click **Up** or **Down**. The selected row moves accordingly.

**Note:** Make sure that the priority of the **Servers that can run the Group** consists with the failover policy of the failover group to which the resource using this server group belongs.

## Displaying the server group properties with WebManager

1. Start WebManager.

2. In the tree view, click the object . The following will be displayed in the list view.

Server Groups	
ServerGroup Name	Server Name
server-group-1	server1
	server2
server-group-2	server2

Server group name Server group name

Server name Server names which belong to the server group

# **Understanding application resources**

You can register applications managed by ExpressCluster and executed when a groups in ExpressCluster starts, stops, fails over or moves. It is also possible to register your own applications in application resources.

### Dependency of application resources

By default, application resources depend on the following group resource types:

Group resource type
Croup resource type
Floating IP resource
Virtual IP resource
Virtual computer name resource
Disk resource
Mirror disk resource
Hybrid disk resource
Print spooler resource
Registry synchronization resource
CIFS resource
NAS resource

### **Application resources**

Application resources are the programs that are executable from the command line by the files whose extension is exe, cmd, bad, or other.


## Note on application resources

◆ An application to be run from application resources must be installed on all servers in failover and must have the same version.

## Displaying and changing the application resource details

- 1. In the tree view shown on the left pane of the Builder, click the icon of the group to which the application resource whose detailed information you want to display or change belongs.
- 2. The list of group resources is displayed in the table view on the right pane of the screen. Right-click the name of the application resource that you want to display or change. Click **Properties**, and then click **Details** tab.
- 3. Display and/or change the settings by following the description below.

#### Resource Properties: Details tab



#### Resident Type GroupStopRestart

Specify the type of the application. Select one of the following:

- · Resident
  - Select this when the application resides in ExpressCluster.
- · Non-resident

Select this when the application does not reside (Process returns right after being executed) in ExpressCluster.

#### Start Path Within 1023 bytes GroupStopRestart

Specify the name of the file that can be run when the application resource is started.

#### **Stop Path** Within 1023 bytes

Specify the name of the file that can be run when the application resource is stopped. This cannot be set when the resident type is Resident.

#### Note:

For the Start Path and Stop Path, specify an absolute path to the executable file or the name of the executable file of which the path configured with environment variable is effective. Do not specify a relative path. If it is specified, starting up the application resource may fail.


#### **Tuning**

Use this button to display the **Application Resource Tuning Properties** dialog box. Configure the detailed settings for the application resources.

#### **Application Resource Tuning Properties**

#### Parameter tab

Detailed parameter settings are displayed on this tab.



#### Synchronous (Start)

This setting is not available for a resident application.

If the application is non-resident, select this to wait for the application to stop when it is run.

#### Asynchronous (Start)

This setting is not available for a resident application.

If the application is non-resident, select this so as not to wait for the application to stop when it is run.

#### Synchronous (Stop)

If the application is resident, select this to wait for the currently running application to stop.

If the application is non-resident, select this to wait for the application to stop when it is run.

#### Asynchronous (Stop)

If the application is resident, select this so as not to wait for the currently running application to stop.

If the application is non-resident, select this so as not to wait for the application to stop when it is

#### Timeout (Start) (0 to 9999) SuspendResume

This setting is not available for a resident application.

Configure the time-out value to wait (synchronous) for a non-resident application to stop when the application is run. A value can be entered only when **Synchronous** is selected. If the application does not stop within the time-out value set here, it is considered as an error.

#### Timeout (Stop) (0 to 9999) SuspendResume

Configure the time-out value to wait (synchronous) for currently running resident application(s) to stop or for a non-resident application to stop when the application is run.

The time-out value can be set only when **Synchronous** is selected. If the application does not stop within the time-out value set here, it is considered as an error.

#### Target VCOM Resource Name GroupStopRestart

Select a virtual computer name used as a computer name for the application resource. Virtual computer names and resource names that exist in the failover group where the application resource belong to are listed.

#### Allow to Interact with the Desktop GroupStopRestart


Specify whether to allow the application to be run to interact with desktop. If this is selected, the application screen is displayed on the desktop when the application starts running. This setting is not available when an Exec User is specified on the **Start** and **Stop** tabs.

#### **Initialize**

Click **Initialize** to reset the values of all items to their default values.

#### **Start and Stop tabs**

A detailed setting for starting and stopping the application is displayed.



**Current Directory** Within 1023 bytes

Specify a directory for running the application.

**Option Parameter** Within 1023 bytes

Enter parameters to be entered for the application. If there are multiple parameters, delimit parameters with spaces. For a parameter that includes a space, enclose the parameter with double quotation marks.

Example: "param 1" param2

#### Window Size

Select the size of the window for running the application from the following:

· Hide

The application is not displayed.

Normal

The application is displayed in a regular window size.

· Maximize

The application is displayed in a maximum window size.

· Minimize

The application is displayed in a minimum window size.

#### Exec User Domain GroupStopRestart

Specify the domain of a user account that runs the application.

In the case of **Stop** tab, it is unnecessary to stop and/or resume the group.

#### Exec User Account GroupStopRestart

Specify the user account that runs the application.

In the case of **Stop** tab, it is unnecessary to stop and/or resume the group.

#### Exec User Password GroupStopRestart

Specify the password for the user account that runs the application.

In the case of **Stop** tab, it is unnecessary to stop and/or resume the group.

#### **Execute from the Command Prompt**

Specify whether to run the application from the command prompt (cmd.exe). Specify this when running an application (such as JavaScript and VBScript) whose extension is other than exe, cmd, or bat.

#### Initialize

Click **Initialize** to reset the values of all items to their default values.

# Displaying the application resource properties with the WebManager

- 1. Start the WebManager. (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click an object for an application resource in the tree view. The following information is displayed in the list view.

Application Name: appli1		Details
Properties	Value	
Name	appli1	
Comment		
Resident Type	Resident	
Start Path	C:\appli\appli1.exe	
Stop Path		
Status	Online	

Resource Status on Each Server		
Server Name	Status	
server1	Online	
server2	Offline	

Name: Name of the application resource
Comment: Comment on the application resource
Resident Type: Resident type of the application resource

Start Path: Start path of the application
Stop Path: Stop path of the application
Status: Status of the application resource

Server Name: Server name

Status: Status of the application resource in the given server

If you click the **Details** button, the following information is displayed.

Properties	Value
Type	appli
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Retry Count at Activation Failure	0
Final Action at Activation Failure	No Operation (Activate next resource)
Execute Script before Final Action	Off
Retry Count at Deactivation Failure	0
Final Action at Deactivation Failure	No Operation (Deactivate next resource)
Execute Script before Final Action	Off
Dependent Resources	
Retry Interval at Activation Failure	5
Retry Interval at Inactivation Failure	5
Target VCOM Name	
[Start]Type	Synchronous
[Start]Timeout (seconds)	1800
[Start]Current Directory	
[Start]Option Parameter	
[Start]Window Size	Hide
[Start]Domain	
[Start]Account	
[Start]Allow To Interact With Desktop	Off
[Start]Execute From Command Prompt	Off
[Stop]Type	Synchronous
[Stop]Timeout (seconds)	1800
[Stop]Current Directory	
[Stop]Option Parameter	
[Stop]Window Size	Hide
[Stop]Domain	
[Stop]Account	
[Stop]Allow To Interact With Desktop	Off
[Stop]Execute From Command Prompt	Off

Type: Resource type

Failover Target Server: Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an error Retry Count at Activation Failure: The number of times activation is retried when an activation

error is detected

Final Action at Activation Failure: Final action at an activation error

Execute Script before Final Action: Whether or not script is executed upon activation failure

Retry Count at Deactivation Failure: The number of times deactivation is retried when a

deactivation error is detected

Final Action at Deactivation Failure: Final action at a deactivation error

Execute Script before Final Action: Whether or not script is executed upon deactivation failure

Dependent Resources:

Retry Interval at Activation Failure:

Retry Interval at Inactivation Failure:

Dependent resources

Activation retry interval

Deactivation retry interval

Target VCOM Name:

[Start]Type:

[Start] Timeout (Second):

[Start]Current Directory:

VCOM name that the application uses

Execution type of Start application

Timeout for Start application

Directory for Start application

[Start]Option Parameter: Option parameter to be passed to Start application

[Start]Window Size: Window size of the Start application

[Start]Domain: Domain of the account that runs Start application

[Start] Account that runs Start application

[Start]Allow to Interact with Desktop: Allow Start application to communicate with desktop [Start]Execute from the Command Prompt: Run Start application from the command prompt

[Stop]Type: Execution type of Stop application
[Stop]Timeout(Second): Timeout for Stop application
[Stop]Current Directory: Directory for Stop application

[Stop]Option Parameter: Option parameter to be passed to Stop application

[Stop]Window Size:Window size of the Stop application[Stop]Domain:Domain of the account that runs application[Stop]Account:Account that runs Stop application

[Stop]Allow to Interact with Desktop: Allow Stop application to communicate with desktop [Stop]Execute from the Command Prompt: Run Stop application from the command prompt

ExpressCluster X 2.1 for Windows Reference Guide

# **Understanding floating IP resources**


# **Dependencies of floating IP resources**

By default, this function does not depend on any group resource type.

### Floating IP

Client applications can use floating IP addresses to access cluster servers. By using floating IP addresses, clients do not need to be aware of switching access destination server when a failover occurs or moving a group migration.

Floating IP addresses can be used on the same LAN and over the remote LAN.



#### Address assignment

An IP address to assign for floating IP address needs to meet the condition described below:

• Available host address which is in the same network address as the LAN that the cluster server belongs

Allocate as many IP addresses that meet the above condition as required (generally as many as failover groups). These IP addresses are the same as general host addresses, therefore, you can assign global IP addresses such as Internet.

You can also allocate IPv6addresses to floating IP addresses.

#### **Routing**

You do not need to make settings for the routing table.

#### Conditions to use

Floating IP addresses are accessible to the following machines:

- Cluster server itself
- Other servers in the same cluster and the servers in other clusters
- Clients on the same LAN as the cluster server and clients on remote LANs

If the following conditions are satisfied, machines other than the above can also access floating IP addresses. However, connection is not guaranteed for all models or architectures of machines. Test the connection thoroughly by yourself before using those machines.

- ◆ TCP/IP is used for the communication protocol.
- ◆ ARP protocol is supported.

Even over LANs configured with switching hubs, floating IP address mechanism works properly. When a server goes down, the TCP/IP connection the server is accessing will be disconnected.

# Notes on floating IP resources

If OS stalls with the floating IP address activated, the resource failover may fail when the following settings are made:


- ♦ Run ping .is On.
- **♦ Forced FIP Activation** is Off.

This problem occurs due to the following causes:


- ◆ A part of OS stalls (as examples below) with the floating IP address activated.
  - Network modules are running and respond to ping from other nodes
- When activating the floating IP address on the server to which the resource is failed over, if the ping command is executed to the IP address to be activated in order to prevent redundant activation, ping reaches the IP address because of the reason above, and the resource activation error occurs

In the machine environment where this problem often occurs, this can be prevented by the settings below. However, both groups may be activated depending on the status of a stall, and server shutdown may occur depending on the timing of the activation of both groups.


- Specify "Off" to Run ping
   Overlap check is not performed to the floating IP address.
- ◆ Specify "On" to **Forced FIP Activation**The floating IP address is activated forcibly even when the address is used on a different server.
- \* When Run ping is set to On and Forced FIP Activation is set to Off



#### \* When **Run ping** is set to Off



#### \* When **Run ping** is set to On and **Forced FIP Activation** is set to On




Notes on allocating floating IP addresses to IPv6 addresses

- ♦ IPv6 addresses should not be specified in Management Resources in Management Group.
- In the setting of virtual computer name resource, setting connection of floating IP resource assigned to IPv6 is invalid.
- ♦ When the floating IP address is set to perform to register in virtual computer name resource dynamically and it is selected to correspond to virtual computer name, the floating IPaddress cannot be allocated to IPv6 address.
- ♦ For Windows Server 2008, it is necessary to add the **Routing and Remote Access** service to each cluster server to enable the LAN routing. This is not required when the interconnect LAN with the highest priority is common to public LAN.
- ♦ When an IPv6 address is used as a virtual IP address in Windows Server 2003, it is necessary to specify public LAN as the interconnect with the highest priority.

# Displaying and changing the details of floating IP resource

- 1. From the tree view displayed on the left pane of the Builder, click the icon of the group to which the floating IP resource whose detailed information you want to display and/or change belongs.
- 2. The group resource list is displayed in the table view in the right pane of the window. Right-click the desired floating IP resource name, click **Disk Resource Properties** and select the **Details** tab.
- 3. On the **Details** tab, you can see and/or change the settings by following the description below.





IP Address GroupStopRestart

Enter the floating IP address to be used.

Follow the instruction below to enter an IPv6 address.

Example: fe80::1

With the default value of prefix length 64 bit, floating IP resource searches for the addresses that have matching prefix on the local computer and adds floating IP address to the matching index. When there is more than one matching address, address is added to the index that has the largest index value.

In order to specify the prefix length explicitly, specify the prefix length after the address.

Example: fe80::1/8

In order to specify the index explicitly, specify %index after the address.

Example: fe80::1%5


The example above shows how to add a floating IP address to the index5.

#### Tuning

Opens the **Floating IP Resource Tuning Properties** dialog box where you can make detailed settings for the floating IP resource.

#### **Floating IP Resource Tuning Properties**

Detailed settings on floating IP resource are displayed.



#### Run ping

Specify this to verify if there is any overlapped IP address before activating floating IP resource by using the ping command.

- ♦ When selected:
  - The ping command is used.
- ♦ When cleared:

The ping command is not used.

#### ping

These are the detailed settings of the ping command used to check if there is any overlapped IP address before activating floating IP resource.

- ♦ Interval (0 to 999) SuspendResume
- Set the interval to issue the ping command in seconds.

  Timeout (1 to 999999)

  SuspendResume
- Set time-out of the ping command in milliseconds.

Retry count (0 to 999) SuspendResume

Set retry count of the ping command.

#### **♦** Forced FIP Activation

Specify whether to forcibly activate floating IP address when an overlapped IP address is detected by command check.

When selected:

Forced activation is performed.

When cleared:


Forced activation is not performed.

#### Initialize

Click **Initialize** to reset the values of all items to the default values.

# Displaying the properties of floating IP resource with the WebManager

- 1. Start the WebManager. (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003.))
- 2. Click an object for a floating IP resource information is displayed in the list view.



Name: Floating IP resource name

Comment: Comment

Status: Status of floating IP resource

IP Address: IP address used by floating IP resource

Server Name: Server name

Status: Status of floating IP resource of the server

If you click the **Details** button, the following information is displayed in the pop-up dialog.

Properties	Value
Type	fip
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Retry Count at Activation Failure	5
Final Action at Activation Failure	No Operation (Not activate next resource)
Execute Script before Final Action	Off
Retry Count at Deactivation Failure	0
Final Action at Deactivation Failure	No Operation (Deactivate next resource)
Execute Script before Final Action	Off
Dependent Resources	
Retry Interval at Activation Failure	5
Retry Interval at Inactivation Failure	5
Ping Execute	On
Ping Timeout (milliseconds)	1000
Ping Retry Threshold	5
Ping Retry Interval (seconds)	1
FIP Force Activation	Off

Type: Resource type

Failover Target Server

Failover Threshold:

Determination method of Failover Target Server
The number of failovers to be made at detection of an

error

Retry Count at Activation Failure: The number of times activation is retried when an

activation error is detected

Final Action at Activation Failure: Final action at activation error

Execute Script before Final Action: Whether or not script is executed upon activation

ailure

deactivation error is detected

Final Action at Deactivation Failure: Final action at deactivation error

Execute Script before Final Action: Whether or not script is executed upon deactivation

failure

Dependent Resources:
Retry Interval at Activation Failure:
Retry Interval at Inactivation Failure:
Ping Execute:
Dependent resource
Activation retry interval
Deactivation retry interval
Ping to verify redundancy

Ping Timeout(Second): Timeout of ping to confirm redundancy (in

milliseconds)

Ping Retry Threshold: Ping retry threshold count Ping Retry Interval(Second): Ping retry interval

FIP Force Activation: Forced floating IP activation

# **Understanding mirror disk resources**

### Dependencies of mirror disk resources

By default, this function does not depend on any group resource type.

#### Mirror disk

Mirror disks are a pair of disks that mirror disk data between two servers in a cluster.

Mirroring is performed by partition. It requires the RAW partition (cluster partition) to record the management data as well as the data partition that is to be mirrored. In addition, the license of ExpressCluster X Replicator 2.0/2.1 for Windows is necessary on both servers that mirroring is performed.

The specifications of the disks need to be the same on both servers in order to use them as mirror disks.

Examples:

#### Disk type and geometry

The size of the data partitions has to be completely the same by byte on both servers. If the disk size and geometry are different on each server, it may be unable to create partitions that are exactly the same size. Thus the geometry of disks which are used to secure data partitions needs to be the same on both servers.

It is recommended to use disks of the same model on both servers. Example:

Combination	server1	server2
Correct	SCSI	SCSI
Correct	IDE	IDE
Incorrect	IDE	SCSI

Comb	ination	Head	Sector	Cylinder
Correct	server1	240	63	15881
Conect	server2	240	63	15881
Incorrect	server1	240	63	15881
incorrect	server2	120	63	31762


If it is not possible to make both servers have exactly the same disk type and geometry, check the size of data partitions in precise by using the clpvolsz command. If the disk size does not match, shrink the larger partiotin by using the clpvolsz command again.

For more information about the clpvolsz command, see "Chapter 4 ExpressCluster command reference."


#### • Drive letter of partition

Configure the same drive letter for a data partition and cluster partition on both servers.

Example: Adding a SCSI disk to both servers to create a pair of mirroring disks.



Example: Using available area of the IDE disk on which OS of both servers are stored to create a pair of mirroring disks.



A mirror partition (cluster partition, data partition) can be allocated on the same disk as OS.

When the maintainability at occurrence of failure is important:

It is recommended to have another disk for a mirror than a disk for OS in advance.

When a logical disk cannot be added because of the limitations of the hardware RAID specifications:


When it is difficult to change the configuration of a logical disk since hardware RAID is pre-installed:

A mirror partition (cluster partition, data partition) can be allocated on the same disk as OS.

#### ♦ Disk allocation

One mirror disk resource can perform mirroring to only one partition. However, multiple partitions can be mirrored by creating multiple mirror disk resources.


It is possible to create multiple mirroring resources by allocating multiple data partitions and cluster partitions on a single disk.



Example: Adding one SCSI disk to both servers to create two pairs of mirroring disks.

- · Allocate a cluster partition and two data partitions in a pair on a single disk.
- Assign 0 and 1 for the offset index of the cluster partition management area to be used in each data partition.

Example: Adding two SCSI disks for both servers to create two mirroring partitions.



- Secure a cluster partition and data partition on the first disk and a data partition on the second disk.
- Routing and Remote AccessAssign 0 and 1 for the offset index of the cluster partition management area to be used in each data partition.
- A cluster partition can be secured on each disk. In that case, the offset index is assigned to be 0 and 0.
- · When performing mirroring in the asynchronous mode, an access to a cluster partition is generated in accordance with writing in a data partition. The access to a disk can be distributed by securing a cluster partition and data partition on separate disks.

#### **Data partition**

Partitions where data that is mirrored by ExpressCluster (such as application data) is stored are referred to as data partitions. Allocate data partitions as follows:

◆ Data partition size

There is no limitation for partition size. Allocate any size of partition. However, if the size is too large when copying completely at the time of initial construction and/or changing disks, the maintainability is deteriorated. This is because the larger the size is, the more it takes time to copy completely. Thus, it is recommended to set the size of the data partition 100GB or less in total.

- ◆ File system
  - Format the partition with NTFS. FAT/FAT32 is not supported.
- ♦ Allocate the partition on a basic disk. The dynamic disk is not supported.
- When making data partitions as logistical partitions on the extended partition, make sure the data partitions are logical partition on both servers. The actual size may be different even the same size is specified on both basic partition and logical partition
- ◆ The access to the data partition is controlled by ExpressCluster.

#### **Cluster partition**

Dedicated partitions used in ExpressCluster for mirror partition controlling are referred to as cluster partition.


Allocate cluster partitions as follows:

- Cluster partition size
  - 17 MB or more. Depending on the geometry, the size may be larger than 17 MB, but that is not a problem.
- A cluster partition and data partition for data mirroring should be allocated in a pair.
- ◆ You do not need to make the file system on cluster partitions. Do not format.
- ◆ The access to a cluster partition is limited.

#### Access control of a data partition

The data partition to be mirrored by a mirror disk resource can be accessed only from the active server where a mirror disk resource is activated.

- ◆ ExpressCluster is responsible for the access control of the file system. Application's accessibility to a data partition is the same as switching partition (disk resources) that uses shared disks.
- Mirror partition switching is done for each failover group according to the failover policy.
- ♦ By storing data required for applications on data partitions, the data can be automatically used after failing over or moving failover group.



# **Understanding mirror parameters**

#### The maximum size of request queues

Configure the size of queues which is used for the mirror disk driver to queue I/O requests on the communication among servers. If you select a larger value, the performance will improve but more memory will be required. If you select a smaller value, less memory will be used but the performance may be lowered.

Note the following when setting the number of queues:

- ◆ The improvement in the performance is expected when you set a larger value under the following conditions:
  - Large amount of physical memory is installed on the server and there is plenty of available memory.
  - The performance of the disk I/O is high.
- It is recommended to select a smaller value under the conditions:
  - Small amount of physical memory is installed on the server.
  - I/O performance of the disk is low.

#### **Mirror Connect Timeout**

This is the time required to cut a mirror connect when there is no response on the communication among servers and/or when the data synchronization has not completed at the time of mirror recovery and/or data synchronization. The time for time-out needs to be configured longer, if the line speed of the mirror connect is slow and/or the load to the mirror disk is high.

#### **Initial Mirror Construction**

Specify if initial mirroring is configured when activating cluster for the first time after the cluster is created.

• Execute the initial mirror construction

An initial mirroring is configured (disk images of the data partition are fully copied) when activating cluster for the first time after the cluster is created.

◆ Do not execute initial mirror construction

Assume that data in the data partition has already matched among servers and do not configure initial mirroring at initial startup after constructing a cluster. When constructing a cluster, it is necessary to make the disk image of the data partition (physical data) identical without using ExpressCluster.

#### Mode

Switch the synchronization mode of mirroring.

Mode	Overview	Explanation
Synchronous	Complete match of the data in the active and standby servers is guaranteed.	Writing the data to the mirrored disk is finished when writing the data to both local and remote disks is finished.
Asynchronous	The order to write in the updated data is guaranteed. However, the latest updated data may be lost, if a failover is performed in the state that a mirror disk resource cannot be deactivated as servers are down.	Writing the data to the mirrored disk is finished when writing the data to the local disk is finished.  The data is transferred to the remote disk after writing request is queued and performed on the background.  After queuing is kept in the kernel space memory, it is transferred to the user space memory. When the volume of data reaches a limit that the user space memory can keep, the data is sent out to a temporary file and kept there.

#### **Kernel Queue Size**

Specify the size of the request for writing to the remote disk to be kept in the kernel space memory when the mode is set to "Asynchronous." Normally, default value is specified.

Input and output are completed, if writing data can be saved in the kernel queue.

If taking data into the application queue is delayed as the load on CPU is high, the size is set larger. However, if the size is too large, it will result in compressing the system resource.

#### **Application Oueue Size**

Specify the size of the request for writing to the remote disk to be kept in the user space memory when the mode is set to "Asynchronous." Normally, the default value is used. However, if a high-speed network is used, the frequency of creating a temporary file can be reduced and the overhead caused by input and output can be decreased by making the queue size larger.

#### **Upper Bound of Communication Band**

When the mode is" asynchronous", the server tries to transfer data that has been queued to the standby server. When the channel for mirror connection is used for connections for other applications, the communication band may become busy. In this case, by setting the bound of communication band for the mirror connect communication, the impact on other communications can be reduced. If the communication band for mirror connect is smaller than the average amount of data to be written into the mirror disk, the queued data cannot be fully transferred to the standby server, which can result in overflow and suspension of mirroring. The bandwidth should be large enough for data to be written into the business application.

This function makes a limit to the communication band by having a maximum of one-second pause when the total amount of data to be transferred per second exceeds the configured value. If the size of data to be written into the disk at a time is greater than the configured value, expected performance may not be achieved. For example, even if you set the value of communication band limit to be 64Kbyte or smaller, the actual amount of communication during copy can be greater than the configured value because the size of data to be transferred for a copy of a mirror disk at a time is 64 Kbyte.

#### **History Files Store Folder**

Specify the folder that keeps the temporary file which is created when the request for writing to the remote disk in the "Asynchronous" mode cannot be recorded in the application queue. When the communication band runs short, data is recorded up to the limit of the disk space if the limit of the history file size is not specified. Thus, specifying a folder on the system disk runs out of the empty space and the system behavior may become unstable. Therefore, if you want to suspend mirroring when recording data is exceeded a certain size, create a dedicated partition or specify the limit of the history file size. Do not specify any folder on the cluster partition and data partition to the history files store folder.


#### **Thread Timeout**

This is the time that time-out is occurred when data cannot be transferred to the application queue from the kernel queue in the mode of "Asynchronous." When it is timed out, a mirror connect is cut.

Timeout may occur, if the data transfer to the application queue is delayed due to high load. In this case, increase the timeout value.

# **Examples of mirror disk construction**

• Execute the initial mirror construction



Mirror disk

Mirror disk

- ◆ Do not execute the initial mirror construction
  - Follow the procedures below to have identical data in the data partition on both servers:
  - 1. If application data to be duplicated can be prepared before configuring a cluster, create it on data partition of the mirror disk on the active server in advance (ex. initial data of the database).
- **2.** Install ExpressCluster and configure a cluster without executing the initial mirror construction.
- **3.** Shut down the cluster.
- 4. Remove disks that have data partitions on both servers, and connect to the Linux server. Then copy the data in the data partition on the active server to the data partition on the standby server by using the dd command in the state that disks are not mounted.
- **5.** Return disks to the active and standby server and start both servers.


#### Note on mirror disk resources

Set both servers so that the identical partitions can be accessed under the identical drive letter. If a drive letter different from those used on partition is set, the drive letter will be changed when the mirror disk resource is started. If the drive letter is used on any other partitions, starting up the mirror disk resource will fail.

# Displaying and changing the details of mirror disk resources

- 1. From the tree view displayed on the left pane of the Builder, click the icon of the group to which the mirror disk resource whose detailed information and settings you want to display and/or change belongs.
- 2. The group resource list is displayed on the table view in the right pane of the window. Right-click the desired mirror disk resource name, and click **Properties** on the shortcut menu. In the properties dialog box, click the **Details** tab.
- 3. Display and/or change the detailed settings on the **Details** tab as described below.

#### Mirror Disk Resource: Details tab



Mirror Disk Number SuspendResume GroupStopRestart

Select the number to be allocated to the mirror partition.

 Data Partition Driver Letter (up two 1023 bytes)
 SuspendResume
 GroupStopRestar

Specify the drive letter of the data partition.

Cluster Partition Drover Letter (up to 1023 bytes) SuspendResume GroupStopRestart


Specify the drive letter to the cluster partition.

Cluster Partition Offset Index SuspendResume GroupStopRestart

Select an index number for the area used in the cluster partition. When using the multiple mirror disks, assign different numbers for each mirror disk so that the areas to be used in the cluster partition are not overlapped.

#### Add ShutdownReboot

Click this button to add the selected server to **Servers that can run the group**. When this button is clicked, the dialog box that allows for selection of a partition of the selected server is displayed.



#### **♦** Data Partition

Select a partition to be used as a data partition from the list. The GUID of the selected data partition is displayed.

#### **♦** Cluster Partition

Select a partition to be used as a cluster partition from the list. The GUID of the selected cluster partition is displayed.

#### **♦** Connect

Use this button to connect to the server and obtain the list of partitions.

#### Important:

Specify different partitions for data partition and cluster partition. If the same partition is specified, data on the mirror disk may be corrupted. Make sure not to specify the partition on the shared disk for the data partition and cluster partition.

#### Delete ShutdownReboot

Use this button to delete a server from **Servers that can run the group**.

#### Edit SuspendResume GroupStopRestart

Use this button to display the dialog box to select the partition of the selected server.

#### Tuning


Opens the **Mirror Disk Resource Tuning Properties** dialog box. You make detailed settings for the mirror disk resource there.

# **Tuning mirror disk resource**

- 1. From the tree view displayed on the left pane of the Builder, click the icon of the group to which the mirror disk resource whose detailed information and settings you want to display and/or change belongs.
- 2. The group resource list is displayed on the table view in the right pane of the window. Right-click the desired mirror disk resource name, click **Properties** on the shortcut menu. In the properties dialog box, click the **Details** tab.
- 3. On the **Details** tab, click **Tuning** to display the **Mirror Disk Resource Tuning Properties** dialog box. Display and/or change the detailed settings as described below.

#### Mirror tab

The advanced settings of mirror are displayed.



Execute the initial mirror construction SuspendResume GroupStopRestart

Specify whether to execute an initial mirror construction (full copy of data partition) when configuring a cluster.

- When selected Execute an initial mirror construction. In general, specify this.
- When cleared Handle as it is configured without executing an initial mirror construction. Specify this if the data partition contents are already the same and full copying is not required.

Mirror Connect Timeout (2 to 999) SuspendResume GroupStopRestar

Specify the time-out for mirror connect.

Request Queue Maximum Size (512 to 65535) SuspendResume GroupStopRestart

Specify the size of queue that a mirror disk driver uses to queue I/O requests on the communication among servers.

#### Mode SuspendResume GroupStopRestart

Switch the mode of the mirror data synchronization.

- Synchronous
  - Write in the local disk and remote disk simultaneously to queue the completion.
- **♦** Asynchronous
  - After writing in the local disk, write in the remote disk. Queue for the completion of writing in the local disk.

Kernel Queue Size (512 to 65535) SuspendResume GroupStopRestart

Specify the queue size of the kernel space to save the I/O data of the asynchronous mirror temporarily.

Application Queue Size (512 to 65535) SuspendResume GroupStopRestart

Specify the queue size of the user space to save the I/O data of the asynchronous mirror temporarily.

Thread Timeout (2 to 999) SuspendResume GroupStopRestart

Specify the time-out when it becomes unable to transfer from the kernel queue to the application queue.

Upper Bound of Communication Band (0 to 999999999) SuspendResume GroupStopRestart

Set the upper limit of communication band in Mirror Connect

History Files Store Folder Within 256 bytes SuspendResume GroupStopRestart

Specify the destination folder to store the file when I/O data is overflowed form the application queue. It is required to specify a folder that has sufficient free space so that the remote disk and the asynchronous I/O data can be kept as a file.

Do not specify any folder in the cluster partition and data partition to the history files store folder. Additionally do not specify a folder that contains two byte characters in the path.

Max. size of history files size (0 to 999999999) SuspendResume GroupStopRestart

Set the size limit of temporary files stored in the history file store folder. If the upper limit of size is specified, mirroring will stop when it reaches the limit. The configured value is only applied to the limit of the temporary file size for the mirror disk resources and not applied to the amount of the temporary files in the folder.

#### Initialize

Click **Initialize** button to reset the values of all items to their default values.

# Displaying the mirror disk resource properties with the WebManager

- 1. Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click an object for a mirror disk resource in the tree view. The following information is displayed in the list view.

Mirror Disk Name: md1	Details
Properties	Value
Name	md1
Comment	
Mirror Disk Number	1
Drive Letter	F:
Status	Online

Resource Status on Each Server		
Server Name	Status	
server1	Online	
server2	Offline	

Name: Mirror disk resource name
Comment: Mirror disk resource comment

Mirror Disk No.: Mirror disk number allocated to the mirror partition

Drive Letter: Drive letters of the data partition Status: Status of the mirror disk resource

Server Name: Server name

Status: Status of the mirror disk resource in the given server

If you click the **Details** button, the following information is displayed in the pop-up dialog.

Properties	Value	
Туре	md	
Failover Target Server	Stable Server	
Failover Threshold	Number of Servers	
Retry Count at Activation Failure	0	
Final Action at Activation Failure	No Operation (Not activate next resource)	
Execute Script before Final Action	Off	
Retry Count at Deactivation Failure	0	
Final Action at Deactivation Failure	No Operation (Deactivate next resource)	
Execute Script before Final Action	Off	
Dependent Resources		
Retry Interval at Activation Failure	5	
Retry Interval at Inactivation Failure	5	
Cluster Partition - Drive Letter	E:	
Cluster Partition - Offset Index	0	
Initial Mirror Construction	On	
Mode	Synchronous	
Max. Number of Request Queues(KB)	2048	
Mirror Connect Timeout(sec)	20	
Asynchronous - History Files Store Folder		
Asynchronous - Kernel Queue Size(KB)	2048	
Asynchronous - Application Queue Size(KB)	2048	
Asynchronous - Thread Timeout(sec)	30	
Asynchronous - Max. Size of History File(MB)	Unlimited	
Asynchronous - Upper Bound of Communication Band(KB/sec)	Unlimited	

Type: Resource type

Failover Target Server Determination method of Failover Target Server Failover Threshold: The number of failovers to be made at detection of an

error

Retry Count at Activation Failure: The number of times activation is retried when an

activation error is detected

Final Action at Activation Failure: Final action at an activation error

Execute Script before Final Action: Whether or not script is executed upon activation

failure

Retry Count at Deactivation Failure: The number of times deactivation is retried when a

deactivation error is detected

Final Action at Deactivation Failure: Final action at deactivation error

Execute Script before Final Action: Whether or not script is executed upon deactivation

failure

Dependent Resources: Dependent resource

Retry Interval at Activation Failure Interval to perform activation retry when an activation

Error is detected

activation error is detected.

Cluster Partition

Cluster Partition Drive Letter: Drive letters of the cluster partition

Cluster Partition Offset Index: Index number for the area to be used for cluster

partition

Initial mirror construction: Whether to execute an initial mirror construction when

configuring a cluster

Mode: Synchronization mode of the mirror data

Request Queue Maximum Size (KB): Size of queue for the mirror disk drive to queue I/O

requests on the communication among servers.

Mirror Connect Timeout (Second): Time until mirror connect is cut when there is no response on the communication among servers and the

response on the communication among servers and the data synchronization has not completed at the time of

mirror recovery and data synchronization.

Asynchronous:

History Files Store Folder: Folder to keep the writing requests to the remote disk

in files

Kernel Queue Size (KB): Size to keep the writing request to the remote disk in

the kernel space memory

Application Queue Size (KB): Size to keep the writing request to the remote disk in

the user space memory

Thread Timeout: Timeout when it became unable to transfer data form

the kernel queue to the application queue

Max. size of history file size (MB): Upper limit of amount of files stored in history files

store folder.

Upper Bound of Communication Band (KB/sec.):

Upper limit of communication band on Mirror

Connect.


# Understanding registry synchronization resources

# Dependencies of registry synchronization resources

By default, this function depends on the following group resource types.

Group resource type
Floating IP resource
Virtual IP resource
Virtual computer name resource
Disk resource
Mirror disk resource
Hybrid disk resource
Print spooler resource

# Registry synchronization resources



Registry keys to be synchronized at failover can be configured. When the content in a registry key set as synchronization target is updated while registry synchronization resource is active, the updated content is reflected to the registry of the Failover Target Server.

The following describes how a registry synchronization resource synchronizes registry:

- 3. When there is a registry synchronization resource in a failover group, update of a registry key that has been configured is monitored when the registry synchronization resource is activated.
- 4. When the registry key update is detected, what is in the registry key is saved as a file in the local disk. Then the file is delivered to each Failover Target Server.
- 5. The servers that received the file keep it in their local disks. If a failover occurs and registry synchronization resource is activated in a server that received the file, the content of the file is restored in the corresponding registry key.

# Notes on registry synchronization resources

- ◆ Do not open synchronization target registry keys in the standby server.
  - If a synchronization target registry key is opened when a failover occurs, restoration of the registry will fail. To start and stop applications that use the synchronization target registry key, use a script resource within a control of ExpressCluster.
- Minimize the number of synchronization target registry keys. Do not set more than needed. It is not recommended to set a registry key that is frequently updated as a synchronization target registry key.
  - Saving in a file and delivering the file to other servers is done every time a synchronization target registry key is updated. The number of synchronization target registry keys and frequency of updating them can affect the system performance.
- For the synchronization target registry keys, the following can be set. The registry keys other than those listed below cannot be synchronized.
  - · Any key under the HKEY USERS
  - · Any key under the HKEY LOCAL MACHINE

Do not set the following keys.


- Keys under the HKEY\_LOCAL\_MACHINE/SOFTWARE/NEC/ExpressCluster
- · HKEY\_LOCAL\_MACHINE/SOFTWARE/NEC
- · HKEY LOCAL MACHINE/SOFTWARE
- · HKEY LOCAL MACHINE

Do not set the keys that are in parent-child relationship within the same resource.

- Up to 16 synchronization target registry keys can be set per resource.
- The following restrictions apply to names of the synchronization target registry keys:
  - The characters that can be used for registry key are determined by the OS specifications.
  - · Up to 259 bytes can be used. Do not set the key name of 260 or larger bytes.


# Displaying and changing the details of registry synchronization resource

- 1. From the tree view displayed on the left pane of the Builder, click the icon of the group to which the registry synchronization resource whose detailed information and settings you want to display and/or change belongs.
- 2. The group resource list is displayed on the table view in the right pane of the window. Right-click the desired registry synchronization name, click **Properties** on the shortcut menu. In the properties dialog box, click the **Details** tab.
- 3. Display and/or change the detailed settings on the **Details** tab as described below.



Add SuspendResume GroupStopRestart

Use this button to add a registry key to monitor. The **Entry of registry key** dialog box is displayed.



#### Registry Key

Enter a registry key to synchronize and click **OK**.

Delete SuspendResume GroupStopRestart

Click this button to delete a registry key from synchronization target listed in **Registry List**.

Edit SuspendResume GroupStopRestart

The **Entry of registry key** dialog box is displayed. The selected registry keys are listed in **Registry List**. Edit a registry key and click **OK**.


# **Tuning registry synchronization resource**

- 1. From the tree view displayed in the left pane of the window, click the icon of the group to which the registry synchronization resource whose detailed information and settings you want to display and/or change belongs.
- 2. The group resource list is displayed on the table view in the right pane of the window. Right-click the desired registry synchronization resource name, select **Properties** on the shortcut menu. In the properties dialog box, click the **Details** tab.
- **3.** Clicking **Tuning** on the **Details** tab displays the **VxVM Volume Resource** dialog box. Display and/or change the detailed settings as described below.

### **Registry Synchronization Resource Tuning Properties**

#### Parameter tab

The detailed setting for registry synchronization resource is displayed.



**Delivery Interval** (1 to 99) SuspendResume

Specify the interval to deliver the updated registry key information to other servers.

- ♦ When short-time interval is set
  - · Updated information is immediately delivered to other servers.
  - The system may get heavily loaded by frequently updating a registry key.
- ♦ When long-time interval is set
  - A delay in delivering updated information to other servers may occur. If a failover occurs before delivery of the updated information is not completed, it will not be delivered to the Failover Target Server.
  - Increase in system load due to synchronization can be reduced when a registry key is frequently updated.

#### Initialize

Click **Initialize** to reset the values of all items to their default values.

# Displaying the registry synchronization resource properties with the WebManager

- 1. Start the WebManager. (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click an object for registry synchronization resource in the tree view. The following information is displayed in the list view.

Registry Synchronization Name: regsync1 Details				
Properties	Value			
Name	regsync1			
Comment				
Registry Key HKEY_LOCAL_MACHINE\S				
Status	Online			
Resource Status on Each Server				
Server Name Status				
server1 Online				
server2 Offline				

Name: Registry synchronization resource name
Comment: Registry synchronization comment
Registry Key: Registry key to be synchronized

Status: Status of the registry synchronization resource

Server Name: Server name

Status: Status of registry synchronization resource on the given server

#### If you click the **Details** button, the following information is displayed in the pop-up dialog.

Properties	Value
Type	regsync
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Retry Count at Activation Failure	0
Final Action at Activation Failure	No Operation (Not activate next resource)
Execute Script before Final Action	Off
Retry Count at Deactivation Failure	0
Final Action at Deactivation Failure	Stop the cluster service and shutdown OS
Execute Script before Final Action	Off
Dependent Resources	fip1,md1
Retry Interval at Activation Failure	5
Retry Interval at Inactivation Failure	5

Type: Resource type

Failover Target Server Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an error

Retry Count at Activation Failure: The number of times activation is retried when an

activation error is detected

Final Action at Activation Failure: Final action at an activation error

Execute Script before Final Action: Whether or not script is executed upon activation failure Retry Count at Deactivation Failure: The number of times deactivation is retried when a

deactivation error is detected

Final Action at Deactivation Failure: Final action at an deactivation error

Execute Script before Final Action: Whether or not script is executed upon deactivation failure

Dependent Resources: Dependent resource

Retry Interval at Activation Failure: Retry Interval when activation failure is detected Retry Interval at Inactivation Failure: Retry interval when deactivation failure is detected

# **Understanding script resources**

You can register scripts managed by ExpressCluster and run when starting, stopping, failing over, or moving a group in ExpressCluster. It is also possible to register your own scripts for script resources.

## Note:

The same version of the application to be run from script resources must be installed on all servers in failover policy.

# **Dependencies of script resources**


By default, this function depends on the following group resource types.

Group resource type
Floating IP resource
Virtual IP resource
Virtual computer name resource
Disk resource
Mirror disk resource
Hybrid disk resource
Print spooler resource
Registry synchronization resource
CIFS resource
NAS resource

# Scripts in script resources

## Types of scripts

Start script and stop script are provided in script resources. ExpressCluster runs a script for each script resource when the cluster needs to change its status. You have to write procedures in these scripts about how you want applications to be started, stopped, and restored in your cluster environment.



Start: Start script Stop: Stop script

# **Environment variables in script of script resource**

When ExpressCluster runs a script, it records information such as the condition when the script is run (script starting factor) in environment variables.

You can use the environment variables on the table below as branching condition to write code for your system operation.

The environment variable of a stop script returns the content of the start script that was run immediately before as a value. Start script does not set environment variables of CLP\_FACTOR and CLP\_PID.

The environment variable of CLP\_LASTACTION is set only when the environment variable CLP FACTOR is CLUSTERSHUTDOWN or SERVERSHUTDOWN.

Environment Variable	Value of environment variable	Meaning	
	START	The script was run: - by starting a cluster; - by starting a group; - on the destination server by moving a group; - on the same server by restarting a group due to the detection of a monitor resource error; or	
CLP_EVENTscript starting factor		<ul> <li>on the same server by restarting a group resource due to the detection of a monitor resource/ARMLOAD command error.</li> </ul>	
script starting factor	FAILOVER	The script was run on the Failover Target Server:	
		- by the server's failing;	
		- due to the detection of a monitor resource/ARMLOAD command error; or	
		- because activation of group resources failed.	
		The server is recovered.	
	RECOVER	The script is started/restarted due to detection of a monitor resource/ARMLOAD command error	

Environment Variable	Value of environment variable	Meaning	
	CLUSTERSHUTDOWN	The group was stopped by stopping the cluster.	
	SERVERSHUTDOWN	The group was stopped by stopping the server.	
	GROUPSTOP	The group was stopped by stopping the group.	
CLP_FACTOR	GROUPMOVE	The group was moved by moving the group.	
group stopping factor		The group failed over because an error was detected in monitor resource; or	
	GROUPFAILOVER	the group failed over because of activation failure in group resources.	
	GROUPRESTART	The group was restarted because an error was detected in monitor resource.	
	RESOURCERESTART The group resource was restarted because an error was detected in mercesource.		
CLP_LASTACTION	REBOOT	In case of rebooting OS	
process after cluster shutdown	HALT	In case of halting OS	
	NONE	No action was taken.	
CLP_SERVERserver where the	HOME The script was run on the primary se of the group.		
script was run	OTHER	The script was run on a server other than the primary server of the group.	
CLP_DISKpartition connection	SUCCESS	There was no partition with connection failure.	
information on shared or mirror disks	FAILURE	There was one or more partition with connection failure.	
CLP_PRIORITY the order in failover policy of the server where the script is run	1 to the number of servers in the cluster	Represents the priority of the server where the script is run. This number starts from 1 (The smaller the number, the higher the server's priority).  If CLP_PRIORITY is 1, it means that the script is run on the primary server.	
CLP_GROUPNAMEGroup name	Group name	Represents the name of the group to which the script belongs.	
CLP_RESOURCENAM E Resource name	Resource name	Represents the name of the resource to which the script belongs.	
CLP_PID Process ID	Process ID	Represents the process ID of the start script when the properties of the start script are set to asynchronous. This environment variable is null when the start script is set to synchronous.	

# **Execution timing of script resource scripts**

This section describes the relationships between the execution timings of start and stop scripts and environment variables according to cluster status transition diagram.

- ◆ To simplify the explanations, a 2-server cluster configuration is used as an example. See the supplements for the relations between possible execution timings and environment variables in 3 or more server configurations.
- O and X in the diagrams represent the server status.

Server	Server status
0	Normal (properly working as a cluster)
Х	Stopped (cluster is stopped)

(Example) OA: Group A is working on a normally running server.

- Each group is started on the top priority server among active servers.
- ◆ Three Group A, B and C are defined in the cluster, and they have their own failover policies as follows:


Group	First priority server	r Second priority server	
Α	server1	server2	
В	server2	server1	
С	server1	server2	

◆ The upper server is referred to as server1 and the lower one as server2.



Cluster status transition diagram

This diagram illustrates a typical status transition of cluster.




Numbers (1) to (13) in the diagram correspond to descriptions as follows.

## (1) Normal startup

Normal startup here refers to that the start script has been run properly on the primary server.

Each group is started on the server with the highest priority among the active servers.




Environment variables for Start. bat

Group		Environment variable	Value
Α	A (1)	CLP_EVENT	START
A	(1)	CLP_SERVER	HOME
В	(1)	CLP_EVENT	START
Б	(1)	CLP_SERVER	HOME
С	(1)	CLP_EVENT	START
	(1)	CLP_SERVER	HOME

## (2) Normal shutdown

Normal shutdown here refers to a cluster shutdown immediately after the start script corresponding to a stop script was run by performing normal startup or by moving a group (online failback).




Environment variables for Stop. bat

Group		Environment variable	Value
Δ	A (1)	CLP_EVENT	START
		CLP_SERVER	HOME
В	(1)	CLP_EVENT	START
		CLP_SERVER	HOME
C	C (1)	CLP_EVENT	START
		CLP_SERVER	HOME

#### (3) Failover at the failed server1

The start script of a group that has server1 as its primary server will be run on a lower priority server (server2) if an error occurs. You need to write CLP\_EVENT(=FAILOVER) as a branching condition for triggering application startup and recovery processes (such as database rollback process) in the start script in advance.

For the process to be performed only on a server other than the primary server, specify CLP SERVER(=OTHER) as a branching condition and describe the process in the script.



Environment variables for Start.bat


Group		Environment variable	Value
Δ	A (1)	CLP_EVENT	FAILOVER
		CLP_SERVER	HOME
С	(1)	CLP_EVENT	FAILOVER
(1)	CLP_SERVER	HOME	

## (4) Recovering server1 to cluster

When server1 that has been rebooted (operating as non-cluster) returns to a cluster, the start script of the failover group that was running when a failover occurred is run in server1. This means recovery is executed in the server where the failover has occurred.

To execute a recovery (for example, recovering database information in a local disk), you need to write CLP\_EVENT(=RECOVER) as a branching condition. Even if recovery is not required, you need to write the script not to start the operation.

For data mirroring operation, data is restored (reconfiguration of mirror set) at cluster recovery.





Environment variables for Start.bat

Group		Environment variable	Value
Α	(1)	CLP_EVENT	RECOVER
	(1)	CLP_SERVER	HOME
С	(4)	CLP_EVENT	RECOVER
	(1)	CLP_SERVER	HOME

## (5) Cluster shutdown after failover of server1

The stop scripts of the Group A and C are run on server2 to which the groups failed over (the stop script of Group B is run by a normal shutdown).







Environment variables for Stop. bat

Group		Environment variable	Value
Α	(1)	CLP_EVENT	FAILOVER
	(1)	CLP_SERVER	OTHER
В	(1)	CLP_EVENT	START
ъ	, (1)	CLP_SERVER	HOME
	C (1)	CLP_EVENT	FAILOVER
		CLP_SERVER	OTHER

## (6) Moving of Group A and C

After the stop scripts of Group A and C are run on server2 to which the groups failed over, their start scripts are run on server1.





Environment variables for Stop.bat

-				
Group		Environment variable	Value	
Α	(1)	CLP_EVENT	FAILOVER 1	
^	(1)	CLP_SERVER	OTHER	
С	(1)	CLP_EVENT	FAILOVER	
		CLP_SERVER	OTHER	

Environment variables for Start. bat


Group		Environment variable	Value
Α	(2)	CLP_EVENT	START
_ ^		CLP_SERVER	HOME
С	(2)	CLP_EVENT	START
		CLP_SERVER	HOME

Environment variables in a stop script take those in the previous start script.

For moving in "(6) Moving of Group A and C" because it is not preceded by a cluster shutdown, the environment variable used here is FAILOVER. However, if a cluster shutdown is executed before moving in "(6) Moving of Group A and C", the environment variable is START.

## (7) server1 startup (Auto recovery mode)

Auto recovery of server1 is executed. The start script of the failover group operated when a failover occurred is run in server1. This means, recovery is executed in the server where the failover occurred. Note what is stated in "(4) **Recovering server1 to cluster**." For data mirroring operation, data is restored (reconfiguration of mirror set) at cluster recovery.







Environment variables for Start.bat

Group		Environment variable	Value
Α	(1)	CLP_EVENT	RECOVER
		CLP_SERVER	HOME
С	(1)	CLP_EVENT	RECOVER
		CLP_SERVER	HOME

# (8) Error in Group C and failover

When an error occurs in Group C, its stop script is run on server1 and start script is run on server2.





Stop. bat for server1

Gro	up	Environment variable	Value
С	(1)	CLP_EVENT	START
C	(1)	CLP_SERVER	HOME

Start. bat for server1


Group		Environment variable	Value
С	(1)	CLP_EVENT	RECOVER
	(1)	CLP_SERVER	HOME


Start.bat for Server2

Group		Environment variable	Value
	(2)	CLP_EVENT	FAILOVER
C	(2)	CLP_SERVER	OTHER

## (9) Moving of Group C

Move the Group C that failed over to server2 in (8) from server2 to server1. Run the stop script on server2, and then run the start script on server1.





Stop bat. (because this failed over in (8))


Group		Environment variable	Value
_	(1)	CLP_EVENT	FAILOVER
	(')	CLP_SERVER	OTHER


Start.bat

Group		Environment variable	Value
	(2)	CLP_EVENT	START
	(2)	CLP_SERVER	HOME

# (10) Stopping Group B

The stop script of Group B is run on server2.







Stop. bat

Group		Environment variable	Value
R	B (1)	CLP_EVENT	START
В		CLP_SERVER	HOME

# (11) Starting Group B

The start script of Group B is run on server2.







Start.bat

Group		Environment variable	Value
В	(1)	CLP_EVENT	START
	(')	CLP_SERVER	HOME

# (12) Stopping Group C

The stop script of Group C is run on server2.







Stop.bat

Group		Environment variable	Value
	(1)	CLP_EVENT	FAILOVER
	(1)	CLP_SERVER	OTHER

# (13) Starting Group C

The start script of Group C is run on server2.






Start

Gre	oup	Environment variable	Value
	(1)	CLP_EVENT	START
	(1)	CLP_SERVER	OTHER

#### Additional information 1


For a group that has three or more servers specified in the failover policy to behave differently on servers other than the primary server, use CLP\_PRIORITY instead of CLP\_SERVER (HOME/OTHER).



Example 1: "(3) Failover at the failed server1" in the cluster status transition diagram

A group has server1 as its primary server. If an error occurs on server1, the group's start script is run on server2 that has next highest priority failover policy. You need to write CLP\_EVENT(=FAILOVER) as the branching condition for triggering applications' startup and recovery processes (such as database rollback) in the start script in advance.


For a process to be performed only on the server that has the second highest priority failover policy, you need to write CLP\_PRIORITY(=2) as the branching condition.




Environment variables for Start. bat

Group		Environment variable	Value
		CLP_EVENT	FAILOVER
Α	(1)	CLP_SERVER	OTHER
		CLP_PRIORITY	2
		CLP_EVENT	FAILOVER
С	(1)	CLP_SERVER	OTHER
		CLP_PRIORITY	2

Example 2: "(6) Moving of Group A and C" in the cluster status transition diagram



After the stop scrip of Group C is run on server2 from which the group failed over, the start script is run on server3.



Environment variables for Stop. bat

Group		Environment variable	Value
		CLP_EVENT	FAILOVER
С	(1)	CLP_SERVER	OTHER
		CLP_PRIORITY	2

Environment variables for Start. bat


Group		Environment variable	Value
		CLP_EVENT	START
С	(1)	CLP_SERVER	OTHER
		CLP_PRIORITY	3

#### Additional information 2

When a monitor resource or ARMLOAD command starts or restarts a script:

The environment variables to run a start script when a monitor resource or ARMLOAD command detected an error in application are as follows:

Example 1: a monitor resource or ARMLOAD command detected an error and restarts Group A on the server1.



Environment variable for Stop.bat


Group		Environment variable	Value
Α	(1)	CLP_EVENT	The same value as when the start script is run

Environment variable for Start.bat

Group		Environment variable	Value
^	(2)	CLP_EVENT	RECOVER
Α	(3)	CLP_EVENT	START

<sup>\*</sup> start.bat is executed twice.

Example2: a monitor resource or ARMLOAD command detected an error and restarts Group A on server2 through failover to server2.



Environment variable for Stop.bat

Group		Environment variable	Value
Α	(1)	CLP_EVENT	The same value as when the start script is run

Environment variable for Start.bat


Group		Environment variable	Value
А	(2)	CLP_EVENT	RECOVER
	(3)	CLP_EVENT	FAILOVER

# **Writing scripts**

This section describes how you actually write script codes in association with timing to run scripts as mentioned in the previous topic.

Numbers in brackets "(*number*)" in the following example script code represent the actions described in "Execution timing of script resource scripts" on page **473**.


## **A.** Group A start script: a sample of **stop.bat**



Refer to the environment variable of script executing factor and divide the processes. IF "%CLP\_SERVER%" = "OTHER" GOTO ON\_OTHER2 Overview of processing: A process to be executed only when the application is started on the primary server after failover When to start this process: GOTO EXIT :ON OTHER2 Overview of processing: A process to be executed only when the application is terminated on the non-primary server after failover.

When to start this process: (3) Failing over due to server1 down GOTO EXIT :RECOVER Overview of processing: Recovery processing after cluster recovery When to start this process: (4) Cluster recovery GOTO EXIT  $:\!ERROR\_DISK$ Disk-related error handling :no\_arm :EXIT exit

#### **B.** Group A stop script: a sample of **stop.sh**



Refer to the environment variable of executing server and divide the processes. IF "%CLP\_SERVER%" == "OTHER" GOTO ON\_OTEHR2 A process to be executed only when the application is terminated on the primary server after failover When to start this process: GOTO EXIT :ON\_OTHER2 Overview of processing:
A process to be executed only when the application is terminated on the non-primary server after failover. When to start this process: (5) Cluster shutdown after failover of Server 1 (6) Moving of Group A and C GOTO EXIT  $:ERROR_DISK$ Disk-related error handling :NO\_ARM :EXIT exit

# Tips for creating scripts


◆ The clplogcmd command, though which message output on the WebManager alert view is possible, is available.

# Displaying and changing the settings of the script resource details

You can display and change the settings of the detail information of the script resources by using **Resource Properties** of the Builder.


# Displaying and changing the script resource details

- 1. In the tree view shown on the left pane of the Builder, click the icon of the group to which the script resource whose detailed information you want to display or change belongs.
- 2. The list of group resources is displayed in the table view on the right pane of the screen. Right-click the name of the script resource that you want to display or change. Click **Properties**, and then click **Details** tab.
- 3. Display and/or change the settings by following the description below.



#### Change

Open a dialog box for changing script editor. You can change the script editor for viewing and editing scripts to any editor.



#### **Standard Editor**

Select this option to use the standard editor for editing scripts.

Windows: Notepad (notepad.exe which is detected by the user's search path)

#### **External Editor**

Select this option to specify a script editor. Click **Browse** to select an editor.


#### **Tuning**

Open the script resource tuning properties dialog box. You can make advanced settings for the script resource.

# Displaying and/or changing the script resource script created by the Builder

- 1. From the tree view in the left pane of the Builder, click the icon of the group to which script resource whose detail information you want to display and change belongs.
- 2. Group resource list is displayed on the table view in the right pane of the window. Right-click the script resource name. Then click **Properties** and select the **Details** tab.
- 3. Display and/or change the settings by following the description below.

The default script file names, start.bat and stop.bat, are listed on Scripts.



#### Add

Use this button to add a script other than start.bat script and stop.bat script.

#### Delete

Use this button to delete a script. The start.bat script and stop.bat script cannot be deleted.

#### View

Use this button to display the selected script file on the script editor. Changes made and saved by the editor are not reflected.


If the selected script file is being viewed or edited, you cannot see it.

#### **Edit**

Use this button to edit the selected script file on the script editor. To reflect changes, overwrite the file. If the selected script file is being viewed or edited, you cannot edit it. You cannot rename the script file

#### Replace

Opens the **Open** dialog box, where you can select a file.



#### Note:


The file will not be deleted even if you delete a script file from the Builder. If the cluster configuration data is reloaded by restarting the Builder after deleting the script file, the deleted script file will be displayed in the **Scripts**.

The content of the script file selected in the **Resource Property** is replaced with the one selected in the **Open** dialog box. If the selected script file is being viewed or edited, replacement cannot be achieved. Select a script file, not a binary file such as an application program.

# **Tuning script resource**

- 1. From the tree view displayed on the left pane of the Builder, click the icon of the group to which the script resource whose detail information you want to display and change belongs.
- 2. Group resource list is displayed on the table view in the right pane of the window. Right-click the script resource name. Then click **Properties** and select the **Details** tab.
- 3. On the **Details** tab, click **Tuning** to display **Script Resource Tuning Properties** dialog box.
- 4. Display and/or change the settings by following the description below.

#### Parameter tab



## Common to all start scripts and stop scripts

#### **Synchronous**

Select this button to wait for a script to end when it is run.

## Asynchronous

This cannot be selected.

# Timeout 0 to 9999 SuspendResume

When you want to wait for a script to end (when selecting **Synchronous**), specify how many seconds you want to wait before a time-out. This box is enabled when **Synchronous** is selected. If the script does not complete within the specified time, it is determined as an error.

## **Target VCOM Resource Name**

Configure this to use a virtual computer name as a computer name used for script resources. Virtual computer names and resource names that exist in a failover group to which script resources belong are listed.

## Allow to Interact with Desktop

Specify whether to allow the script to be run to communicate with desktop. If this is selected, progress status of the script can be checked on the screen. It is effective if used when debugging the script.

## **Initialize**

Click **Initialize** to reset the values of all items to their default values.

# Displaying the script resource properties with the WebManager

- 1. Start the WebManager. (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click an object for script resource in the tree view. The following information is displayed in the list view.

Script Name: script1	Details	
Properties	Value	
Name	script1	
Comment		
Start Path	start.bat	
Stop Path	stop.bat	
Status	Online	
D		
Resource Status on Each Serve	r	
Server Name	Status	
server1	Online	
server2	Offline	

Name: Script resource name
Comment: Script resource comment

Start Path: Path of the start script for script resource Stop Path: Path of the stop script for script resource

Status: Status of script resource

Server Name: Server name

Status: Script resource status on the given server

If you click the **Details** button, the following information is displayed in the pop-up dialog.

Properties	Value
Туре	script
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Retry Count at Activation Failure	0
Final Action at Activation Failure	No Operation (Not activate next resource)
Execute Script before Final Action	Off
Retry Count at Deactivation Failure	0
Final Action at Deactivation Failure	Stop the cluster service and shutdown OS
Execute Script before Final Action	Off
Dependent Resources	fip1,sd1
Retry Interval at Activation Failure	5
Retry Interval at Inactivation Failure	5
Target VCOM Name	
[Start]Type	Synchronous
[Start]Timeout (seconds)	1800
[Start]Allow To Interact With Desktop	Off
[Stop]Type	Synchronous
[Stop]Timeout (seconds)	1800
[Stop]Allow To Interact With Desktop	Off

Type: Resource type

Failover Target Server Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an

error

Retry Count at Activation Failure: The number of times activation is retried when an

activation error is detected

Final Action at Activation Failure: Final action at an activation error

Execute Script before Final Action: Whether or not script is executed upon activation failure Retry Count at Deactivation Failure: The number of times deactivation is retried when a

deactivation error is detected

Final Action at Deactivation Failure: Final action at a deactivation error

Execute Script before Final Action: Whether or not script is executed upon deactivation failure

Dependent Resources:
Retry Interval at Activation Failure:
Dependent resources
Activation retry interval

Retry Interval at Activation Failure: Activation retry interval
Retry Interval at Inactivation Failure: Deactivation retry interval
VCOM name that the script uses

[Start]Type: Type of start application

[Start]Timeout (Second): Timeout for start application

[Start] Allow to Interact with Desktop: Allow start application to communicate with desktop

[Stop]Type: Type of stop application

[Stop]Timeout (Second): Timeout for stop application

[Stop]Allow to Interact with Desktop: Allow stop application to communicate with desktop

# **Understanding disk resources**

# Dependencies of disk resources

By default, this function does not depend on any group resource type.

# **Disk resources**


A disk resource refers to a switching partition on a shared disk accessed by more than one server that constitutes a cluster.

## ◆ Switching partitions

A switching partition refers to a partition on a shared disk connected to more than one server in a cluster.

Switching is done on a failover group basis according to the failover policy. By storing data required for applications on a switching partition, the data can be automatically inherited when failover takes place or a failover group is moved.

A switching partition should be accessible with the same drive letter in the same area on all servers.



◆ Size of switching partitions

There is no restriction on partition size. Allocate any size for partition.

File system

Format partitions with NTFS. FAT and FAT32 are not supported.

♦ Access control

ExpressCluster controls access to file system.

◆ Configuring Host Bus Adapters (HBAs)

When more than one server is connected to a shared disk, simultaneous access from servers to the file system can corrupt the data. It is necessary to control accesses to a partition on a shared disk.

In ExpressCluster, accesses to a shared disk are controlled by HBA (Host Bus Adapter) settings. Configure HBAs that connect a shared disk to control accesses. For details, refer to "HBA tab" in Chapter 3, "Function of the Builder."

◆ Configuring DISK network partition solution resource

When a disk resource is used, it is recommended to use DISK network partition solution resource. For details on DISK network partition solution resources, refer to "Understanding network partition resolution by DISK method" in Chapter 9, "Details on network partition resolution resources."

# Notes on disk resources


- **Note 1** Make settings so that the same partition is accessible with the same drive letter on all servers.
- **Note 2** If a drive letter different from the one used on partition is set, the drive letter will be changed when the disk resource is started up. If the drive letter is used on other partitions, starting up the disk resource will fail.
- **Note 3** Dynamic disk is not supported. If a partition on dynamic disk is used for disk resource, starting up the disk resource will fail.
- **Note 4** Configure HBAs for a partition used for disk resource. If a partition without HBA configuration is used for disk resource, starting up resource will fail.

When HBA configuration is changed, OS reboot is required to reflect the changes. If OS is not rebooted after changing HBA configuration, starting up disk resource will fail.

For details on HBA configuration, refer to "HBA tab" in Chapter 3, "Function of the Builder."

# Displaying and changing the details of disk resources

- From the tree view displayed on the left pane of the Builder, click the icon of the group to which the disk resource whose detailed information you want to display and/or change belongs.
- The group resource list is displayed in the table view in the right pane of the window. Right-click the desired disk resource name, click **Properties**, and then click **Details** tab.
- In the **Details** tab, you can display and/or change the settings by following the description below.



#### Disk Resource Properties: Details tab

Drive Letter Within 1023 bytes SuspendResume GroupStopRestart

Specify the drive letter for the disk to be used.




Use this button to add a server to **Servers that can run the group**. The list of added server partitions is displayed in the **Selection of Partition** dialog box.

Delete SuspendResume GroupStopRestart

Use this button to delete a server from Servers that can run the group.

Edit SuspendResume GroupStopRestart

The **Selection of Partition** dialog box of the selected server is displayed.



#### **♦** Selection of Partition

Select the partition to be used as switching partition from the list. GUID of the selected switching partition is displayed. GUID is an identifier used to uniquely identify partitions.

#### ◆ Connect

Connects to the server and obtain the list of partitions.

## Important:

For a partition specified by disk resource, specify the partition on the shared disk that is connected to the filtering configured HBA.

Make sure not to specify a partition specified by disk resource to partition for disk heartbeat resource, or cluster partition or data partition for mirror disk resource. Data on the shared disk may be corrupted.

# Displaying the disk resource properties with the WebManager

- 1. Start the WebManager. (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click an object for a disk resource in the tree view. The following information is displayed in the list view.

Disk Name: sd1	Details
Properties	Value
Name	sd1
Comment	
Drive Letter	X:
Status	Online
Resource Status on Each	n Server
Server Name	Status
server1	Online
server2	Offline

Name: Disk resource name

Comment: Comment

Drive Letter: Drive letter of switching partition

Status: Status of disk resource

Server Name: Server name

Status: Resource status of the given server

If you click the **Details** button, the following information is displayed.

Properties	Value
Туре	sd
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Retry Count at Activation Failure	0
Final Action at Activation Failure	No Operation (Not activate next resource)
Execute Script before Final Action	Off
Retry Count at Deactivation Failure	0
Final Action at Deactivation Failure	Stop the cluster service and shutdown OS
Execute Script before Final Action	Off
Dependent Resources	
Retry Interval at Activation Failure	5
Retry Interval at Inactivation Failure	5

Type: Resource type

Failover Target Server Determination method of failover target server

Failover Threshold: The number of failovers to be made at detection of an

error

Retry Count at Activation Failure: The number of times activation is retried when an

activation error is detected

Final Action at Activation Failure: Final action at an activation error

Execute Script before Final Action: Whether or not script is executed upon activation failure Retry Count at Deactivation Failure: The number of times deactivation is retried when a

deactivation error is detected

Final Action at Deactivation Failure: Final action at a deactivation error

Execute Script before Final Action: Whether or not script is executed upon deactivation

failure

Dependent Resources:
Retry Interval at Activation Failure:
Dependent resource
Activation retry interval
Deactivation retry interval


# **Understanding service resources**

You can register services managed by ExpressCluster and run when starting, stopping, failing over, or moving groups in ExpressCluster. It is also possible to register your own services to service resources.

# Dependencies of service resources

By default, this function depends on the following group resource types.

Group resource type
Floating IP resource
Virtual IP resource
Virtual computer name resource
Disk resource
Mirror disk resource
Hybrid disk resource
Print spooler resource
Registry synchronization resource



# Service resources

A service resource refers to a service managed by the OS service control manager.


## Notes on service resources

Service executed in service resource must be installed on all servers in failover policy.

# Displaying and changing the details of service resource

- 1. From the tree view displayed on the left pane of the Builder, click the icon of the group to which the service resource whose detailed information you want to display and/or change belongs.
- 2. The group resource list is displayed in the table view in the right pane of the window. Right-click the desired service resource name, click **Properties**, and then click **Details** tab.
- **3.** On **Details** tab, you can display and/or change the settings by following the description below.

#### Service resource details tab



Service Name Within 1023 bytes GroupStopRestart

Specify the service name or service display name used in the service resource.


## **Tuning**

Use this button to display the service resource tuning properties dialog box. You can make advanced settings for the service resource.

#### Service resource tuning properties

#### Parameter tab

The detailed setting for parameters is displayed.



## **Synchronous**

When the service is started up, it waits for "Started." Typically, the status changes from "Stopping" to "Started" when the service is started.

When stopping the service, it waits for that the status of service becomes "Stopped." Typically, the status changes from "Stopping" to "Stopped" when the service is stopped.

## Asynchronous

No synchronization is performed.

## Timeout (0 to 9999) SuspendResume

Specify the time-out for the status of the service to become "Started" at the time starting the service. The time-out can be specified only when **Synchronous** is selected. If the status of the service does not change to "Started" within the time-out, it is determined as an error.

Specify the time-out for the stats of the service to become "Stopped" at the time stopping the service. The time-out can be specified only when **Synchronous** is selected. If the status of the service does not change to "Stopped" within the time-out, it is determined as an error.

# Target VCOM Resource Name GroupStopRestart


Configure this to use a virtual computer name as a computer name used for the service resource. The virtual computer name and resource name that exist in a failover group which the service resource belongs to are listed.

#### Initialize

Click **Initialize** to reset the values of all items to their default values.

#### Service tab

The settings for the service are displayed.



**Start Parameters** Within 1023 bytes **GroupStopRestart** 

Specify a parameter for the service. When there are multiple parameters, leave a space between parameters. For a parameter that includes a space, enclose the parameter by double quotation marks. Note that backslash \ cannot be used.

Example: "param 1" param2

# Do not assume it as an error when the service is already started GroupStopRestart

When selected

When the service is started, if the service is already started up, activation status is kept.

When cleared

When the service is started, if the service is already started up, it is considered as activation error.

#### **Initialize**

Click **Initialize** to reset the values of all items to their default values.

### Note:

When Do not assume it as an error when the service is already started is selected, service resources that have the same service name can be registered to multiple groups. In this case, do not configure Target VCOM Resource Name. If it is configured, status of service resources becomes abnormal when multiple groups are started on one server.

# Displaying the service resource properties with the WebManager

- 1. Start the WebManager. (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click an object for service resource in the tree view. The following information is displayed in the list view.

Service Name: service1	Details
Properties	Value
Name	service1
Comment	
Service Name	Sample
Start Parameters	
Status	Online
Resource Status on Each Serve	r
Server Name	Status
server1	Online
server2	Offline

Name: Service resource name Comment: Service resource comment

Service Name: Service name for the service resource

Start Parameters: Start parameter of the service Status: Status of the service resource

Server Name: Server name

Status: Service resource status on the given server

If you click the **Details** button, the following information is displayed in the pop-up dialog.

Properties	Value
Туре	service
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Retry Count at Activation Failure	0
Final Action at Activation Failure	No Operation (Not activate next resource)
Execute Script before Final Action	Off
Retry Count at Deactivation Failure	0
Final Action at Deactivation Failure	Stop the cluster service and shutdown OS
Execute Script before Final Action	Off
Dependent Resources	fip1,sd1
Retry Interval at Activation Failure	5
Retry Interval at Inactivation Failure	5
When service has already started, the error is not caused	No
Target VCOM Name	
[Start]Type	Synchronous
[Start]Timeout (seconds)	1800
[Stop]Type	Synchronous
[Stop]Timeout (seconds)	1800

Type: Resource type

Failover Target Server Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an error

Retry Count at Activation Failure: The number of times activation is retried when an

activation error is detected

Final Action at Activation Failure: Final action at an activation error

Execute Script before Final Action: Whether or not script is executed upon activation failure Retry Count at Deactivation Failure: The number of times deactivation is retried when a

deactivation error is detected

Final Action at Deactivation Failure: Final action when a deactivation error is detected

Execute Script before Final Action: Whether or not script is executed upon deactivation failure

Dependent Resources:

Retry Interval at Activation Failure:

Retry Interval at Inactivation Failure:

Do not assume it as an error when the service is already started:

Check the status of the service when starting the service.

Target VCOM Name: VCOM name that the service uses

[Start]Type: Type of execution when the service is started

[Start]Timeout: Timeout for the service start

[Stopped]Type: Type of execution when stopping the service

[Stopped]Timeout: Timeout for the service stop

# **Understanding print spooler resources**

# Dependencies of print spooler resources

By default, this function depends on the following group resource types.

Group resource type	
Disk resource	
Mirror disk resource	
Hybrid disk resource	

# **Print spooler resources**

Print spooler resources make the printer functions failover by creating a spool directory on the partition of the disk resource or mirror disk resource.


# Notes on print spooler resources

- **Note 1** All servers should use the same printer name, same port and same shared name in their printer definitions and configure the settings for local printer.
- **Note 2** Set the spool directory on a partition of a disk resource or mirror disk resource because the printer spool directory should fail over.

# Displaying and changing the details of print spooler resources

- From the tree view displayed on the left pane of the Builder, click the icon of the group to which the print spooler resource whose detailed information you want to display and/or change belongs.
- The group resource list is displayed in the table view in the right pane of the window.
   Right-click the desired print spooler resource name, click **Properties**, and then click **Details** tab.
- On **Details** tab, you can display and/or change the settings by following the description below.

# Spool resource properties: Details tab



Printer Name Within 220 bytes SuspendResume

Specify the printer name to be used.

Partition Within 7 bytes SuspendResume

Select a drive letter for the spool directory. Select a drive letter on disk resource or mirror disk resource.

Spool Directory Within 244 bytes SuspendResume

Specify a path for the spool directory. Specify a path after the drive letter starting with a back slash \.

Example: \PRINTER\SPOOL

# Displaying the print spooler resource properties with the WebManager

- 1. Start the WebManager. (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click an object for print spooler resource in the tree view. The following information is displayed in the list view.

Print Spooler Name: spool1	Details
Properties	Value
Name	spool1
Comment	
Printer Name	printer1
Partition	F:
Spool Directory	\spool
Status	Online
Resource Status on Each Server	,
Server Name	Status
server1	Online
server2	Offline

Name: Print spooler resource name Comment: Print spooler resource comment

Printer Name: Printer name used for the print spooler resource

Partition: Partition for the spooler directory

Spooler Directory: Spooler directory

Status: Status of the print spooler resource

Server Name: Server name

Status: Print spooler resource status on the given server

If you click the **Details** button, the following information is displayed in the pop-up dialog.

Properties	Value
Туре	spool
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Retry Count at Activation Failure	0
Final Action at Activation Failure	No Operation (Not activate next resource)
Execute Script before Final Action	Off
Retry Count at Deactivation Failure	0
Final Action at Deactivation Failure	Stop the cluster service and shutdown OS
Execute Script before Final Action	Off
Dependent Resources	md1
Retry Interval at Activation Failure	5
Retry Interval at Inactivation Failure	5

Type: Resource type

Failover Target Server Determination method of Failover Target Server Failover Threshold: The number of failovers to be made at detection of an

error

Retry Count at Activation Failure: The number of times activation is retried when an

activation error is detected

Final Action at Activation Failure: Final action at an activation error

Execute Script before Final Action: Whether or not script is executed upon activation

failure

Retry Count at Deactivation Failure: The number of times deactivation is retried when a

deactivation error is detected

Final Action at Deactivation Failure: Final action when a deactivation error is detected Execute Script before Final Action: Whether or not script is executed upon deactivation

failure

Dependent Resources:
Retry Interval at Activation Failure:
Retry Interval at Inactivation Failure:
Dependent resources
Activation retry interval
Deactivation retry interval

# Understanding virtual computer name resources

# Dependencies of virtual computer name resources


By default, this function depends on the following group resource types.

Group resource type
Floating IP resource
Virtual IP resource

# Virtual computer name resources

Client applications can be connected to a cluster server by using a virtual computer name. The servers can be connected to each other by using a virtual computer name. By using a virtual computer name, switching from one server to the other to which a client is connecting remains transparent even if failover or moving of a failover group occurs.

Only client applications on Windows machine can connect to the cluster server by a virtual computer name.



# **Determining virtual computer name**

- A computer name used as a virtual computer name should satisfy the following conditions:
- ◆ The name should be different from cluster server names.
- The name should be different from any computer names of machines connected to the same network segment.
- ◆ The name should be within 15 characters.
- ♦ The name should consist of letters from alphabet, numbers, and/or hyphen.
- ◆ The name is not case-sensitive.

# Linking virtual computer name and floating IP address

Once a virtual computer name is linked with a floating IP address, the combination of the virtual computer name and floating IP address can be written to the client's LMHOSTS file. To configure this, use the Builder. Select **Virtual Computer Name Resource Properties**, and click **Details** tab, and then click **Target FIP Resource Name**. This configuration allows using the virtual computer name from a remote LAN.

If the virtual computer name and floating IP address are not linked, the virtual computer name cannot be used from a remote LAN. WINS needs to be set to use virtual computer names from a remote LAN. For information on how to configure WINS, refer to the next section "Configuring **WINS** server".

# **Configuring WINS server**

To use a virtual computer name from a remote LAN without linking the virtual computer name to a floating IP address, set the WINS server as follows:

- ◆ When installing the WINS server to cluster servers
- 1. Install the WINS server on all servers in a cluster. If you are prompted to reboot the servers after installation, click **No**.
- 2. Configure the settings described from step 3 to 6 on all cluster servers.
- 3. Open Control Panel and double-click Network Connections. Double-click Local Area Connection and open Local Area Connection Properties.
- 4. Click Internet Protocol (TCP/IP) and click Properties.
- 5. Click **Advanced** and click **WINS** tab.
- 6. Add the IP addressees of public LAN in all servers in a cluster to the WINS address (The order of usage does not matter.)
- 7. Shut down and reboot the cluster.
- 8. Install the WINS server on the client on a remote LAN by following the same steps.
- ♦ When setting the WINS server on a server other than a cluster server
- 1. Install WINS server on a server other than a cluster server.
- 2. Open Control Panel and double-click Network Connections. Double-click Local Area Connection and open Local Area Connection Properties.
- 3. Click Internet Protocol (TCP/IP) and click Properties.
- 4. Click **Advanced** and click **WINS** tab.
- 5. In **WINS** addresses, add the IP addresses of WINS server.
- 6. Repeat the steps above for all servers in the cluster.
- 7. Shut down and reboot the cluster.
- 8. Install the WINS server to the client on a remote LAN by following the same steps.

# Services available to the virtual computer name

The following services are available to the virtual computer name:


- ◆ TCP/IP name resolution (from computer name to IP address)
- Network drive connection
- ♦ Network printer connection
- Pipe with the name
- ◆ RPC (pipe with the name, TCP/IP)

# Notes on virtual computer name resources

- Note 1 Create a virtual computer name control process (clpvcomp.exe) per virtual computer name resource to be activated. Make sure not to stop the process by mistake. An error of process disappearance can be detected by virtual computer name monitoring resources.
- **Note 2** The following services are not available to the virtual computer name:
  - 1. Mail slot
  - 2. RPC (NetBIOS)
- **Note 3** Network printer connection cannot be set up from Control Panel. Use the net use command for set up. The net use command displays information related to connecting or disconnecting a computer to shared resources. The command controls network connectivity in the next logon as well. For details on the net use command, refer to the OS Help.
- **Note 4** When the virtual computer name and floating IP address are not linked, the following needs to be considered:
  - In the x64 environment, the configuration where the virtual computer name and the floating IP address are not linked is not supported.

    Do not forget to link them in the x64 environment.
  - When using the virtual computer name from Windows 98 or Windows Me client, install ExpressCluster Client and configure client settings.
  - It may take a few minutes to reconnect to the cluster after failover due to a failure of the server. This can be avoided by installing the ExpressCluster Client and configuring client settings.
  - It may take a few minutes to display the virtual computer name in the network computer after the cluster is started.
  - · The virtual computer name cannot be written to LMHOSTS.
  - When you have the settings to use a DNS server and the DNS server is associated with WINS, switching by failover cannot be done while cache information of the virtual computer name remaining on the DNS server. Configure the time to retain cache for WINS to approximately 1 second on the DNS server.
- **Note 5** The NetBEUI protocol cannot be used if the virtual computer name and floating IP address are linked.
- **Note 6** Multiple virtual computer names cannot be liked to the same floating IP.
- **Note 7** To register a virtual computer name with the WINS server on a remote network, configure the following settings in cluster servers:

- 1. Open Control Panel, and double-click Network Connections
- 2. From the menu, click **Advanced**, and then click **Advanced Settings**. Select **Adapters** and **Bindings** tab.
- **3.** Change the order of the BindPath. The public LAN (the network adapter with which the WINS server address is registered) should be on the top. **Adapters and Bindings** tab should look similar to the following:



**Note 8** Communication by file sharing protocol (SMB/CIFS) using a virtual computer name owned by an activated group on the active server may fail due to an authentication error. Follow the procedures below to avoid the problem from occurring.

# (Example 1)

The Explorer is started in the server where the group is active and the following address is entered in the address bar. However it results in causing an authentication error and cannot open the shared folder.

<Virtual computer name>/shared name

### (Example 2)

In a server where the group was active, started the registry editor and specified the virtual computer name in "Connect Network Registry," but failed due to authentication error.

- <Concerned OS>
- Every edition of Windows Server 2003
- <Workaround>
- 1. Verify that the all servers are properly working from the WebManager.
- **2.** Execute Steps 3 to 7 below in each server in the cluster.
- 3. From the **Start** menu, select **Run**, and run regedit.exe and add the following registry value:

 $HKEY\_LOCAL\_MACHINE \\ SYSTEM \\ Current Control Set \\ Services \\ lanman server \\ parameters$ 

Name (Type):

DisableStrictNameChecking (DWORD type)

Value:

0x1

**4.** If the following value exists in the following key, delete it:


Key:

HKEY\_LOCAL\_MACHINE\SYSTEM\CurrentControlSet\Control\Lsa\MSV1\_0 Name (Type):

BackConnectionHostNames (DWORD type)

5. Create a new multi-line string value for the same the name in Step 4 (BackConnectionHostNames), and set a virtual computer name.

(Example) when there are two virtual computer names: vcom1 and vcom2



- **6.** Close the registry editor.
- 7. (applicable only when the virtual computer name and the floating IP address are linked)

In the system drive: \Windows\system32\drivers\etc\hosts, add an entry of the virtual computer name (not FQDN name but computer name only) and the linked floating IP address. When there are multiple virtual computer names linked with floating IP address, add entries for all of them.

(Example) when the virtual computer name is "vcom1" and the linked floating IP address is "10.1.1.11":

Add the following to the hosts file: 10.1.1.11 vcom1

**8.** Execute Steps 3 to 7 above in all servers. Then shut down the cluster and reboot all servers.

Note 9 Notes on registering a virtual computer name with DNS dynamically


- 1. Cluster server must be assigned in the domain.
- 2. DNS must be configured for the public LAN. ExpressCluster registers virtual computer name specified by public LAN with DNS.
- **3.** DNS registration is performed when virtual computer name resource is activated. Failure of registration will not be recognized as an error.
- **4.** A virtual computer name is deleted from DNS when virtual computer name resource is deactivated. Failure of deletion will not be recognized as an error.

- **Note 10** On Windows Server 2008, virtual computer name resource cannot be activated on the NIC that LAN cable is not connected.
- **Note 11** When Server service of OS is stopped, virtual computer name resource cannot be activated. If you want to use virtual computer name resource, do not disable/stop Server service.

# Displaying and changing the details of virtual computer name resource

- 1. From the tree view on the left pane of the Builder, click the group icon where the virtual computer name resource whose details you want to display and/or change belongs.
- 2. The group resource list is displayed in the table view in the right pane of the window. Right-click the desired virtual computer resource name, click **Properties**, and then click **Details** tab.
- 3. On **Details** tab, you can display and/or change the settings by following the description below.

### Virtual computer name resource details tab



Virtual Computer Name Within 15 bytes SuspendResume GroupStopRestart

Specify the virtual computer name.

Target FIP Resource Name SuspendResume GroupStopRestart

Select the floating IP resource name to be linked to the virtual computer name.


#### **Tuning**

Display the virtual computer name resource tuning properties dialog box to configure the details of virtual computer name resource.

# **Virtual Computer Resource Tuning Properties**

#### Parameter tab

Display the details of setting the parameter.



# Register with DNS dynamically SuspendResume GroupStopRestart

Specify whether or not to register with DNS dynamically during activation of resource.

# IP address to be associated SuspendResume GroupStopRestart

Select one of the followings as IP address for registration with DNS dynamically to associate with virtual computer name.

- FIP
  - Associates the floating IP address in selected in the target FIP resources name.
- Public

Associates the public LAN address of a server to activate resources.

Any Address

Associates any IP address you want on a server basis.

# Edit SuspendResume GroupStopRestart

When **Any Address** is selected for IP address to be associated, select your target server in **Servers**. Click **Edit** to specify an IP address on a server basis.

# Initialize

Click this button to configure default values for all options.

# Displaying the virtual computer name resource properties with the WebManager

- 1. Start the WebManager. (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click an object for virtual computer name resource in the tree view. The following information is displayed in the list view.

Virtual Computer Name Name: v	com1 Details
Properties	Value
Name	vcom1
Comment	
Virtual Computer Name	server5
Target FIP Name	fip1
Status	Online
Resource Status on Each Server	r
Server Name	Status
server1	Online
server2	Offline

Name: Virtual computer name resource name

Comment: Comment for the virtual computer name resource

Virtual Computer Name: Virtual computer name

Target FIP Resource Name: Floating IP resource to be linked to the virtual computer name

Status: Status of the virtual computer name resource

Server Name: Server name

Status: Status of the virtual computer name resource on the given server

If you click the Details button, the following information is displayed in the pop-up dialog.

Properties	Value
Туре	vcom
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Retry Count at Activation Failure	5
Final Action at Activation Failure	No Operation (Not activate next resource)
Execute Script before Final Action	Off
Retry Count at Deactivation Failure	0
Final Action at Deactivation Failure	Stop the cluster service and shutdown OS
Execute Script before Final Action	Off
Dependent Resources	fip1
Retry Interval at Activation Failure	5
Retry Interval at Inactivation Failure	5

Type: Resource type

Failover Target Server Determination method of Failover Target Server Failover Threshold: The number of failovers to be made at detection of an

error

Retry Count at Activation Failure: The number of times activation is retried when an

activation error is detected

Final Action at Activation Failure: Final action at an activation error

Execute Script before Final Action: Whether or not script is executed upon activation

failure

Retry Count at Deactivation Failure: The number of times deactivation is retried when a

deactivation error is detected

Final Action at Deactivation Failure: Final action when a deactivation error is detected Execute Script before Final Action: Whether or not script is executed upon deactivation

failure

Dependent Resources:
Retry Interval at Activation Failure:
Retry Interval at Inactivation Failure:
Dependent resources
Activation retry interval
Deactivation retry interval


# **Understanding virtual IP resources**

# **Dependencies of virtual IP resources**

By default, this function does not depend on any group resource type.

# **Virtual IP resources**

Client applications can be connected to a cluster server by using a virtual IP address. The servers can be connected to each other by using a virtual IP address. By using a virtual IP address, switching from one server to the other to which a client is connecting remains transparent even if failover or moving of a failover group occurs. The graphic in the next page shows how virtual IP resources work in the cluster system.



# **Determining virtual IP address**

An IP address used as a virtual IP address should satisfy the following conditions:

- The IP address should not be within the network address of the LAN to which the cluster belongs.
- The IP address should not conflict with existing network addresses.

Select one of the following allocation methods to meet the requirements above:

- Obtain a new network IP address for virtual IP address and allocate virtual IP address.
- ◆ Determine a network IP address from private IP address space and allocate virtual IP address. The following procedures are given as an example.
  - · Select one network address from 192.168.0 to 192.168.255 for virtual IP address.
  - · Allocate up to 64 host IP addresses for virtual IP address from the network address you have selected. (For example, select the network address 192.168.10 and allocate two host IP addresses: 192.168.10.1 and 192.168.10.254)
  - Specify 255.255.255.0 to net mask of the virtual IP address.
  - Private IP addresses are addresses for a closed network and they cannot be accessed using virtual IP address from outside of the network through internet providers.
  - Do not disclose path information of private IP addresses outside the organization.
  - · Adjust the private IP addresses to avoid conflict with other address.

# **Controlling path**

To access to a virtual IP address from a remote LAN, path information of the virtual IP address must be effective to all routers on the path from the remote LAN to the LAN for cluster server. To be specific, the following condition must be satisfied:

- Routers on the cluster servers LAN interpret host RIP.
- Routers on the path from a cluster server to the remote server have the dynamic routing settings or information on the virtual IP address routes has configured as static routing settings.

# Requirement to use virtual IP address

# Environments where virtual IP address can be used

Virtual IP addresses can be accessed from the machines listed below. Virtual IP address mechanism functions properly even in a LAN where switching hubs are used. However, when a server goes down, TCP/IP that has been connected will be disconnected.

When using virtual IP addresses with a switching HUB that cannot be configured to create a host routing table by receiving host RIP, you need to reserve one new network address and configure virtual IP addresses so that the IP address of each server belongs to a different network address.

♦ Cluster servers that belong to the same LAN that the server the virtual IP activates belongs to

Virtual IP addresses can be used if the following conditions are satisfied:

· Machines that can change the path by receiving RIP packets.

 Machines that can resolve the path information of a virtual IP address by accessing a router.

# ♦ Cluster servers that belong to a different LAN that the server the virtual IP activates belongs to

Virtual IP addresses can be used if the following condition is satisfied:

Machines that can resolve path information of the virtual IP address by accessing a router

#### ♦ Clients that belong to the same LAN that cluster servers belong to

Virtual IP addresses can be used if the following conditions are satisfied:

- · Machines that can change the path by receiving RIP packets.
- Machines that can resolve the path information of a virtual IP address by accessing a router.

#### ♦ Clients on the remote LAN

Virtual IP addresses can be used if the following condition is satisfied:

 Machines that can resolve path information of the virtual IP address by accessing a router.

# **Notes on IP resources**

Virtual IP addresses do not support NetBIOS protocol.

- ◆ Even if you map a virtual IP address to a host name using LMHOSTS, it cannot be used for accessing and user authentication for Windows browsing, networks, and printer resources.
- ◆ Use a virtual computer name to automatically switch the connection destination with the NetBIOS protocol.

The following rule applies to virtual IP addresses.

- The number of a virtual IP resource to be registered on one cluster system is up to 64.
- ◆ To use a virtual IP resource, the names of a cluster, server and group need to be set according to the naming rules of Ver8.0 or earlier.

Adjust the value of the flush timer of the router within the value for heartbeat timeout. See "Timeout tab" in "Chapter 3 Function of the Builder" for details on heartbeat timeout.

# Displaying and changing the details of virtual IP resource

- 1. From the tree view on the left pane of the Builder, click the group icon where the virtual IP resources whose details you want to display and/or change belong.
- 2. The group resource list is displayed in the table view in the right pane of the window. Right-click the desired virtual IP resource name, click **Properties**, and then click **Details** tab.
- 3. On **Details** tab, you can display and/or change the settings by following the description below.

# [ vip1 ] Resource Properties Info Dependency Settings Details Common server1 server2 IP Address 192.168.13.144 255.255.255.0 Net <u>M</u>ask **Destination IP Address** 192.168.16.255 Source IP Address 30 **sec** Send Interval Use Routing Protocol Routing Protocol RIPngver1 RIPngver2 RIPngver3 RIPver1 RIPver2 Tuning ОК Cancel Apply

#### Virtual IP resource details tab

IP Address Within 45 bytes GroupStopRestart

Enter the virtual IP address to use.

Net Mask Within 45 bytes GroupStopRestart

Specify the net mask of the virtual IP address to use. It is not necessary to specify it when the IPv6 address is specified as a virtual IP address.

**Destination IP Address** (within 45 bytes) GroupStopRestart

Enter the destination IP address of RIP packets. The broadcast address is specified for IPv4 and the multicast address is specified for IPv6.

# Source IP Address (within 45 bytes) GroupStopRestart

Enter the IP address to bind for sending RIP packets. Specify the actual IP address activated on NIC which activates the virtual IP address.

**Note:** The source IP address should be set on a server basis, and set the actual IP address of each server. Virtual IP resources do not operate properly if a source address is invalid.

# Send Interval (1 to 30) GroupStopRestart

Specify the send interval of RIP packets.

# Use Routing Protocol (1 to 30) GroupStopRestart

Specify the RIP version to use. For IPv4 environment, select RIPver1 or RIPver2. For IPv6 environment, select RIPngver1 or RIPngver2 or RIPngver3. You can select one or more routing protocol.


#### **Tuning**

Use this button to display the **Virtual IP Resource Tuning Properties** dialog box. You can make advanced settings for the virtual IP resource.

# **Virtual IP Resource Tuning Properties**

#### Parameter tab

Detailed setting for parameter is displayed.



# Run ping

Use this button to configure whether or not to check if there is any overlapped IP address by the ping command before activating the virtual IP resource.

- When selected Check by using the ping command.
- When cleared Do not check by using the ping command.

# ping

In this box, make detailed settings of the ping command used to check for any overlapped IP address before activating the virtual IP resource.

• Interval (0 to 999) SuspendResume
Specify the interval to issue the ping command in seconds.


- Timeout (1 to 999999) SuspendResume
  Specify the time-out for the ping command in milliseconds.
- Retry Count (0 to 999) SuspendResume
  Specify how many retries of issuing the ping command are attempted.
- VIP Forced Activation
  Use this button to configure whether to forcibly activate the virtual IP address when an overlapped IP address is found using the ping command.
  - · When selected Forcefully activate the virtual IP address.
  - When cleared Do not forcefully activate the virtual IP address.

#### **Initialize**

Click **Initialize** to reset the values of all items to their default values.

# RIP tab

Detailed settings on RIP of virtual IP resource are displayed.



# Next Hop IP Address GroupStopRestart

Enter the next hop address (address of the next router). Next hop IP address can be omitted. It can be specified for RIPver2 only. You cannot specify a netmask or prefix.

# Metric (1 to 15) GroupStopRestart


Enter a metric value of RIP. A metric is a hop count to reach the destination address.

# Port GroupStopRestart

On Port Number, a list of communication ports used for sending RIP is displayed.

#### Add

Add a port number used for sending RIP. Click this button to display the dialog box to enter a port number.



#### **Port Number**

Enter a port number to be used for sending RIP, and click **OK**.

# Delete


Click **Delete** to delete the selected port on the **Port Number**.

# Edit

A dialog box to enter a port number is displayed. The port selected in the **Port Number** is displayed. Edit it and click  $\mathbf{OK}$ .

# RIPng tab

Detailed settings of RIPng of virtual IP resource are displayed.



# Metric (1 to 15) GroupStopRestart


Enter a metric value of RIPng. A metric is a hop count of RIPng to reach the destination address.

# Port GroupStopRestart

On **Port Number**, a list of ports used for sending RIPng is displayed.

#### Add

Add a port number used for sending RIPng. Click this button to display the dialog box to enter a port number.



#### **Port Number**

Enter a port number to be used for sending RIPng, and click **OK**.

#### Remove


Click **Remove** to delete the selected port on the **Port Number**.

# **Edit**

A dialog box to enter a port number is displayed. The port selected in the **Port Number** is displayed. Edit it and click **OK** 

# Displaying the virtual IP resource properties with the WebManager

- 1. Start the WebManager. (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click an object for virtual IP resource in the tree view. The following information is displayed in the list view.



Name: Virtual IP resource name

Comment: Comment for the virtual IP resource IP Address: IP address of the virtual IP resource Subnet Mask: Subnet mask of the virtual IP resource

Destination IP Address:

Source IP Address:

Source IP Address:

Source IP Address of RIP for virtual IP resource

Send Interval:

Interval of RIP sending for virtual IP resource

Routing Protocol: RIP version for virtual IP resource Status: Status of the virtual IP resource

Resource Status on Each Server	
Server Name Status	
server1	Online
server2	Offline

Server Name: Server name

Status: Status of the virtual IP resource on the given server

If you click the **Details** button, the following information is displayed in the pop-up dialog.

Properties	Value
Туре	vip
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Retry Count at Activation Failure	5
Final Action at Activation Failure	No Operation (Not activate next resource)
Execute Script before Final Action	Off
Retry Count at Deactivation Failure	0
Final Action at Deactivation Failure	Stop the cluster service and shutdown OS
Execute Script before Final Action	Off
Dependent Resources	
Retry Interval at Activation Failure	5
Retry Interval at Inactivation Failure	5
Ping Execute	On
Ping Timeout (milliseconds)	1000
Ping Retry Threshold	5
Ping Retry Interval (seconds)	1
VIP Force Activation	Off
RIP Next Hop IP Address	
RIP Metric	3
RIP Port Number	520
RIPng Metric	1
RIPng Port Number	521

Type: Resource type

Failover Target Server

Failover Threshold:

Determination method of Failover Target Server
The number of failovers to be made at detection of an

error

Retry Count at Activation Failure: The number of times activation is retried when an

activation error is detected

Final Action at Activation Failure: Final action at an activation error

Execute Script before Final Action: Whether or not script is executed upon activation

failure

Retry Count at Deactivation Failure: The number of times deactivation is retried when a

deactivation error is detected

Final Action at Deactivation Failure: Final action when a deactivation error is detected Execute Script before Final Action: Whether or not script is executed upon deactivation

failure

Dependent Resources:
Retry Interval at Activation Failure:
Retry Interval at Inactivation Failure:
Dependent resources
Activation retry interval
Deactivation retry interval

Ping Execute: Issue the ping command to verify overlapped IP

address

Ping Timeout (Millisecond):

(millisecond)

Ping Retry Threshold: Threshold value for retrying the ping command Ping Retry Interval (Second): Retry interval for the ping command

VIP Forced Activation: Forcibly activate the virtual IP resource

RIP Next Hop Ip Address: Next hop address of RIP

RIP Metric:
RIP Port Number:
RIP port number
RIPng Metric:
RIPng Port Number:
RIPng port number
RIPng port number

Timeout for the ping command

# **Understanding CIFS resources**

# **Dependencies of CIFS resources**

By default, CIFS resources depend on the following group resources type:

Group resource type
Disk resource
Mirror disk resource
Hybrid disk resource

# **CIFS** resources

CIFS resources control publicizing and removal of shared folders. By using CIFS resources, the folders on shared disks and mirror disks are publicized as a shared file.

There are two ways of publicizing as follows:

# Specify shared configuration individually

Specify shared folder configuration in advance in configuration items of CIFS resources, and then publicize shared folder with the configuration specified at resource activation. You need to create CIFS resource per shared folder to be publicized.

#### Auto-save shared configuration of drive

When a specified folder on shared disk/mirror disk is shared and publicized, acquire the shared configuration and save it in the configuration file of shared disk/mirror disk. The shared configuration is once released when shared disk/mirror disk is deactivated, but the shared folder is publicized again with the saved configuration.

# **Notes on CIFS resources**

When files on the shared disks or the mirror disks are publicized, the sharing settings, which are configured by right-click, will be cleared by deactivation of disk resource or mirror disk resource, which will result in no inheritance to another server at a failover. In this case, publicize and delete the shared folders by using the ARMNSADD and ARMNSDEL commands from scrip resource, or use CIFS resources.

When shared configuration of drive is automatically saved, shared configuration file configured as the saving destination is created as a hidden file. For the back up when the shared configuration file is corrupted, a file with ".bak" at the end of the specified file name is created in the same folder. Ensure not to use the same file name with the currently existing file.


A folder that the shared configuration file is to be created must have access permission to create/update a file for the local system account (SYSTEM). Without proper access permission, creation/updating of the shared configuration file fails. If both the shared configuration file and the backup file are deleted mistakenly, configuration data may be lost. It is recommended that these files should not be deleted by other account.

# Displaying and changing the details of CIFS resources

From the tree view displayed on the left pane of the Builder, click the icon of the group to which the CIFS resource whose detailed information and settings you want to display and/or change belongs.

- 1. The group resources list is displayed on the table view in the right of the window. Right-click the desired CIFS resource name, and click **Properties.** In the properties dialog box, click the **Details** tab.
- **2.** Display and/or change the detailed settings on the **Details** tab as shown below.

#### CIFS resource Details tab



#### Execute the automatic saving of shared configuration of drive GroupStopRestart

Configure whether to save shared configuration of drive automatically. Check this when you want to set the auto-saving.

# Target Drive GroupStopRestart

Specify the drive letter of the target disk when you want to execute auto saving of shared configuration of drive.

#### Shared Configuration File (within 255 bytes) GroupStopRestart

Specify the file that saves shared configuration of drive with full path. You need to specify a path of shard disk/mirror disk/hybrid disk within the same group.

The following configurations are executed when specifying shared configuration individually.

Shared name Within 80bytes GroupStopRestart

Specify the name of the shared folder, which is publicized by using CIFS resource.

Folder Within 255bytes GroupStopRestart

Specify the full path to the shared folder, which is publicized by CIFS resources.

Comment Within 256bytes GroupStopRestart

ExpressCluster X 2.1 for Windows Reference Guide

Specify the comment of the shared folder, which is publicized by using CIFS resource.


# **Tuning**

Display CIFS resource tuning properties dialog box. You can change the settings of the detail information of the CIFS resource.

# **CIFS** resource tuning properties

# Cache tab

Display the details of cache



# Allow caching GroupStopRestart

Set to enable the caching of shared folders.

# Settings GroupStopRestart

Select the caching settings if you choose to allow caching.

Choose one of the following settings.


- Auto Caching
- Manual Caching
- Auto Caching (Optimized for the performance)

### **Initialize**

Click the **Initialize** button to initialize all the items to the default value.

#### User tab

Display the detailed settings of restriction of the number of users and permission of access.



User Limit (1 to 9999) GroupStopRestart

Set the maximum number of users who can access the shared folder at a time.

# Add GroupStopRestart

Add the settings of access permission for user account or user group to **Access Permission**. When you click this button, the **Enter user** dialog box is displayed. Specify the user name and the permission.

# Remove GroupStopRestart

Delete the access permission selected in **Permissions**.

# Edit GroupStopRestart

Modify the access permission specified in **Permissions**. The **Enter user** dialog box is displayed. The specified access permission displayed in the **Enter user** allows you to modify permission.

# Initialize

Click the **Initialize** button to initialize all the items to the default values.



**User Name** (Within 256 bytes)

Enter the Window User name or a group name. When using a domain account, enter in the format of "Domain name\User Name"

## **Permission**

Select one of following settings for access permission of the entered user/group.

- Full control
- Change
- Read
- None

When **Off** is selected, access is denied.

# Displaying CIFS resource properties with the WebManager.

**1.** Start WebManager.

(http://FIP\_address\_for\_the\_WebManager\_group:port\_number (Default value is 29003.)

2. Click the object for CIFS resource in the tree view. The following information is displayed in the list view.

Properties	Value
Name	cifs
Comment	
Share Name	share
Path	Z:\share
Drive Administration	Off
Drive	Z:
Config File Path	Z:\share_config\share_config_date.conf
Status	Online

Name: CIFS resource name
Comment: CIFS resource comment

Share Name: Name of the shared folder publicized by CIFS resource

Path: Path to the shared folder publicized by CIFS resource

Drive Administration: Execute auto-saving of shared configuration

Drive: Target drive to execute auto-saving of shared configuration

File paths: File path to save share configuration

Status: Status of CIFS resource

Resource Status on Each Server	
Server Name	Status
server1	Online
server2	Offline

Server Name: Server name

Status: Status of CIFS resource on the given server

If you click the **Details** button, the following information is displayed in the pop-up dialogue.

Properties	Value
Туре	cifs
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Retry Count at Activation Failure	0
Final Action at Activation Failure	No Operation (Not activate next resource)
Execute Script before Final Action	Off
Retry Count at Deactivation Failure	0
Final Action at Deactivation Failure	Stop the cluster service and shutdown OS
Execute Script before Final Action	Off
Dependent Resources	md1
Retry Interval at Activation Failure	5
Retry Interval at Inactivation Failure	5
Comment	
User Limit	Maximum Allowed
Client-side Cache	On
CSC Method	Automatic Cashing (Optimized for performance)

Type: Resource type

Failover Target Server Determination method of Failover Target Server The number of failovers to be made at detection of an Failover Threshold:

Retry Count at Activation Failure: The number of times activation is retried when an

activation error is detected

Final Action at Activation Failure: Final action at an activation error

Execute Script before Final Action: Whether or not script is executed upon activation

failure

Retry Count at Deactivation Failure: The number of times deactivation is retried when a

deactivation error is detected Final action when a deactivation error is detected

Final Action at Deactivation Failure:

Execute Script before Final Action

Whether script is executed upon deactivation failure

Dependent Resources: Dependent resources Retry Interval at Activation Failure: Activation retry interval Retry Interval at Inactivation Failure: Deactivation retry interval

Comment: Comment of the shared folder publicized by CIFS

resource

User Limit: Maximum number of users that can simultaneously

connect to the shared folder publicized by CIFS

resource.

Client -side Cache: Whether or not to cache of the shared folder

publicized by CIFS resource

CSC Method: Cache method of the shared folder publicized in CIFS

resource

# **Understanding NAS resources**

## **Dependencies of NAS resources**

By default, NAS resources depend on the following group resources types:

Group resource type
Floating IP resource
Virtual IP resource

#### **NAS** resources

NAS resources control mounts / unmounts of a network drive. By storing data required for business operation on the network drive mounted by NAS resources, the data is taken over to the other servers in the case of failover or transfer of fail groups.


#### **Notes on NAS resources**

- NAS resources mount a network drive by local system account. Because applications and scripts activated by the application resources or script resources are executed in the local system unless otherwise specified, they can access this network drive. However applications with no permission to access the shared folder mounted as the network drive cannot access the network drive mounted by NAS resources.
- ♦ When multiple NAS resources mount the shared folders on the same file server, the same name should be configured as the account to access the file server.
- ◆ For the applications (databases) for which orders for the orders to disks and completion of writing should be assured the network drive may not be used as storage for data files.
- ◆ The network drive mounted by NAS resource is displayed as **Disconnected Network Drive** in **My computer** on explorer. The connection account information configured by NAS resources is not taken over to the logon session except local system account. When the login account has no right to the target shared folders, you cannot access this network drive from explorer unless you explicitly specify the connecting account to the server that has the shared folders.

## Displaying and changing NAS resources

- 1. From the tree view displayed on the table view in the right of the window. Click the icon of the group to which the NAS resources whose detailed information and settings you want to display and/ or change belong.
- **2.** The group resources list is displayed on the table view in the right of the window. Right-click the desired NAS resource name, and click **Properties**. In the properties dialog box, click the **Details** tab.
- **3.** Display and/or change the detailed settings on the **Details** tab as shown below.

#### NAS resource details tab



#### Drive GroupStopRestart

Specify the drive letter of the network to be mounted by NAS resource.

Folder (Within 260 bytes) GroupStopRestart

Specify the shared folder mounted by NAS resource in the UNC format.

User Name (Within 96 bytes) GroupStopRestart

Specify the user name of the account required to mount shared folders by NAS resources.

Password (Within 96 bytes) GroupStopRestart

Specify the account password required to mount shared folders by NAS resource.


#### **Tuning**

Display NAS resource tuning properties dialog to set the details of NAS resource.

#### NAS resource tuning properties

#### Disconnect

Display the details about mounting of network drive.



Retry Count (1 to 999) GroupStopRestart

Specify the number of times to retry when failed to unmount.

Retry Interval (1to 999) GroupStopRestart


Specify the retry intervals when failed to unmount.

#### Initialize

Click the **Initialize** button to initialize all the items to the default values.

# Displaying NAS resource properties with the WebManager

- **1.** Start WebManager. (http://FIP\_address\_for\_the\_WebManager\_group: port\_number(Default value is 29003))
- 2. Click the object for NAS resource, in the tree view, the following information is displayed in the list view.



Name: NAS resource name

Comment of NAS resource

Drive: Drive letters for network drive mounted by NAS resource

Network Resource: Shared folders mounted by NAS resource

Status: Status of NAS resource

Resource Status on Each Server		
Server Name	Status	
server1	Online	
server2	Offline	

Server Name: Server name

Status: Status of NAS resource on the given server

If you click the **Details** button, the following information is displayed in the pop-up dialogue.

Properties	Value
Type	nas
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Retry Count at Activation Failure	0
Final Action at Activation Failure	No Operation (Not activate next resource)
Execute Script before Final Action	Off
Retry Count at Deactivation Failure	0
Final Action at Deactivation Failure	Stop the cluster service and shutdown OS
Execute Script before Final Action	Off
Dependent Resources	fip1
Retry Interval at Activation Failure	5
Retry Interval at Inactivation Failure	5
User Name	CLUSTER\CLUSTER
Disconnect Retry Threshold	3
Disconnect Retry Interval (seconds)	5

Type: Resource type

Failover Target Server: Determination method of failover server

Failover Threshold: The number of failovers to be made at detection of an

error

Retry Count at Activation Failure: The number of times activation is retried when an

activation error is detected

Final Action at Activation Failure: Final action at an activation error

Execute Script before Final Action: Whether or not script is executed upon activation failure Retry Count at Deactivation Failure: The number of times deactivation is retried when a

deactivation error is detected

Final Action at Deactivation Failure: Final action when a deactivation error is detected

Execute Script before Final Action: Whether or not script is executed upon deactivation

failure

Dependent Resources:
Retry Interval at Activation Failure:
Retry Interval at Inactivation Failure:
Dependent resources
Activation retry interval
Deactivation retry interval

User name: Account user name to mount shared folders in NAS

resource

Disconnect Retry Threshold: The number of retires to be performed when unmounting

fails

Disconnect Retry Interval (Second): Interval between retires that are performed when

unmounting fails


# **Understanding hybrid disk resources**

## Dependencies of hybrid disk resources

By default, hybrid disk resources do not depend on any group resource type.

### **Hybrid disk**

A hybrid disk resource is a resource in which disk resource and mirror disk resource are combined. When you use a disk resource, a failover group can perform failover only to the cluster server connected to the same shared disk. On the other hand, in hybrid disk, by mirroring the data in the shared disk, failover can be performed to a server which is not connected to the shared disk. This enables configuring a remote cluster as in the following figure, where failover is performed in the active site upon normal failure, while failover can be performed to the stand-by site when a disaster occurs.



In hybrid disk, a group of servers that is connected to the shared disk is referred to as a server group. Disk mirroring is performed between two server groups. A server which does not use the shared disk is a server group in which there is only one server.

Like mirror disk resources, mirroring takes place in each partition, where RAW partition (cluster partition) to record management information is required as well as data partition which is the mirroring target. It is necessary that each server using hybrid disk resource has a license for ExpressCluster X Replicator DR 2.0/2.1 for Windows.

# Notes on hybrid disk

◆ Data partition size

The sizes of data partitions to be mirrored need to be exactly the same by byte.

If the type or geometry of the disks differs, you may fail to configure the same size for partitions. If this happens, check the precise size of data partitions of the servers by the clpvolsz command before configuring hybrid disk resource. If the sizes are not consistent, run the clpvolsz command again to contract the larger partition.

For more information on the clpvolsz command, see "Chapter 4 ExpressCluster command reference".

Although there is no limit for data partition size, upon fully copying at the time of initial construction or disk replacement, too large data size will degrade the maintenance performance since the required time increases in proportion to the size. For this reason, we recommend data partition size of 100GB or smaller in total.

#### Cluster partition size

Reserve at least 17MB. In some disk geometry it may be 17MB or larger, which is not a problem.

#### ◆ Partition drive letter

Specify the same drive letters in each server for data partition and cluster partition.

Do not change the drive letter until deleting resources after configuring hybrid disk resources. If a drive letter has been changed, restore the drive letter when hybrid disk resource is started. When the original drive letter is used by other partition, starting mirror disk resource fails.

#### Partition allocation

When a data partition on the shared disk is mirrored, the data partition and the cluster partition need to be allocated on the same shared disk (they do not have to be allocated on the same logical disk).

Allocate the data partition and the cluster partition on a basic disk in the MBR format. Dynamic disk is not supported.

When making data partitions as logical partitions on the extended partition, make sure the data partitions are logical partition on both servers. The actual size may be slightly different even the same size is specified on both basic partition and logical partition.

#### Partition format

Format a data partition by NTFS. FAT/FAT32 is not supported.

It is not necessary to construct a file system in a cluster partition. Do not format it.

#### ◆ Access control of a data partition

The data partition to be mirrored by a hybrid disk resource can be accessed only from the active server where a hybrid disk resource is activated. Access from other servers is restricted by ExpressCluster.

Access to the cluster partition is also restricted by ExpressCluster.

#### ◆ Partition deletion


When you delete a data partition or cluster partition on the hybrid disk resource, delete the hybriddisk resource in Builder in advance.

#### Server group settings

In a failover group having hybrid disk resource, it is necessary to register two server groups which are mirrored by the hybrid disk resource in the **Server Groups** tab of **Group Properties.** Configure the settings for these server groups in **Server Groups** in the tree view in Builder.

# Displaying / changing the details of hybrid disk

- 1. Click the icon of the group to which the hybrid disk belongs.
- 2. The list of group resources is displayed in the table view in the right pane of the screen. Click the desired hybrid disk resource name, and then the **Details** tab in **Properties**.
- **3.** In the **Details** tab, display / change the details settings according to the following description.



Hybrid disk resource details tab

#### Hybrid disk number

Select a disk number to be allocated to a hybrid disk resource. This number must be different from the ones for other hybrid disk resources and mirror disk resources.

#### **Data partition drive letter** (within 1023 bytes)

Specify the drive letter for the data partition.

#### Cluster partition drive letter (within 1023 bytes)

Specify the drive letter for the cluster partition. Multiple hybrid disks can use the same cluster partition, but it cannot be the cluster partition of the mirror disk resource.

#### **Cluster Partition Offset Index**

Select an index number for the area used in the cluster partition. When using the multiple hybrid disks, assign different numbers for hybrid disk so that the areas to be used in the cluster partition do not overlap.

#### Server groups

Information on each member server of the two server groups selected in the **Server Groups** tab in **Properties** of failover groups is displayed.

When you click the **Obtain information** button while Builder is online, GUID information of data and cluster partitions of each server can be acquired.

#### **Tuning**

The **Hybrid Disk Resource Tuning Properties** dialog box is displayed. You can configure the details on hybrid disk resources.


# **Tuning hybrid disk resources**

In the tree view in the left pane of Builder, click the icon of the group to which the hybrid disk resource you want to display the detailed information or change the settings belongs.

- 1. The list of group resources is displayed on the table view in the right pane of the screen. Click the desired hybrid disk resource name, and then the **Details** tab in **Properties**.
- 2. In the **Details** tab, click **Tuning**.
- **3.** The **Hybrid Disk Resource Tuning Properties** is displayed. Display / change the detailed settings according to the following description.

#### Mirror tab

Detailed settings on mirror are displayed.



Parameters on this configuration window are the same as those of mirror disk resources.

For information on what the parameters indicate and how to configure the settings, see "Understanding mirror disk resources" (P.447).

# Displaying hybrid disk resource properties with WebManager

- **1.** Start WebManager (http://WebManager floating IP address for groups: port number (default value 29003)).
- 2. Click the object of hybrid disk resource in the tree view. The following is displayed in the list view:

Hybrid Disk Name: hd		Details		
Common	servei	r1	server2	
Propertie	es			
Name		hd		
Comment				
Hybrid Disk N	lo.	1		
Drive Letter		Ζ		
Status		Or	nline	

Name: Hybrid disk resource name Comment: Hybrid disk resource comment

Hybrid Disk No.: Hybrid disk number

Drive Letter: Drive letters of the data partition Status: Status of the hybrid disk resource

Resource Status on Each Server	
Server Name	
server1	Offline
server2	Online

Server name: Server name

Status: Hybrid disk resource status in the server

If you click the **Details** button, the following is displayed.

Properties	Value
Туре	hd
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Retry Count at Activation Failure	0
Final Action at Activation Failure	No Operation (Not activate next resource)
Execute Script before Final Action	Off
Retry Count at Deactivation Failure	0
Final Action at Deactivation Failure	Stop the cluster service and shutdown OS
Execute Script before Final Action	Off
Dependent Resources	
Retry Interval at Activation Failure	5
Retry Interval at Inactivation Failure	5
Cluster Partition - Drive Letter	W
Cluster Partition - Offset Index	0
Initial Mirror Construction	On
Mode	Synchronous
Max. Number of Request Queues(KB)	2048
Mirror Connect Timeout(sec)	20
Asynchronous - History Files Store Folder	
Asynchronous - Kernel Queue Size (KB)	2048
Asynchronous - Application Queue Size (KB)	2048
Asynchronous - Thread Timeout (sec)	30
Asynchronous - Max. Size of History File(MB)	Unlimited
Asynchronous - Upper Bound of Communication Band(	Unlimited

Type: Resource type

Failover Target Server: Determination method of Failover Target Server
Failover Threshold: The number of failovers to be made at detection of an

error

Retry Count at Activation Failure: The number of times activation is retried when an

activation error is detected

Final Action at Activation Failure: Final action at an activation error

Execute Script before Final Action: Whether or not script is executed upon activation

failure

Retry Count at Deactivation Failure: The number of times deactivation is retried when a

deactivation error is detected

Final Action at Deactivation Failure: Final action at a deactivation error

Execute Script before Final Action: Whether or not script is executed upon deactivation

failure

Dependent Resources: Dependent resources

Retry Interval at Activation Failure: Activation retry interval upon activation failure

detection

Retry Interval at Inactivation Failure: Deactivation retry interval upon inactivation failure

detection

**Cluster Partition** 

Cluster Partition Drive Letter: Drive letters of the cluster partition

Cluster Partition Offset Index: Index number for the area to be used for cluster

partition

Execute the initial mirror construction: Whether to execute an initial mirror construction when

configuring a cluster

Mode: Synchronization mode of the mirror data

Request Queue Maximum Size (KB): Size of queue for the mirror disk drive to queue I/O

requests on the communication among servers.

Mirror Connect Timeout (Second): Time until mirror connect is cut when there is no

response on the communication among servers and the data synchronization has not completed at the time of

mirror recovery and data synchronization.

Asynchronous:

History Files Store Folder: Folder to keep the writing requests to the remote disk

in files

Kernel Queue Size (KB): Size to keep the writing request to the remote disk in

the kernel space memory

Application Queue Size (KB): Size to keep the writing request to the remote disk in

the user space memory

Thread Timeout (Second): Timeout when it became unable to transfer data form

the kernel queue to the application queue

Max. size of history file size (MB): Upper limit of amount of files stored in history files

store folder.

Upper Bound of Communication Band (KB/sec.): Upper limit of communication band on

Mirror Connect.

# **Chapter 7** Monitor resource details

This chapter provides detailed information on monitor resources. Monitor resource is a unit to perform monitoring.

This	chapter	covers:
------	---------	---------

•	Monitor resources	
•	Displaying and changing the settings of group resources	. 595
•	Understanding application monitor resources	.603
•	Understanding disk RW monitor resources	.605
•	Understanding floating IP monitor resources	609
•	Understanding IP monitor resources	612
•	Understanding mirror connect monitor resources	·617
•	Understanding mirror disk monitor resources	621
•	Understanding NIC link up/down monitor resources	625
•	Understanding multi target monitor resources ·····	.629
•	Understanding registry synchronization monitor resources	635
•	Understanding disk TUR monitor resources  Understanding service monitor resources	637
•	Understanding service monitor resources	640
•	Understanding print spooler monitor resources	· 642
•	Understanding virtual computer name monitor resources	· 644
•	Understanding virtual IP monitor resources	. 646
•	Understanding CIFS monitor resources	· 648
•	Understanding NAS monitor resources	652
•	Understanding hybrid disk monitor resources	654
•	Understanding hybrid disk TUR monitor resources	657
•	Understanding custom monitor resources	.661
•	Understanding DB2 monitor resources	. 665
•	Understanding FTP monitor resources	. 669
•	Understanding HTTP monitor resources	672
•	Understanding IMAP4 monitor resources	676
•	Understanding ODBC monitor resources	680
•	Understanding Oracle monitor resources	684
•	Understanding OracleAS monitor resources	689
•	Understanding OfficeScan CL monitor resource	693
•	Understanding OfficeScan SV monitor resource ·····	695

551

## Chapter 7 Monitor resource details

-		
•	Understanding POP3 monitor resources	697
•	Understanding PostgreSQL monitor resources	701
•	Understanding SMTP monitor resources·····	705
•	Understanding SQL Server monitor resources ·····	709
•	Understanding Tuxedo monitor resources ·····	713
•	Understanding Websphere monitor resources ······	717
•	Understanding Weblogic monitor resources·····	722
•	Understanding WebOTX monitor resources·····	726

# **Monitor resources**

A monitor resource refers to a resource that monitors a specified target to be monitored. When detecting an error in a target to be monitored, a monitor resource restarts a group resource and/or executes failover.

Currently supported monitor resource are as follows:

Monitor resource name	Abbreviati on	Functional overview
Application monitor resources	appliw	Refer to "Understanding application monitor resources" on page 603.
Disk RW monitor resources	diskw	Refer to "Understanding disk RW monitor resources" on page 605.
Floating IP monitor resources	fipw	Refer to "Understanding floating IP monitor resources" on page 609.
IP monitor resources	ipw	Refer to "Understanding IP monitor resources" on page 612.
Mirror connect monitor resources	mdnw	Refer to "Understanding mirror connect monitor resources" on page 617.
Mirror disk monitor resources	mdw	Refer to "Understanding mirror disk monitor resources" on page 621.
NIC Link Up/Down monitor resources	miiw	Refer to "Understanding NIC link up/down monitor resources" on page 625.
Multi target monitor resources	mtw	Refer to "Understanding multi target monitor resources" on page 629.
Registry synchronization monitor resources	regsyncw	Refer to "Understanding registry synchronization monitor resources" on page 635.
Disk TUR monitor resources	sdw	Refer to "Understanding disk TUR monitor resources" on page 637.

Monitor resource name	Abbreviati on	Functional overview
Service monitor resources	servicew	Refer to "Understanding service monitor resources" on page 640.
Print spooler monitor resources	spoolw	Refer to "Understanding print spooler monitor resources" on page 642.
Virtual computer name monitor resources	vcomw	Refer to "Understanding virtual computer name resources" on page 513.
Virtual IP monitor resources	vipw	Refer to "Understanding virtual IP monitor resources" on page 646.
CIFS monitor resources	cifsw	Refer to "Understanding CIFS monitor resources" on page 535.
NAS monitor resources	nasw	Refer to "Understanding NAS monitor resources" on page 541.
Hybrid disk monitor resources	hdw	Refer to "Understanding hybrid disk monitor resources" on page 654.
Hybrid disk TUR monitor resources	hdtw	Refer to "Understanding hybrid disk TUR monitor resources" on page 657.
Custom monitor resources	genw	Refer to "Understanding custom monitor resources" on page 661.
DB2 monitor resources	db2w	Refer to "Understanding DB2 monitor resources" on page 665.
FTP monitor resources	ftpw	Refer to "Understanding FTP monitor resources" on page 669.
HTTP monitor resources	httpw	Refer to "Understanding HTTP monitor resources" on page 672.
IMAP4 monitor resources	imap4w	Refer to "Understanding IMAP4 monitor resources" on page 676.

Monitor resource name	Abbreviati on	Functional overview
ODBC monitor resources	odbcw	Refer to "Understanding ODBC monitor resources" on page 680.
Oracle monitor resources	oraclew	Refer to "Understanding Oracle monitor resources" on page 684.
OracleAS monitor resources	oracleasw	Refer to "Understanding OracleAS monitor resources on page 689.
OfiiceScan CL monitor	oscw	Refer to "Understanding OfficeScan CL monitor resource" on page 693.
OfficeScan SV monitor	ossw	Refer to "Understanding OfficeScan SV monitor resource" on page 695.
POP3 monitor resources	pop3w	Refer to " Understanding POP3 monitor resources" on page 697.
PostgreSQL monitor resources	psqlw	Refer to "Understanding PostgreSQL monitor resources" on page 701.
SMTP monitor resources	smtpw	Refer to "Understanding SMTP monitor resources" on page 705.
SQL Server monitor resources	sqlserverw	Refer to "Understanding SQL Server monitor resources" on page 709.
Tuxedo monitor resources	tuxw	Refer to ""Understanding Tuxedo monitor resources on page 713.
Websphere monitor resources	wasw	Refer to "Understanding Websphere monitor resources" on page 717.
Weblogic monitor resources	wlsw	Refer to "Understanding Weblogic monitor resources" on page 722.
WebOTX monitor resources	otxw	Refer to "Understanding WebOTX monitor resources" on page 726.

Monitoring by monitor resources are done in one of two ways: monitoring the target all the time or monitoring the target when it is activated.

You cannot change monitoring timings of each monitor resource. The initial settings are shown below.

The default settings are as follows.

◆ Always monitor (From the cluster startup to the cluster stop)

IP monitor resources

Mirror connect monitor resources

Mirror disk monitor resources

Hybrid disk monitor resources

Hybrid disk TUR monitor resources

NIC Link Up/Down monitor resources

Disk TUR monitor resources

Custom monitor resources

OfficeScan CL monitor resource

♦ Monitor while a group is activated (from activation to deactivation of the group)

Application monitor resources

Disk RW monitor resources

Floating IP monitor resources

Multi target monitor resources

Registry synchronization monitor resources

Service monitor resources

Print spooler monitor resources

Virtual computer name monitor resources

Virtual IP monitor resources

CIFS monitor resources

NAS monitor resources

DB2 monitor resources

FTP monitor resources

HTTP monitor resources

IMAP4 monitor resources

ODBC monitor resources

Oracle monitor resources

OracleAS monitor resources

OfficeScan SV monitor resource

POP3 monitor resources

PostgreSQL monitor resources

SMTP monitor resources


SQL Server monitor resources

Tuxedo monitor resources

Websphere monitor resources

Weblogic monitor resources

WebOTX monitor resources



# Monitor timing of monitor resources

Monitor resource	Monitor timing	Target resource	
Application monitor resources	When activated (Fixed)	appli	
Disk RW monitor resources	Always or when activated	All resources	
Floating IP monitor resources	When activated (Fixed)	ip .	
IP monitor resources	Always or when activated		
Mirror connect monitor resources	Always (Fixed) -		
Mirror disk monitor resources	Always (Fixed)	-	
NIC Link Up/Down monitor resources	Always or when activated	All resources	
Multi target monitor resources	Always or when activated	All resources	
Registry synchronization monitor resources	Always or when activated	regsync	
Disk TUR monitor resources	Always or when activated sd		
Service monitor resources	When activated (Fixed)	service	
Print spooler monitor resources	When activated (Fixed)	spool	
Virtual computer name monitor resources	When activated (Fixed)	vcom	
Virtual IP monitor resources	When activated (Fixed) vip		
CIFS monitor resources	When activated (Fixed) cifs		
NAS monitor resources	When activated (Fixed)	l) Nas	
Hybrid disk monitor resources	Always (Fixed) -		
Hybrid disk TUR monitor resources	Always or when activated Hd		
Custom monitor resources	Always or when activated		
DB2 monitor resources	When activated (Fixed)	All resources	
FTP monitor resources	When activated (Fixed) All resources		

HTTP monitor resources	When activated (Fixed)	All resources	
IMAP4 monitor resources	When activated (Fixed)	All resources	
ODBC monitor resources	When activated (Fixed)	All resources	
Oracle monitor resources	When activated (Fixed) All resources		
OracleAS monitor resources	When activated (Fixed) All resources		
OfiiceScan CL monitor	Always (Fixed) -		
OfficeScan SV monitor	When activated (Fixed)	All resources	
POP3 monitor resources	When activated (Fixed)	All resources	
PostgreSQL monitor resources	When activated (Fixed)	All resources	
SMTP monitor resources	When activated (Fixed)	All resources	
SQL Server monitor resources	When activated (Fixed)	All resources	
Tuxedo monitor resources	When activated (Fixed)	All resources	
Websphere monitor resources	When activated (Fixed) All resources		
Weblogic monitor resources	When activated (Fixed)	ed) All resources	
WebOTX monitor resources	When activated (Fixed)	All resources	

# Monitoring interval for monitor resources

All monitor resources monitor their targets at every monitoring interval.


The following describes the timeline of how a monitor resource monitors its target and finds an error with the monitoring interval settings:

#### When no error is detected

Examples of behavior when the following values are set:

<Monitor>

Monitor Interval30 secMonitor Timeout60 secMonitor Retry Count0 time




#### When an error is detected (without monitor retry setting)

Examples of behavior when the following values are set:

<Monitor>
Monitor Interval
Monitor Timeout
Monitor Retry count
30 sec
60 sec
0 time

<Error detection>

Recovery Target group
Reactivation Threshold 0 time
Failover Threshold 1 time
Final Action None



When an error occurs, it is detected at the next monitoring and the recovery operation for the recovery target starts.

#### When an error is detected (with monitor retry settings)


Examples of behavior when the following values are set:

<Monitor>

Monitor Interval 30 sec Monitor Timeout 60 sec Monitor Retry Count 2 times

<Error detection>

Recovery Target group
Reactivation Threshold 0 time
Failover Threshold 1 time
Final Action None



When an error occurs, it is detected at the next monitoring. If recovery cannot be achieved within the monitor retries, the failover is started for the recovery target.

#### When an error is detected (without monitor retry settings)

Examples of behavior when the following values are set.


<Monitor>

Monitor Interval 30 sec Monitor Timeout 60 sec Monitor Retry Count 0 time

<Error detection>

Recovery Target group
Reactivation Threshold 0 time
Failover Threshold 1 time

Final Action None




Immediately after an occurrence of a monitoring time-out, the failover for the recovery target starts.

#### When a monitoring time-out is detected (with monitor retry setting)

Examples of behavior when the following values are set:

<monitor></monitor>			
Monitor Interval	30 sec		
Monitor Timeout	60 sec		
Monitor Retry Count	1 times		
<error detection=""></error>			
Recovery Target	group		
Reactivation Threshold	0 time		
Failover Threshold	1 time		
Final Action	none		



When a monitoring time-out occurs, monitor retry is performed and failover is started for the recovery target.

## Behavior when an error is detected by a monitor resource

When an error is detected, the following recovery actions are taken against the recovery target in sequence:

- Reactivation of recovery target: this takes place when an error is detected in a monitor target.
- ◆ Failover: this takes place when reactivation fails for the number of times set in the reactivation threshold.
- Final action: this takes place when the error is detected even after the failover is executed for the number of times set in the failover threshold.

No recovery action is taken if the status of the recovery target is:

Recovery target	Status	Reactivation <sup>2</sup>	Failover <sup>3</sup>	Final action <sup>4</sup>
Group resource/ Failover group	Already stopped	No	No	No
	Being activated/stopped	No	No	No
	Already activated	Yes	Yes	Yes
	Error	Yes	Yes	Yes
Cluster	-	•	-	Yes

ExpressCluster X 2.1 for Windows Reference Guide

<sup>&</sup>lt;sup>2</sup> Effective only when the value for the reactivation threshold is set to 1 (one) or greater.

<sup>&</sup>lt;sup>3</sup> Effective only when the value for the failover threshold is set to 1 (one) or greater.

<sup>&</sup>lt;sup>4</sup> Effective only when an option other than **No Operation** is selected.

#### Note:

Do not operate the following by running commands or using the WebManager when a group resource (e.g. disk resource, application resource) is set as a recovery target in the settings of error detection for the monitor resource, and recovery is in progress (reactivation -> failover -> final action) after detection of an error:

- ◆ Stopping/suspending the cluster
- ◆ Starting/stopping/moving a group

If you perform the above-mentioned operations while recovery caused by detection of an error by a monitor resource is in progress, other group resources of the group with an error may not stop.

However, you can perform them when the final action is completed.

When the status of the monitor resource recovers (becomes normal) from error, the reactivation count, failover count, and if the final action is executed are reset. Note that when group resource or failover group is specified as recovery target, these counters are reset only when the status of all the monitor resources in which the same recovery targets are specified are normal.

An unsuccessful recovery action is also counted into reactivation count or failover count.

The following is an example of the progress when only one server detects an error while the gateway is specified as an IP address of the IP monitor resource:

Examples of behavior when the following values are set:

<Monitor>

Interval 30 sec
Timeout 30 sec
Retry Count 3 times


<Error detection>


Recovery Target Failover Group A


Reactivation Threshold 3 times

Failover Threshold 1

Final Action No Operation







In server2, the operation can continue by failover of the Failover Group A because the IP monitor resource 1 is running properly.

The following is an example of the process when both servers detect an error while the gateway is specified as IP address of the IP monitor resource.

Examples of behavior when the following values are set.

<Monitor>


Interval 30 sec Timeout 30 sec Retry Count 3 times


<Error detection>


Recovery Target Failover Group A


Reactivation threshold 3 times Failover Threshold 1


Final Action No Operation











#### **Additional Information**

When the status of the monitor resource becomes normal from an error, the reactivation count and failover count are reset to zero (0). When an error is detected next time, the process will be exactly the same as what has been described up to here. (The description up to here assumed the interconnect LANs are working properly.)

If all interconnect LANs are disconnected, internal communications with other servers are blocked. As a result, even if an error is detected on a monitor target, failover of groups fails. To fail over a group when all interconnect LANs are disconnected, you can choose to shut down the server where an error is detected. This will allow other servers to detect the server is shut down and to start failover of the group.

The following is an example of the process when an error is detected while all interconnect LANs are disconnected.

Configuration example

<Monitor>

Interval 30 seconds
Timeout 30 seconds
Retry Count 3 times


<Error detection>

Recovery Object Failover Group A


Reactivation Threshold 3 times Failover Threshold 1

Final Action Stop cluster service and shutdown OS

Reactivation for the recovery target is same as the situation when the interconnect LANs are working properly. The description begins from the failover on server1, which requires interconnect LANs.




When the failover count exceeds its threshold on server1



Reactivation of the Failover Group A is executed on server2 as is the case on server1.

Failover is attempted on server2 as well when reactivation of the group A fails. However, the failover cannot be executed because there is no destination server for the failvoer.

When the failover count exceeds its threthhold, the final action is taken on server2 as is the case on server1.



## **Returning from monitor error (Normal)**

When return of the monitor resource is detected during or after recovery actions following the detection of a monitoring error, counts for the following thresholds that the monitor resource keeps are reset. Note that when a group resource or failover group is specified as recovery target, these counters are reset only when the status of all the monitor resources in which the same recovery targets are specified become normal.

- ◆ Reactivation Threshold
- Failover Threshold

Whether or not to execute the final action is reset, (execution required).

The following pages describe what will be executed from the point when the final action as described in "Behavior when an error is detected by a monitor resource" on page 562 is executed and another monitoring error occurs after monitoring returns to normal.

Examples of behavior when the following values are set.

Configuration


<Monitor>

Interval 30 sec
Timeout 30 sec
Retry Count 3 times


<Error detection>


Recovery Target Failover Group A

Reactivation Threshold 3 times Failover Threshold 1



The number of reactivations and failovers are reset because it has been detected that the status of the monitor target resource became normal.





Reactivation is executed again because it has been detected that the status of the monitor target resource became normal and reactivation count has been reset before.

# Activation and deactivation error of recovery target when executing recovery operation

When the monitoring target of the monitor resource is the device used for the group resource of the recovery target, an activation/deactivation error of the group resource may be detected during recovery when a monitoring error is detected.

The following is an example of the recovery progress when the same device is specified as the monitor target of the TUR monitor resource and the disk resource of the Failover Group A:

Configuration of the TUR monitor resource

<Monitor>

Interval60 secondsTimeout120 secondsRetry CountZero

<Error detection>

Recovery Target Failover Group A

Reactivation Threshold Zero Failover Threshold 1

Final Action Stop Failover Group

Configuration of the failover group A: disk resource

<Activation error>

Activation retry Threshold Zero Failover Threshold 1


Final Action No Operation (Next resources are not activated)


<Deactivation abnormality>


Deactivation Retry Threshold Zero

Final Action Stop cluster service and shutdown OS

The reactivation threshold of the monitor resource and the activation retry threshold of the group resource are not mentioned in the following diagrams because they are set to zero (0).










The TUR monitor resource 1 detects an error in server2 as is the case in server1. However, no recovery action is taken because the failover group A, the recovery target, is activated.

For more information on recovery executed by monitor resources against their recovery targets, see "Behavior when an error is detected by a monitor resource" on page 562









The final action is executed in server2 because the number of failovers due to failure of disk resource activation has exceeded its threshold.


However, note that activation ends abnormally without activating the rest of the group resources in the Failover Group A because "No operation (Next resources are not activated)" is selected as the final action.






The final action is executed in server1 as is the case in server2 because the number of failovers due to failure of activating the disk resource 1 has exceeded the threshold.

However, note that activation ends abnormally without activating the rest of the group resources in the Failover Group A because "No operation (Next resources are not activated)" is selected as the final action.



The final action is executed in server1 because the number of failovers due to monitoring error detected by the disk TUR monitor resource 1 has exceeded the threshold.



After the Failover Group A is stopped due to the final action executed for the disk TUR monitor resource 1 in server1, nothing will happen even if an error is detected by the disk TUR monitor resource 1.


However, note that the final action for the disk TUR monitor resource 1 is executed in server2 if the Failover Group A is manually activated because the final action for the disk monitor TUR resource 1 is not executed yet.

## **Delay warning of monitor resources**

When a server is heavily loaded, due to a reason such as applications running concurrently, a monitor resource may detect a monitoring time-out. It is possible to have settings to issue an alert at the time when the time for monitor processing (the actual elapsed time) reaches a certain percentages of the monitoring time before a time-out is detected.

The following figure shows timeline until a delay warning of the monitor resource is used.

In this example, the monitoring time-out is set to 60 seconds and the delay warning rate is set to 80%, which is the default value.



- **A.** The time for monitor processing is 10 seconds. The monitor resource is in normal status. In this case, no alert is used.
- **B.** The time for monitor processing is 50 seconds and the delay of monitoring is detected during this time. The monitor resource is in the normal status. In this case, an alert is used because the delay warning rate has exceeded 80%.
- **C.** The time for monitor processing has exceeded 60 seconds of the monitoring time-out and the delay of monitoring is detected. The monitor resource has a problem. In this case, no alert is used.

If the delay warning rate is set to 0 or 100:

♦ When 0 is set to the delay monitoring rate

An alert for the delay warning is used at every monitoring. By using this feature, the time for monitor processing for the monitor resource can be calculated at the time the server is heavily loaded, which will allow you to determine the time for monitoring time-out of a monitor resource.

♦ When 100 is set to the delay monitoring rate

The delay warning will not be is used.

Alert for the delay warning is used for the heartbeat resources as well.

#### Note:

Be sure not to set a low value, such as 0%, except for a test operation.

#### **Related Information:**

To configure the delay warning of monitor resources, click **Cluster Properties**, click **Delay Warning**, and select **Monitor Delay Warning**. For details, refer to "Parameter details" in Chapter 3, "Function of the Builder."

## Waiting for monitor resource to start monitoring


"Wait Time to Start Monitoring" refers to start monitoring after the time period specified as the waiting time elapses.

The following describes how monitoring differs when the wait time to start monitoring is set to 0 second and 30 seconds.

Configuration of monitor resource

<Monitor>

Interval30 secTimeout60 secRetry Count0 timeWait Time to Start Monitoring0 sec / 30 sec



#### Note:

Monitoring will restart after the time specified to wait for start monitoring has elapsed even when the monitor resource is suspended and/or resumed by using the monitoring control commands.

The wait time to start monitoring is used when there is a possibility for monitoring to be terminated right after the start of monitoring due to incorrect application settings, such as the application resource monitored by application monitor resource, and when they cannot be recovered by reactivation.

For example, when the monitor wait time is set to 0 (zero), recovery may be endlessly repeated. See the example below:

Configuration of application monitor resource

<Monitor>


Interval5 secTimeout60 secRetry CountZero

Wait Time to Start Monitoring 0 sec (default)

<Error Detection>

Recover Target appli1
Reactivation Threshold 1
Failover Threshold 1

Final Action Stop Group



The reason why recovery action is endlessly repeated is because the initial monitor resource polling has terminated successfully. The current count of recoveries the monitor resource has executed is reset when the status of the monitor resource becomes normal (finds no error in the monitor target). Because of this, the current count is always reset to 0 and reactivation for recovery is endlessly repeated.


You can prevent this problem by setting the wait time to start monitoring. By default, 60 seconds is set as the wait time from the application startup to the end.

Configuration of application monitor resource

<Monitor>

Interval5 secTimeout60 secRetry CountZeroWait Time to Start Monitoring60 sec

<Error Detection>
Recover Target appli1
Reactivation Threshold 1
Failover Threshold 1
Final Action Stop Group



If the application is abnormally terminated in the destination server of the group failover, the group stops as the final action.

When **Stop cluster service and shutdown OS** or **Stop cluster service daemon and reboot OS** is selected as a final action to be taken when an error is detected by the monitor resource, the number of shutdowns or reboots can be limited.

#### Note:

The maximum reboot count is on a server basis because the number of reboots is recorded on a server basis.

The number of reboots caused by a final action in detection of error in group activation/deactivation and the number of reboots caused by a final action in detection of error by a monitor resource are recorded separately.

If the time to reset the maximum reboot count is set to zero (0), the number of reboots will not be reset.

The following is an example of the process when the number of reboots is limited.

As a final action, **Stop cluster service and reboot OS** is executed once because the maximum reboot count is set to one.

When the monitor resource finds no error in its target for 10 minutes after reboot following cluster shutdown, the number of reboots is reset because the time to reset the maximum reboot count is set to 10 minutes.

#### Configuration example

<Monitor>

Interval 60 sec
Timeout 120 sec
Retry count 3 times

<Error Detection>

Recovery Target Failover group A


Reactivation Threshold zero Failover Threshold zero


Final Action Stop cluster service and reboot OS


< Reboot count limit>


Maximum reboot count


Time to reset the maximum reboot count 10 minutes











# Monitor resources that require a license

Monitor resources listed below require a license since they are optional products. To use these monitor resources, obtain and register a product license.

Optional product name	Monitor resource name
ExpressCluster X Database Agent 2.1 for Windows	DB2 monitor resources
	ODBC monitor resources
	Oracle monitor resources
	PostgreSQL monitor resources
	SQL Server monitor resources
ExpressCluster X Internet Server Agent 2.1 for Windows	FTP monitor resources
	HTTP monitor resources
	IMAP4 monitor resources
	POP3 monitor resources
	SMTP monitor resources
ExpressCluster X Application Server Agent 2.1 for Windows	OracleAS monitor resources
	Tuxedo monitor resources
	Websphere monitor resources
	Weblogic monitor resources
	WebOTX monitor resources
ExpressCluster X Anti-Virus Agent 2.1 for Windows	OfficeScan CL monitor resource
	OfficeScan SV monitor resource

For information on how to register a license, refer to Chapter 4, "Registering the license" in the *Installation and Configuration Guide*.

# Displaying and changing the settings of group resources

## Changing the name of a monitor resource

#### SuspendResume

- 1. In the tree view shown on the left pane of the Builder, click the icon of the monitor resource. In the table view shown on the right side of the screen, right-click the icon of the monitor resource whose name is to be changed, and click **Rename Monitor Resource**.
- 2. Enter a new name in the **Change Monitor Resource Name** dialog box.

### Displaying and changing the comment of a monitor resource


- 1. In the tree view shown on the left pane of the Builder, right-click the icon of the monitor resource. In the table view shown on the right side of the screen, right-click the icon of the monitor resource whose comment you want to change, and then click **Properties** to display **Monitor Resource Properties.**
- 2. On the **Info** tab, the monitor resource name and comment are shown. Enter a new comment (within 127 bytes).

#### Note:

You cannot change the monitor resource name on the **Info** tab. To change the group name, right-click the icon of the group resource as described in the step 1 above. Click **Rename Monitor Resource** and enter a new name.

# Displaying and changing the settings of a monitor resource

- 1. In the tree view shown on the left pane of the Builder, click the icon of the monitor resource.
- 2. The list of monitor resources is shown in the table view on the right side of the screen. Right-click the name of the monitor resource whose settings you want to change. Click **Properties**, and then click the **Monitor** tab.
- 3. On the **Monitor** tab, you can see and/or change the settings of monitor resource by following the description below.



Interval (1 to 999) SuspendResume

Specify the interval to check the status of monitor target.

**Timeout** (5 to 999) SuspendResume

When the normal status cannot be detected within the time specified here, the status is determined to be error.

Retry Count (0 to 999) SuspendResume

Specify how many times an error should be detected in a row after the first one is detected before the status is determined as error. If you set this to zero (0), the status is determined as error at the first detection of an error.

Wait Time to Start Monitoring (0 to 9999) SuspendResume

Set the wait time to start monitoring.

Monitor Timing SuspendResume

Set the monitoring timing. Select the timing from:

Always

Monitoring is performed all the time.

• When active:


Monitoring is not started until the specified resource is activated.

#### Target Resource SuspendResume

The resource which will be monitored when activated is shown.


#### **Browse**

Click this button to open the dialog box to select the target resource. The cluster name, group names and resource names that are registered in the cluster are shown in a tree view. Select the target resource and click OK.



#### Choose servers that execute monitoring

Choose the servers that execute monitoring.



#### All Servers SuspendResume

All servers monitor the resources.

#### Select SuspendResume

Servers registered in **Available Servers** monitor the resources. One or more servers need to be set to **Available Servers**.

#### Add SuspendResume

Click this button to add a server selected in **Available Servers** to **Servers that can run the Group**.


#### Remove SuspendResume

Delete a server selected from **Servers that can run the Group**.

# Displaying and changing the settings when an error is detected by a monitor resource

- 1. In the tree view shown on the left pane of the Builder, click the icon of the monitor resource.
- 2. The list of monitor resources is shown in the table view on the right side of the screen. Right-click the name of the monitor resource whose settings you want to change or display. Click **Properties**, and then click the **Error Detection** tab.
- 3. On the **Error Detection** tab, display and/or change the monitor settings by following the description below.

In this dialog box, you can configure the recovery target and an action to be taken at the time when an error is detected. By setting this, it allows failover of the group, restart of the resource and cluster when an error is detected. However, recovery will not occur if the recovery target is not activated.




#### Recovery Target SuspendResume

A target is shown, which is to be recovered when it is determined as a resource error.

#### Browse

Click this button to open the dialog box in which you can select the target resource. The cluster name, group names and resource names that are registered in the cluster are shown in a tree view. Select the target resource and click **OK**.



#### **Reactivation Threshold** (0 to 99)

SuspendResume

Specify how many times you allow reactivation when an error is detected. If this is set to zero (0), no reactivation is executed. This is enabled when a group or group resource is selected as a recovery target.

#### Failover Target Server SuspendResume

Select a Failover Target Server for the failover that takes place after reactivation retries upon activation error detection have failed for the number of times specified in **Retry Count at Activation Failure**.

- Stable operation server
  - The failover destination is the server where least resource errors have been detected. If two or more servers that meet the above condition exist, failover takes place by selecting one of them according to the failover policy of the group..
- Server with the highest priority
  Failover takes place according to the failover policy settings of the group.

#### Failover Threshold (0 to 99) SuspendResume

Specify how many times you allow failover after reactivation fails for the number of times set in **Reactivation Threshold** when an error is detected. If this is set to zero (0), no failover is executed. This is enabled when a group or group resource is selected as a recovery target.

- Set as many as the number of the servers Specify the number of servers as the number of failovers to occur.
- Specify the count Specify any number of times to a failover threshold.

#### Final Action SuspendResume

Select a final action to be taken after reactivation fails for the number of times set in **Reactivation Threshold**, and failover fails for the number of times set in **Failover Threshold** when an error is detected.

Select the final action from the options below:

- No Operation
   No action is taken.
- Stop Group

When a group or group resource is selected as a monitor target, this option stops the group or the group that the group resource belongs. This is disabled when a cluster is selected as a monitor target.

#### • Stop cluster service

Stops the ExpressCluster Server service of the server that detected an error.

#### Stop cluster service and shutdown OS

Stops the ExpressCluster Server service of the server that detected an error, and then shuts down the OS.

#### Stop cluster service and reboot OS

Stops the ExpressCluster Server service of the server that detected an error, and then reboots the OS.

#### Generating of intentional Stop Error

Intentionally cause stop error for the server that detected an error.

#### **Execute Script before Final Action**

Select whether script is run or not before executing final action.

• When selected:


A script/command is run before executing final action. To configure the script/command setting, click **Settings**.

When cleared:

Any script/command is not run.

#### **Settings**

Click here to display the **Edit Script** dialog box. Set the script/command to be run before executing final action.



#### **User Application**

Use an executable file (executable batch file or execution file) on the server as a script. For the file name, specify an absolute path or name of the executable file of the local disk on the server. If you specify only the name of the executable file, you must configure the path with environment variable in advance. If there is any blank in the absolute path or the file name, put them in double quotation marks ("") as follows.

#### Example:

"C:\Program Files\script.bat"

If you want to execute VBScript, enter a command and VBScript file name as follows.

#### Example:

escript script.vbs

Each executable file is not included in the cluster configuration information of the Builder. They must be prepared on each server since they cannot be edited or uploaded by the Builder.

#### Script created with this product

Use a script file which is prepared by the Builder as a script. You can edit the script file with the Builder if you need. The script file is included in the cluster configuration information.

File (Within 1023 bytes)

Specify a script to be executed (executable batch file or execution file) when you select **User Application**.

#### View

Click here to display the script file with the editor when you select **Script created with this product**. The information edited and stored with the editor is not reflected. You cannot display the script file if it is currently displayed or edited.

#### Edit

Click here to edit the script file with the editor when you select **Script created with this product**. Overwrite the script file to reflect the change. You cannot edit the script file if it is currently displayed or edited. You cannot modify the name of the script file.

#### Replace

Click here to replace the contents of a script file with the contents of the script file which you selected in the file selection dialog box when you select **Script created with this product**. You cannot replace the script file if it is currently displayed or edited. Select a script file only. Do not select binary files (applications), and so on.

#### **Timeout** (0 to 99)

Specify the maximum time to wait for completion of script to be executed. The default value is set as 5.

#### Change

Click here to display the **Change Script Editor** dialog. You can change editor for displaying or editing a script to an arbitrary editor.



#### **Standard Editor**

Select here to use a standard editor (Notepad in Windows) as a script editor.

#### **External Editor**

Select here to specify an arbitrary script editor. Click Browse to specify the editor to be used

# Displaying and changing parameters of a monitor resource

Some monitor resources require parameter setting for monitoring. For displaying and changing parameters, please refer to explanations of each monitor resource that described on following pages.

# **Understanding application monitor resources**

Application monitor resources monitor application resources.

## Monitoring by application monitor resources

Application monitor resources monitor application resources in a server where they are activated. They regularly monitor whether applications are active or not. When they detect that applications do not exist, it is determined to be an error.

# Displaying the application monitor resource properties with the WebManager

- 1. Start the WebManager. (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click an object for the application monitor resources in the tree view. The following information is displayed in the list view.

Application Monitor Name: appliw1		Details
Properties		Value
Name	appliw1	
Comment		
Status	Normal	
Resource Status on Each Server		
Server Name		Status
server1	Online	

Name: Application monitor resource name

Comment: Comment for the application monitor resource Status: Status of the application monitor resource

Server Name: Server name

Status: Status of the monitor resource on the given server

#### If you click the **Details** button, the following information is displayed.

Properties	Value
Type	appliw
Monitor Timing	Activating
Target Resource	appli
Interval	60
Timeout	60
Retry Count	1
Final Action	No Operation
Execute Script before Final Action	Off
Recovery Target	ExpressCluster
Recovery Target Type	Itself
Reactivation Threshold	0
Failover Target Server	Stable Server
Failover Threshold	0
Wait Time to Start Monitoring	0

Type: Monitor resource type

Monitor Timing: Timing for the monitor resource to start monitoring

Target Resource: Resource to be monitored

Interval: Interval between monitoring (in seconds) Timeout: Time to elapse from detection of an error to

> establish the monitor resource as error (in seconds) The number of retries to be made from detection of an

Retry Count: error in the monitor target to establish the error as error

Final Action: Final action at detection of an error

Execute Script before Final Action: Whether or not script is executed when a failure is

detected

Recovery Target: Target to be recovered when an error is detected Recovery Target Type: Type of target to be recovered when an error is detected Reactivation Threshold:

The number of times activation is retried when an

activation error is detected

Failover Destination Server Determination method of Failover Target Server Failover Threshold: The number of failovers to be made at detection of an

error

Wait Time to Start Monitoring: Time to wait before start monitoring (in seconds)

# Understanding disk RW monitor resources

Disk RW monitor resources monitor disk devices by writing dummy data to the file system.

## Monitoring by disk RW monitor resources

Disk RW monitor resources write data to the specified file system (basic volume or dynamic volume) with the specified I/O size and evaluate the result. They solely evaluate whether data was written with the specified I/O size but do not evaluate validity of data. (Created file is deleted after writing)


OS and disk get highly loaded if the size of I/O is large. Depending on disk and/or interface being used, caches for various writing are mounted. Because of this, if the size of I/O is small, a cache hit may occur and an error in writing may not get detected. Intentionally generate a disk error to confirm that the size of I/O is sufficient to detect an error.

#### Note:

If you want multipath software to initiate path failover when disk path is not connected, you should set longer timeout for disk RW monitor resource than path failover time.

### Displaying and changing disk RW monitor resource details

- 1. Click **Monitors** on the tree view displayed on the left side of the Builder window.
- 2. List of the monitor resources is displayed in the table view on the right side of the screen. Right click the target disk RW monitor resource, and click the **Parameter** tab in the **Monitor Resource Property** window.
- 3. On the **Parameter** tab, you can display and/or change the detailed settings by following the description below.



File Name Within 1023 bytes SuspendResume

Enter the file name to access. This file is created upon monitoring and deleted after I/O completes.

#### Note:

Specify an absolute path for the file name. If a relative path is specified for the file name, the disk RW monitor resource may monitor the unexpected place.

#### Important:

Do not specify any existing file for the file name. If an existing file is specified for the file name, the data of the file is lost.

I/O size (1 to 9999999) SuspendResume

Specify the I/O size for the disk to monitor.

#### Action when stalling is detected SuspendResume

Specify the action to take when stalling is detected.

No Operation

No action is taken.

HW Reset

Reset the hardware.

Generating of intentional Stop Error

Intentionally cause a stop error.

# Displaying the disk RW monitor resource properties with the WebManager

1. Start the WebManager. (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).

2. Click an object for the disk RW monitor resources in the tree view. The following information is displayed in the list view.

Disk RW Monitor Name: diskw1	Details
Properties	Value
Name	diskw1
Comment	
File Name	X:\diskw
Status	Normal
Docourse Status on Each Corve	,
Resource Status on Each Server	
Server Name	Status
server1	Online
server2	Offline

Name: Disk RW monitor resource name

Comment: Comment for the disk RW monitor resource

File Name Path to the file name on the file system to monitor

Status: Status of the disk RW monitor resource

Server Name: Server name

Status: Status of the disk RW monitor resource on the given server

If you click the **Details** button, the following information is displayed in the pop-up dialog.

Properties	Value
Туре	diskw
Monitor Timing	Activating
Target Resource	sd1
Interval	30
Timeout	300
Retry Count	0
Final Action	No Operation
Execute Script before Final Action	Off
Recovery Target	failover1
Recovery Target Type	Group
Reactivation Threshold	0
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Wait Time to Start Monitoring	0
I/O Size (byte)	2000000
Action On Stall	Stop Error

Type: Monitor resource type Monitor Timing: Timing to start monitoring Target Resource: Resource to be monitored

Interval: Interval between monitoring (in seconds) Time to elapse from detection of an error to Timeout: establish the error as error (in seconds)

Retry Count: The number of retries to be made from detection of an

error in the monitor target to establish the error as error

Final action at detection of an error Final Action:

Execute Script before Final Action: Whether or not script is executed when a failure is

detected

Recovery Target: Target to be recovered when an error is detected Recovery Target Type: Type of target to be recovered when an error is detected Reactivation Threshold:

The number of times activation is retried when an

activation error is detected

Failover Target Server: Determination method of Failover Target Server Failover Threshold: The number of failovers to be made at detection of an

Wait Time to Start Monitoring: Time to wait before start monitoring (in seconds)

I/O size (Byte): Write size (byte)

Action on Stall: Action when stalling is detected

# **Understanding floating IP monitor resources**

Floating IP monitor resources monitor floating IP resources.


## Monitoring by floating IP monitor resources

Floating IP resources monitor floating IP resources in a server where they are activated. Floating IP monitor resources monitor whether floating IP addresses exist in the list of IP addresses. If a floating IP address does not exist in the list of IP addresses, it is determined to be an error.

Floating IP resources monitor link up/down of NIC where a floating IP address is active. If NIC link down is detected, it is considered as an error. In some NIC drivers, required DeviceIoControl may not be supported. In such a case, monitoring cannot be performed.

## Displaying and changing floating IP monitor resource details

- 1. Click **Monitors** on the tree view displayed on the left side of the Builder window.
- List of the monitor resources is displayed in the table view on the right side of the screen. Right click the target floating IP monitor resource, and click the **Parameter** tab in the **Monitor Resource Property** window.
- 3. On the **Parameter** tab, you can display and/or change the detailed settings by following the description below.



Monitor NIC Link Up/Down

Specify whether to monitor NIC Link Up/Down.

# Displaying the floating IP monitor resource properties with the WebManager

- 1. Start the WebManager. (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click an object for the application monitor resources in the tree view. The following information is displayed in the list view.

FIP Monitor Name: Fjipw1	Details	
Properties	Value	
Name	Fipw1	
Comment		
Status	Normal	
Resource Status on Each Server		
Server Name	Status	
server1	Online	
server2	Offline	

Name: Floating IP monitor resource name

Comment: Comment for floating the IP monitor resource Status: Status of the floating IP monitor resource

Server Name: Server name

Status: Status of the monitor resource on the given server

If you click the **Details** button, the following information is displayed in the pop-up dialog.

Properties	Value
Type	fipw
Monitor Timing	Activating
Target Resource	fip1
Interval	60
Timeout	60
Retry Count	1
Final Action	No Operation
Execute Script before Final Action	Off
Recovery Target	A
Recovery Target Type	Group
Reactivation Threshold	3
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Wait Time to Start Monitoring	0
Monitor NIC Link Up/Down	Off

Type: Monitor resource type

Monitor Timing: Timing for the monitor resource to start monitoring

Interval: Interval between monitoring (in seconds) Timeout: Time to elapse from detection of an error to

establish the monitor resource as error (in seconds)

Target Resource: Resource to be monitored

Retry Count: The number of retries to be made from detection of an

error in the monitor target to establish the monitor

resource as error

Final action at detection of an error Final Action:

Execute Script before Final Action: Whether or not script is executed when a failure is

detected

Recovery Target: Target to be recovered when an error is detected Recovery Target Type: Type of target to be recovered when an error is detected Reactivation Threshold:

The number of times activation is retried when an

activation error is detected

Failover Target Server: Determination method of Failover Target Server Failover Threshold: The number of failovers to be made at detection of an

Wait Time to Start Monitoring: Time to wait before start monitoring (in seconds) Monitor NIC Link Up/Down: Monitor/Do not monitor NIC Link Up/Down


# **Understanding IP monitor resources**

IP monitor resource is a monitor resource which monitors IP addresses by using the ping command depending on whether there is a response or not.


## Monitoring by IP monitor resources

IP monitor resource monitors specified IP addresses by using the ping command. If all IP addresses do not respond, the status is determined to be error.

If you want to establish error when all of the multiple IP addresses have error, register all those IP addresses with one IP monitor resource.




If you want to establish error when any one of IP addresses has an error, create one IP monitor resource for each IP address.



### Displaying and changing IP monitor resource details

- 1. Click **Monitors** on the tree view displayed on the left side of the Builder window.
- 2. List of the monitor resources is displayed in the table view on the right side of the screen. Right click the target IP monitor resource, and click the **Parameter** tab in the **Monitor Resource Property** window.
- 3. On the **Parameter** tab, you can display and/or change the detailed settings by following the description below.

IP addresses to be monitored are listed in **IP Addresses**.



#### Add

Click Add to add an IP address to be monitored.

A dialog box where you can enter an IP address is displayed.



#### IP Address (within 255 bytes)

Enter an IP address to be monitored in this field and click  $\mathbf{OK}$ . The IP address to be entered here should be the one that exists on the public LAN.

#### Remove

Click **Remove** to remove an IP address selected in **IP Addresses** from the list so that it will no longer be monitored.

#### Edit

Click **Edit** to display the **IP Address Settings** dialog box. The dialog box shows the IP address selected in **IP Addresses** on the **Parameter** tab. Edit the IP address and click **OK**.

#### **Ping Timeout** (1 to 999999)

Specify the time-out of the ping to be sent to monitor the IP address in milliseconds.

# Displaying the IP monitor resource properties with the WebManager

- 1. Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click an IP monitor object, , in the tree view. The following information is displayed in the list view.

IP Monitor Name: ipw1	Details		
Properties	Value		
Name	ipw1		
Comment			
IP Address List	192.168.0.254		
Ping Timeout (milliseconds)	1000		
Status	Normal		
Resource Status on Each Server			
Server Name	Status		
server1	Online		
server2	Online		

Name: IP monitor resource name

Comment on the IP monitor resource

Status: IP monitor resource status IP Addresses: IP address to be monitored

Server Name: Server name

Status: Status of the monitor resource on the server

If you click the **Details** button, the following information is displayed in the dialog box.

Properties	Value
Type	ipw
Monitor Timing	Always
Target Resource	
Interval	60
Timeout	60
Retry Count	1
Final Action	No Operation
Execute Script before Final Action	Off
Recovery Target	A
Recovery Target Type	Group
Reactivation Threshold	3
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Wait Time to Start Monitoring	0

Type: Monitor resource type

Monitor Timing: Timing for monitor resource to start monitoring Interval: Interval between monitoring (in seconds)

Timeout: Time to elapse from detection of an error to establish the monitor

resource as error (in seconds)

Target Resource: Resource to be monitored

Retry Count: The number of retries to be made from detection of an error in

the monitor target to establish the monitor resource as error

Final Action: Final action at detection of an error

Execute Script before Final Action:

Whether or not script is executed when a failure is detected

Recovery Target: Target to be recovered when an error is detected

Recovery Target Type: Type of target to be recovered when an error is detected Reactivation Threshold: The number of reactivations to be made at detection of an error

Failover Target Server: Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an error

Wait Time to Start Monitoring: Time to wait before start monitoring (in seconds)

## **Understanding mirror connect monitor resources**

#### Note on mirror connect monitor resources

A mirror disk connect monitor resource monitors a network for mirroring. If communication of mirror data using the specified mirror connect fails, it is recognized as an error. This resource is automatically registered when the first mirror disk resource is added. Because mirror disk resources share the same mirror connect interface, only one interface is automatically registered. When this resource is deleted, be careful that auto mirror recovery cannot be executed. Refer to "Automatically recovering from mirroring" in "Connecting mirror disks/hybrid disks manually" of "Chapter 12 Troubleshooting" for the details.

# Displaying and changing the mirror connect monitor resource details ~For Replicator ~


- 1. Click **Monitors** on the tree view displayed on the left side of the Builder window.
- 2. List of the monitor resources is displayed in the table view on the right side of the screen. Right click the target mirror disk monitor resource, and click the **Parameter** tab in the **Monitor Resource Property** window.
- 3. On the **Parameter** tab, you can display and/or change the detailed settings by following the description below.

#### Note:

Do not change the settings shown below on the **Error Detection** tab. With these settings, you can send an alert message if an error is determined.

#### The **Error Detection** tab settings:

Recovery Target Cluster name
Reactivation Threshold Zero (Never)
Failover Threshold Zero (Never)
Failover Target Server Stable operation
Final Action No Operation




### Mirror Disk Resource SuspendResume

The mirror disk resource to be monitored is displayed.

#### **Browse**

Click this button to display the dialog box where you can select a mirror disk resource to be monitored. Mirror disk resources registered with the cluster are displayed in a tree view. You can select only mirror disk resources in this view. Select a mirror disk resource and click **OK**.



# Displaying the mirror connect monitor resource properties with the WebManager

- 1. Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click a mirror connect monitor object, , in the tree view. The following information is displayed in the list view.

Mirror Connect Monitor Name: m	dnw1 Details
Properties	Value
Name	mdnw1
Comment	
Mirror Disk Resource Name	md1
Status	Normal

Resource Status on Each Server		
Server Name Status		
server1	Online	
server2	Online	

Name: Mirror connect monitor resource name

Comment: Comment of the mirror connect monitor resource
Mirror Disk Resource Name: Name of the mirror disk resource to be monitored by

mirror connect monitor resource

Status: Mirror connect monitor resource status

Server Name: Server name

Status: Status of the monitor resource on the given server

If you click the **Details** button, the following information is displayed in the pop-up dialog box.

Properties	Value
Type	mdnw
Monitor Timing	Always
Target Resource	
Interval	60
Timeout	20
Retry Count	0
Final Action	No Operation
Execute Script before Final Action	Off
Recovery Target	md1
Recovery Target Type	Resource
Reactivation Threshold	0
Failover Target Server	Stable Server
Failover Threshold	0
Wait Time to Start Monitoring	0

Type: Monitor resource type

Monitor Timing: Timing for the monitor resource to start monitoring

Target Resource: Resource to be monitored

Interval: Interval between monitoring (in seconds)

Timeout: Time to elapse from detection of an error to establish

the monitor resource as error (in seconds)

Retry Count: The number of retries to be made from detection of an

error in the monitor target to establish the monitor

resource as error.

Final Action: Final action at detection of an error

Execute Script before Final Action: Whether or not script is executed when a failure is detected

Recovery Target: Target to be recovered when an error is detected Recovery Target Type: Type of target to be recovered when a problem is

detected

Reactivation Threshold: The number of reactivations to be made at detection

of an error

Failover Target Server: Determination method of Failover Target Server Failover Threshold: The number of failovers to be made at detection of an

error

Wait Time to Start Monitoring: Time to wait before starting monitoring (in seconds)

## Understanding mirror disk monitor resources

Mirror monitor resources monitor a mirror partition device or mirror driver works properly.

#### Note on mirror disk monitor resources

This resource is automatically registered when a mirror disk resource is added. A mirror disk monitor resource corresponding to the mirror disk resource is automatically registered. When this resource is deleted, be careful that auto mirror recovery cannot be executed.

Refer to "Automatically recovering from mirroring" in "Connecting mirror disks/hybrid disks manually" of "Chapter 12 Troubleshooting" for the details.

### Displaying and changing the mirror disk monitor resource details

- 1. Click **Monitors** on the tree view displayed on the left side of the Builder window.
- 2. List of the monitor resources is displayed in the table view on the right side of the screen. Right-click the target mirror disk monitor resource, and click the **Parameter** tab in the **Monitor Resource Property** window.
- **3.** On the **Parameter** tab, you can display and/or change the detailed settings by following the description below.

#### Note:

Do not change the settings shown below on the Error Detection tab.

The Error Detection tab settings:

Recovery object Mirror disk resource name
Reactivation threshold Zero (Never)
Failover Target Server Stable operation server

Failover threshold Set as many as the number of the servers

Final Action No Operation




### Mirror Disk Resource SuspendResume

The mirror disk resource to be monitored is displayed.

#### **Browse**

Click this button to display the dialog box where you can select a mirror disk resource to be monitored. Mirror disk resources registered with the cluster are displayed in a tree view. You can select only mirror disk resources in this view. Select a mirror disk resource and click OK.



# Displaying the mirror disk monitor resource properties with the WebManager

- **1.** Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click an object for a mirror disk monitor resource, , in the tree view. The following information is displayed in the list view.

Mirror Disk Monitor Name: md	w1 Details	
Properties	Value	
Name	mdw1	
Comment		
Mirror Disk Resource Name	md1	
Status	Normal	
Resource Status on Each Server		
Server Name	Status	
server1	Online	
server2	Online	

Name: Mirror disk monitor resource name

Comment: Comment of the mirror disk monitor resource

Mirror Disk Resource Name: Name of the mirror disk resource to be monitored by the

mirror disk monitor resource

Status: Mirror disk monitor resource status

Server Name: Server name

Status: Status of the monitor resource on the given server

If you click the **Details** button, the following information is displayed in the pop-up dialog box.

Properties	Value
Type	mdw
Monitor Timing	Always
Target Resource	
Interval	30
Timeout	999
Retry Count	0
Final Action	No Operation
Execute Script before Final Action	Off
Recovery Target	md1
Recovery Target Type	Resource
Reactivation Threshold	0
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Wait Time to Start Monitoring	0

Type: Monitor resource type

Monitor Timing: Timing for the monitor resource to start monitoring

Target Resource: Resource to be monitored

Interval: Interval between monitoring (in seconds)

Time to elapse from detection of an error to establish

the monitor resource as error (in seconds)

Retry Count: The number of retries to be made from detection of an

error in the monitor target to establish the monitor

resource as error.

Final Action: Final action at detection of an error

Execute Script before Final Action: Whether or not script is executed when a failure is

detected

Recovery Target: Target to be recovered when an error is detected Recovery Target Type: Type of target to be recovered when an error is

detected

Reactivation Threshold: The number of reactivations to be made at detection

of an error

Failover Target Server: Determination method of Failover Target Server
Failover Threshold: The number of failovers to be made at detection of an

error

Wait Time to Start Monitoring: Time to wait before starting monitoring (in seconds)

## Understanding NIC link up/down monitor resources

NIC Link Up/Down monitor resource obtains the information on how the specified NIC is linked and monitors the linkage is up or down.

### Note on NIC link up/down monitor resources

Some NIC drivers may not support the DeviceIoControl required for monitoring NIC, in which case you cannot use this monitor resource.

### Configuration and range of NIC link up/down monitoring

- ◆ The DeviceIoControl to the NIC driver is used to find how the server is linked to the network. (For the IP monitoring, the status is judged by the ping response from the specified IP address.)
- ◆ You can monitor an NIC dedicated to interconnect (mirror connect). If you do this in the environment where two nodes are directly connected with a cross cable and one server fails, the other server is considered to be failing. This is because no link is established. The recovery action to be taken at detection of error should be configured with the appropriate value.


For example, if you select **Stop cluster service and reboot OS**, other servers will continue to restart the OS endlessly.

## Displaying and changing the NIC link up/down monitor resource details

- 1. Click **Monitors** on the tree view displayed on the left side of the Builder window.
- 2. List of the monitor resources is displayed in the table view on the right side of the screen. Right click the target NIC Link Up/Down monitor resource, and click the **Parameter** tab in the **Monitor Resource Property** window.
- **3.** On the **Parameter** tab, you can display and/or change the detailed settings by following the description below.

NIC Link UP/Down monitor resource acquires the status of the specified NIC Link and monitors the status of being up and down of the Link.

#### NIC Link Up/Down monitor resource parameter tab



#### Add

Add the IP address of the NIC to be monitored to the list of monitoring servers.


#### **Delete**

Delete the IP address of the NIC to be monitored from the list of monitoring servers.

#### Edit

Edit the IP address of the NIC to be monitored.

#### NIC Link Up/Down monitor resource add/edit properties



### IP Address Within 47 bytes

Specify the IP address of the NIC to be monitored.

# Displaying the NIC link up/down monitor resource properties with the WebManager

- **1.** Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click a NIC Link Up/Down monitor resource object, in the tree view. The following information is displayed in the list view.

NIC Link Up/Down Monitor Nar	me: miiw1 Details	
Properties	Value	
Name	miiw1	
Comment		
Status	Normal	
Resource Status on Each Server		
Server Name	Status	
server1	Online	
server2	Online	

Name: NIC Link Up/Down monitor resource name

Comment: Comment of the NIC Link Up/Down monitor resource

Status: NIC Link Up/Down monitor resource status

Server Name: Server name

Status: Status of the monitor resource on the given server

If you click the **Details** button, the following information is displayed in the dialog box.

Properties	Value
Type	miiw
Monitor Timing	Always
Target Resource	
Interval	60
Timeout	60
Retry Count	1
Final Action	No Operation
Execute Script before Final Action	Off
Recovery Target	failover1
Recovery Target Type	Group
Reactivation Threshold	3
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Wait Time to Start Monitoring	0

Type: Monitor resource type

Monitor Timing: Timing for the monitor resource to start monitoring

Target Resource: Resource to be monitored

Interval: Interval between monitoring (in seconds)

Time to elapse from detection of an error to establish

the monitor resource as error (in seconds)

Retry Count: The number of retries to be made from detection of an

error in the monitor target to establish the monitor

resource as error

Final Action: Final action at detection of an error

Execute Script before Final Action: Whether or not script is executed when a failure is

detected

Recovery Target: Target to be recovered when an error is detected Recovery Target Type: Type of target to be recovered when an error is

detected

Reactivation Threshold: The number of reactivations to be made at detection

of an error

Failover Target Server: Determination method of Failover Target Server Failover Threshold: The number of failovers to be made at detection of an

error

Wait Time to Start Monitoring: Time to wait before starting monitoring (in seconds)

### Understanding multi target monitor resources

The multi target monitor resource monitors more than one monitor resources.

### Multi target monitor resource status

The status of the multi target monitor resource is determined by the status of registered monitor resources.

The table below describes status of multi target monitor resource when the multi target monitor resource is configured as follows:

The number of registered monitor resources 2
Error Threshold 2
Warning Threshold 1

The table below describes status of a multi target monitor resource:

Multi target monitor resource status		Monitor resource1 status		
		Normal	Error	Offline
Monitor	Normal	normal	caution	caution
resource2	Error	caution	error	error
Status	Offline	caution	error	normal

- ♦ Multi target monitor resource monitors status of registered monitor resources.
  - If the number of the monitor resources with the error status exceeds the error threshold, multi target monitor resource detects an error.
  - If the number of the monitor resources with the caution status exceeds the caution threshold, the status of the multi target monitor resource becomes caution.
  - If all registered monitor resources are in the status of stopped (offline), the status of multi-target monitor resource becomes normal.
  - Unless all the registered monitor resources are stopped (offline), the multi target monitor resource recognizes the stopped (offline) status of a monitor resource as error.
- ◆ If the status of a registered monitor resource becomes error, actions for the error of the monitor resource are not executed.
  - Actions for error of the multi target monitor resource are executed only when the status of the multi target monitor resource becomes error.


## Displaying and changing the details of the multi target monitor resource

- 1. Click **Monitors** on the tree view displayed on the left pane of the Builder window.
- List of monitor resources is displayed in the table view on the right side of the screen.
   Right-click the multi target monitor resource. Then click **Properties** and select **Parameter** tab
- 3. On the **Parameter** tab, you can display and/or change the detailed settings by following the description below.

Monitor resources are grouped and the status of the group is monitored. You can register up to 64 monitor resources in the **Monitor Resources**.

When the only one monitor resource set in the **Monitor Resources** is deleted, the multi target monitor resource is deleted automatically.

#### Multi target monitor resource parameter tab



Add SuspendResume

Click Add to add a selected monitor resource to Monitor Resources.


Remove SuspendResume

Click **Remove** to delete a selected monitor resource from **Monitor Resources**.

### **Tuning multi target monitor resource**

- 1. From the tree view displayed in the left pane of the Builder, click the **Monitors** icon.
- 2. The list of monitor resources is displayed on the table view in the right pane of the window. Right-click the target multi target monitor resource name. Click **Properties**, and then click **Parameters**.
- **3.** Click **Tuning** on the **Parameters** tab. The **MultiTarget Monitor Resource Tuning Properties** dialog box is displayed.
- **4.** The settings of multi target monitor resource can be displayed and changed by following the description below.

#### Parameter tab



#### **Error Threshold**

Select the condition for multi target monitor resources to be determined as an error.

· Same as Number of Members

The status of multi target monitor resources becomes "Error" when all monitor resources specified to be under the multi target monitor resource are failed, or when "Error" and "Offline" co-exist.

The status of multi target monitor resources becomes "Normal" when the status of all monitor resources specified to be under the multi target monitor resource are "Offline."

· Specify Number

The status of multi target monitor resources becomes "Error" when the number of monitor resources specified in **Error Threshold** becomes "Error" or "Offline."

When the status of some monitor resources among those specified to be under the multi target monitor resource, specify how many monitor resources need to be "Error" or "Offline" to determine that the status of multi target monitor resource is "Error."

#### **Warning Threshold**

When selected:

When the status of some monitor resources among those specified to be under the multi target monitor resource, specify how many monitor resources need to be "Error" or "Offline" to determine that the status of multi target monitor resource is "Caution."

When cleared:

Multi target monitor resources do not display an alert.

#### Initialize

Clicking **Initialize** resets the values of all items to the default values.

# Displaying the properties of the multi target monitor resource with the WebManager

- **1.** Start the WebManager. (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click an object for a multi target monitor resource information is displayed in the list view.

Multi Target Monitor Name: mtw1		Details
Properties		Value
Name	mtw1	
Comment		
Monitor Resource List	appliw1	
	fipw1	
	sdw1	
Status	Normal	
Resource Status on Each S	erver	
Server Name		Status
server1	Online	
server2	Online	

Name: Multi target monitor resource name

Comment: Comment of the multi target monitor resource

Monitor Resources: List of monitor resources

Status: Multi target monitor resource status

Server Name: Server name

Status: Status of the monitor resource status on the given server

If you click the **Details** button, the following information is displayed in the pop-up dialogue.

Properties	Value
Type	mtw
Monitor Timing	Always
Target Resource	
Interval	60
Timeout	60
Retry Count	1
Final Action	No Operation
Execute Script before Final Action	Off
Recovery Target	failover1
Recovery Target Type	Group
Reactivation Threshold	3
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Wait Time to Start Monitoring	0

Type: Monitor resource type

Monitor Timing: Timing for the monitor resource to start monitoring

Target Resource: Resource to be monitored

Interval: Interval between monitoring (in seconds)

Time to elapse from detection of an error to establish the monitor

resource as error (in seconds).

Retry Count: The number of retries to be made from detection of an error in

the monitor target to establish the error as error

Final Action: Final action at detection of an error

Execute Script before Final Action:

Recovery Target:

Whether or not script is executed when a failure is detected

Target to be recovered when an error is detected

Recovery Target Type: Type of target to be recovered when an error is detected Reactivation Threshold: The number of reactivations to be made at detection of an error

Failover Target Server: Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an error Wait Time to Start Monitoring: Time to wait before starting of monitoring (in seconds)

# Understanding registry synchronization monitor resources

Registry synchronization monitor resources monitor registry synchronization resources.

# Displaying and changing the details of the registry synchronization monitor resources

There is no detailed setting to be made for registry synchronization monitor resources.

# Displaying the registry synchronization monitor resources properties with the WebManager

- 1. Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click a registry synchronization monitor resources object, , in the tree view. The following information is displayed in the list view.

Registry Synchronization Monitor Name: reg Details	
Properties	Value
Name	regsyncw1
Comment	
Status	Normal
Resource Status on Each Serve	r
Server Name	Status
server1	Online
server2	Offline

Name: Registry synchronization monitor resource name

Comment: Comment of the registry synchronization monitor resource

Status: Registry synchronization monitor resource status

Server Name: Server name

Status: Status of the monitor resource status on the given server

If you click the **Details** button, the following information is displayed in the pop-up dialogue.

Properties	Value
Type	regsyncw
Monitor Timing	Activating
Target Resource	regsync1
Interval	60
Timeout	60
Retry Count	1
Final Action	No Operation
Execute Script before Final Action	Off
Recovery Target	failover1
Recovery Target Type	Group
Reactivation Threshold	3
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Wait Time to Start Monitoring	0

Type: Monitor resource type

Monitor Timing: Timing for the monitor resource to start monitoring

Target Resource: Resource to be monitored

Interval: Interval between monitoring (in seconds)

Time to elapse from detection of an error to establish the

monitor resource as error (in seconds).

Retry Count: The number of retries to be made from detection of an error

in the monitor target to establish the monitor resource as error

Final Action: Final action at detection of an error

Execute Script before Final Action:

Whether or not script is executed when a failure is detected

Recovery Target: Target to be recovered when an error is detected

Recovery Target Type: Type of target to be recovered when an error is detected Reactivation Threshold: The number of reactivations to be made at detection of an

error

Failover Target Server: Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an error Wait Time to Start Monitoring: Time to wait before starting of monitoring (in seconds)

## **Understanding disk TUR monitor resources**

Disk TUR monitor resources monitor the disk specified by disk resource.


#### Notes on disk TUR monitor resources

- Note 1 You cannot run the SISI Test Unit Ready command on a disk or disk interface (HBA) that does not support it. Even if your hardware supports this command, consult the driver specifications because the driver may not support it.
- Note 2 TUR monitor resources, compared to disk RW monitor resources, burdens OS and disks less.
- Note 3 In some cases, Test Unit Ready may not be able to detect actual errors in I/O to media.
- **Note 4** If you want multipath software to initiate path failover when disk path is not connected, you should set longer timeout for disk RW monitor resource than path failover time.

### Displaying and changing the disk TUR monitor resource details

- 1. Click **Monitors** on the tree view displayed on the left side of the Builder window.
- 2. List of the monitor resources is displayed in the table view on the right side of the screen. Right click the target disk TUR monitor resource, and click the **Parameter** tab in the **Monitor Resource Property** window.
- 3. On the **Parameter** tab, you can display and/or change the detailed settings by following the description below.

#### Disk TUR monitor resource parameter tab




#### Disk Resource SuspendResume

Select a disk resource.

#### **Browse**


Click this button to display the disk resources that can be registered.



Disk TUR monitor resource: disk resource selection properties

# Displaying the disk TUR monitor resources properties with the WebManager

- **1.** Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click a TUR monitor resources object, , in the tree view. The following information is displayed in the list view.



Name: Disk TUR monitor resource name

Comment of the disk TUR monitor resource

Disk Resource: Disk resource to be monitored. Status: Disk TUR monitor resource status

Server Name: Server name

Status: Status of the monitor resource status on the given server

If you click the **Details** button, the following information is displayed in the pop-up dialogue.

Properties	Value
Туре	sdw
Monitor Timing	Always
Target Resource	
Interval	60
Timeout	300
Retry Count	0
Final Action	No Operation
Execute Script before Final Action	Off
Recovery Target	failover1
Recovery Target Type	Group
Reactivation Threshold	0
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Wait Time to Start Monitoring	0

Type: Monitor resource type

Monitor Timing: Timing for the monitor resource to start monitoring

Target Resource: Resource to be monitored

Interval: Interval between monitoring (in seconds)

Timeout: Time to elapse from detection of an error to establish the monitor

resource as error (in seconds).

Retry Count: The number of retries to be made from detection of an error in

the monitor target to establish the monitor resource as error

Final Action: Final action at detection of an error

Execute Script before Final Action:

Whether or not script is executed when a failure is detected

Recovery Target: Target to be recovered when an error is detected

Recovery Target Type: Type of target to be recovered when an error is detected Reactivation Threshold: The number of reactivations to be made at detection of an error

Failover Target Server: Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an error Wait Time to Start Monitoring: Time to wait before starting of monitoring (in seconds)

## **Understanding service monitor resources**

Service monitor resources monitor service resources.

### Monitoring by service monitor resources

Service monitor resources monitor service resources in a server where they are activated. They regularly check the service status with the service control manager and if the status of the service resource becomes Stopped, it is considered as an error.

# Displaying and changing the details of the service monitor resources

There is no detailed setting to be made for service monitor resources.

# Displaying the service monitor resources properties with the WebManager

- 1. Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click a virtual computer name monitor object, in the tree view. The following information is displayed in the list view.

Service Monitor Name: servicew1		Details
Properties		Value
Name	servicew1	
Comment		
Status	Normal	
December Obstacles Control		
Resource Status on Each Sen		
Resource Status on Each Sen		Status
		Status

Name: Service monitor resource name

Comment: Comment of the service monitor resource

Status: Service monitor resource status

Server Name: Server name

Status: Status of the monitor resource status on the given server

If you click the **Details** button, the following information is displayed in the pop-up dialogue.

Properties	Value
Type	servicew
Monitor Timing	Activating
Target Resource	service1
Interval	60
Timeout	60
Retry Count	1
Final Action	No Operation
Execute Script before Final Action	Off
Recovery Target	failover1
Recovery Target Type	Group
Reactivation Threshold	3
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Wait Time to Start Monitoring	0

Type: Monitor resource type

Monitor Timing: Timing for the monitor resource to start monitoring

Target Resource: Resource to be monitored

Interval: Interval between monitoring (in seconds)

Time to elapse from detection of an error to establish the monitor

resource as error (in seconds).

Retry Count: The number of retries to be made from detection of an error in

the monitor target to establish the monitor resource as error

Final Action: Final action at detection of an error

Execute Script before Final Action:

Whether or not script is executed when a failure is detected

Recovery Target: Target to be recovered when an error is detected

Recovery Target Type: Type of target to be recovered when an error is detected

Reactivation Threshold: The number of reactivations to be made at detection of an error

Failover Target Server: Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an error Wait Time to Start Monitoring: Time to wait before starting of monitoring (in seconds)

## Understanding print spooler monitor resources

Print spooler monitor resources monitor print spooler resources. They regularly check the spooler service status with the service control manager and if the status of the print spooler monitor resource becomes Stopped, it is considered as an error.

# Displaying and changing the details of the print spooler monitor resources

There is no detailed setting to be made for print spooler monitor resources.

# Displaying the print spooler monitor resources properties with the WebManager

- 1. Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click a print spooler monitor resources object, , in the tree view. The following information is displayed in the list view.

Print Spooler Monitor Name: sp	oolw1 Details
Properties	Value
Name	spoolw1
Comment	
Status	Normal

Resource Status on Each Server		
Server Name	Status	
server1	Online	
server2	Offline	
Name: Print spooler monitor resource name		
Comment: C	Comment of the print spooler monitor resource	
Status: Pr	Print spooler monitor resource status	
	erver name tatus of the monitor resource status on the given server	

If you click the **Details** button, the following information is displayed in the pop-up dialogue.

Properties	Value
Туре	spoolw
Monitor Timing	Activating
Target Resource	spool1
Interval	60
Timeout	60
Retry Count	1
Final Action	No Operation
Execute Script before Final Action	Off
Recovery Target	failover1
Recovery Target Type	Group
Reactivation Threshold	3
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Wait Time to Start Monitoring	0

Type: Monitor resource type

Monitor Timing: Timing for the monitor resource to start monitoring

Target Resource: Resource to be monitored

Interval: Interval between monitoring (in seconds)

Timeout: Time to elapse from detection of an error to establish the monitor

resource as error (in seconds).

Retry Count: The number of retries to be made from detection of an error in

the monitor target to establish the monitor resource as error

Final Action: Final action at detection of an error

Execute Script before Final Action:

Whether or not script is executed when a failure is detected

Recovery Target: Target to be recovered when an error is detected

Recovery Target Type:

Type of target to be recovered when an error is detected

The number of reactivations to be made at detection of on

Reactivation Threshold: The number of reactivations to be made at detection of an error

Failover Target Server: Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an error Wait Time to Start Monitoring: Time to wait before starting of monitoring (in seconds)

# Understanding virtual computer name monitor resources

Virtual computer name monitor resources monitor virtual computer name resources.

### Monitoring by virtual computer name monitor resources

Virtual computer name monitor resources monitor virtual computer name resources in a server where they are activated. Virtual computer name monitor resources regularly check the virtual computer name control process. It is considered an error if the process is not found.

### Virtual computer name monitor resource

- **Note 1** This monitor resource is automatically registered when the virtual computer name resource is added.
- Note 2 The effective final actions when an error in this resource is detected is set to **Stop the cluster service and shutdown OS**, **Stop the cluster service and reboot OS** and **Generating of intentional Stop Error** only. This is because the OS reboot is required for correctly activating virtual computer name resource when virtual computer name control process disappeared. The default is **Stop the cluster service and shutdown OS**. If the virtual computer name control process is not found, the group fails over by shutting down or rebooting the server that detected an error.

# Displaying and changing the details of the virtual computer name resources

There is no detailed setting to be made for virtual computer name monitor resources.

# Displaying the virtual computer name monitor resource properties with the WebManager

- 1. Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click a virtual IP monitor object, , in the tree view. The following information is displayed in the list view.

Virtual Computer Name Monitor	Name: vco Details
Properties	Value
Name	vcomw1
Comment	
Status	Normal

Resource Status on Each Server	
Server Name	Status
server1	Online
server2	Offline

Name: Virtual computer name monitor resource name

Comment: Comment of the virtual computer name monitor resource Status: Status of the virtual computer name monitor resource

Server Name: Server name

Status: Status of the monitor resource status on the given server

If you click the **Details** button, the following information is displayed in the pop-up dialogue.

Properties	Value
Type	vcomw
Monitor Timing	Activating
Target Resource	vcom1
Interval	60
Timeout	60
Retry Count	1
Final Action	Stop the cluster service and shutdown OS
Execute Script before Final Action	Off
Recovery Target	cluster
Recovery Target Type	Itself
Reactivation Threshold	0
Failover Target Server	Stable Server
Failover Threshold	0
Wait Time to Start Monitoring	0

Type: Monitor resource type

Monitor Timing: Timing for the monitor resource to start monitoring

Target Resource: Resource to be monitored

Interval: Interval between monitoring (in seconds)

Time to elapse from detection of an error to establish the

monitor resource as error (in seconds).

Retry Count: The number of retries to be made from detection of an error

in the monitor target to establish the monitor resource as error

Final Action: Final action at detection of an error

Execute Script before Final Action:

Whether or not script is executed when a failure is detected

Recovery Target: Target to be recovered when an error is detected

Recovery Target Type: Type of target to be recovered when an error is detected Reactivation Threshold: The number of reactivations to be made at detection of an

error

Failover Target Server: Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an error Wait Time to Start Monitoring: Time to wait before starting of monitoring (in seconds)

## **Understanding virtual IP monitor resources**

Virtual IP monitor resources monitor virtual IP resources.

### Monitoring by virtual IP monitor resources


Virtual IP monitor resources monitor virtual IP resources in a server where they are activated. Virtual IP monitor resources monitor whether the virtual IP address exists in the list of IP addresses. If the virtual IP address does not exist, it is considered as an error.

## Displaying and changing the details of the virtual IP monitor resources

There is no detailed setting to be made for virtual IP monitor resources.

# Displaying the virtual IP monitor resource properties with the WebManager

- 1. Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click an application monitor resources object, , in the tree view. The following information is displayed in the list view.



Name: Virtual IP monitor resource name

Comment: Comment of the virtual IP monitor resource Status: Status of the virtual IP monitor resource

Server Name: Server name

Status: Status of the monitor resource on the given server

If you click the **Details** button, the following information is displayed in the pop-up dialogue.

Properties	Value
Type	vipw
Monitor Timing	Activating
Target Resource	vip1
Interval	60
Timeout	60
Retry Count	1
Final Action	No Operation
Execute Script before Final Action	Off
Recovery Target	failover1
Recovery Target Type	Group
Reactivation Threshold	3
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Wait Time to Start Monitoring	0

Type: Monitor resource type

Monitor Timing: Timing for the monitor resource to start monitoring

Target Resource: Resource to be monitored

Interval: Interval between monitoring (in seconds)

Time to elapse from detection of an error to establish the

monitor resource as error (in seconds).

Retry Count: The number of retries to be made from detection of an error

in the monitor target to establish the monitor resource as error

Final Action: Final action at detection of an error

Execute Script before Final Action:

Whether or not script is executed when a failure is detected

Recovery Target: Target to be recovered when an error is detected

Recovery Target Type: Type of target to be recovered when an error is detected Reactivation Threshold: The number of reactivations to be made at detection of an

error

Failover Target Server: Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an error Wait Time to Start Monitoring: Time to wait before starting of monitoring (in seconds)

### **Understanding CIFS monitor resources**

CIFS monitor resources monitor CIFS resources.

### Monitoring by CIFS monitor resources

CIFS resources monitor CIFS resources in a server where they are activated.

CIFS monitor resources obtain the information of shared folders publicized on a server and monitor if the shared folders publicized by CIFS resources are contained. An error is detected when the shared folders publicized by CIFS resources do not exist.


CIFS monitor resources also monitor accessibility to the shared folders. When auto-saving of shared configuration of drive is executed, activation monitoring of the function to share and save the shared configuration is also be executed.

#### Notes on CIFS monitor resources

- When access check needs to be performed, the specified access method must be permitted for the local system account in the CIFS resources to be monitored.
- When auto-saving of shared configuration of drive is executed on the monitoring target CIFS resource and the access check is executed on CIFS monitor resource, the specified access as a check method is executed on all the shared folder of the auto-saving target drive. When Read of folder check/file check is specified as checking method, the folder/file specified on Path must be on each shared folder.

### Displaying and changing the details of CIFS monitor resources

- 1. From the tree view displayed on the left pane of the Builder. Click **Monitors**.
- **2.** The monitor resources list is displayed on the table view in the right of the window. Right-click the desired CIFS monitor resource name, and click **Properties**. In the properties dialog box, click the **Parameter** tab.
- **3.** Display and/or change the detailed settings on the **Parameter** tab.



### Access Check SuspendResume

Specify the way to check access to the shared folders.

Disable (default)

Access check is not performed.

♦ Folder Check

Check if you can refer to the folder specified in Path.

♦ File Check

Check if reading and writing to the file specified in **Path** can be performed.

### Path (Within 256bytes) SuspendResume

Specify the file/folder for access check by using a relative path from the shared folder.

For folder check, specify the folder in the shared folder.

When **Read/Write** is selected as a file check method, the specified file is newly created. Make sure to specify a file name that does not overlap with other file names.

When **Read** is selected a file check method, specify a file in the shared folder.

### Check SuspendResume

Select the way to check the access for File Check.

◆ Read/Write (default value)

Write data to the file and check it can be read.

◆ Read

Open the files and check it can be read.

## Displaying CIFS monitor resource properties with the WebManager

**1.** Start the WebManager.

(http://CIFS\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003.))

**2.** Click the application monitor object in the tree view.



CIFS Monitor Name: cifsw1	Details	
Properties	Value	
Name	cifsw1	
Comment		
Status	Normal	
Name:	CIFS monitor resource name	
Comment:	Comment of CIFS monitor resource	
States:	Normal	

Resource Status on Each Server	
Server Name Status	
server1	Online
server2	Offline

Server name Server name:

Status of monitor resource on the given server Status:

If you click the **Details** button, the following information is displayed in the pop-up dialogue.

Properties	Value
Type	cifsw
Monitor Timing	Activating
Target Resource	cifs1
Interval	60
Timeout	60
Retry Count	1
Final Action	Stop Group
Execute Script before Final Action	Off
Recovery Target	Α
Recovery Target Type	Group
Reactivation Threshold	3
Failover Target Server	Stable Server
Failover Threshold	0
Wait Time to Start Monitoring	0
Access Cehck	Foldero check
Check Path	sample
Check Method	Read/Write

Type: Monitor resource type

Monitor Timing: Timing for the monitor resource to start monitoring Target Resource: Resource to be monitored

Interval: Interval between monitoring (in seconds)

Time to elapse from detection of an error to establish the

monitor resource as error (in seconds).

Retry Count: The number of retries to be made from detection of an error

in the monitor target to establish the monitor resource as error

Final Action: Final action at detection of an error

Execute Script before Final Action:

Whether or not script is executed when a failure is detected

Recovery Target: Target to be recovered when an error is detected

Recovery Target Type: Type of target to be recovered when an error is detected Reactivation Threshold: The number of reactivations to be made at detection of an

error

Failover Target Server: Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an error Wait Time to Start Monitoring: Time to wait before starting of monitoring (in seconds)

Access Check: The way of checking the access

Check Path: The path for the folders/files to be checked

Check Method: The way of performing file check

# **Understanding NAS monitor resources**

NAS monitor resources monitor NAS resources.

## Monitoring by NAS monitor resources

NAS monitor resources monitor NAS resources in a server where they are activated.

Check that the network drive mounted by NAS resources is connected.

## Displaying and changing the details of NAS monitor resources


There is no detailed setting to be made for NAS monitor resources.

# Displaying NAS monitor resources properties with the WebManager

**1.** Start the WebManager.

(http://FIP \_address\_for\_the\_WebManager\_group:port\_number (Default value is 29003.))

2. Click the NAS monitor resources object, in the tree view. The following information is displayed in the list view.



Name: NAS monitor resource name
Comment: Comment of NAS monitor resource
Status: Status of NAS monitor resource

Resource Status on Each Server	
Server Name Status	
server1	Online
server2	Offline

Server: Server name

Status: Status of monitor resource on the given server

If you click the **Details** button, the following information is displayed in the pop-up dialogue.

Properties	Value
Туре	nasw
Monitor Timing	Activating
Target Resource	nas1
Interval	60
Timeout	60
Retry Count	1
Final Action	Stop Group
Execute Script before Final Action	Off
Recovery Target	A
Recovery Target Type	Group
Reactivation Threshold	3
Failover Target Server	Stable Server
Failover Threshold	0
Wait Time to Start Monitoring	0

Type: Monitor resource type

Monitor Timing: Timing for the monitor resource to start monitoring

Target Resource: Resource to be monitored.

Interval: Interval between monitoring (in seconds)

Time to elapse from detection of an error to establish the

monitor resource as error (in seconds).

Retry Count: The number of retries to be made from detection of an error

in the monitor target to establish the monitor resource as error

Final Action: Final action at detection of an error

Execute Script before Final Action:

Whether or not script is executed when a failure is detected

Recovery Target: Target to be recovered when an error is detected

Recovery Target Type: Type of target to be recovered when an error is detected Reactivation Threshold: The number of reactivations to be made at detection of an

error

Failover Target Server: Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an error Wait Time to Start Monitoring: Time to wait before starting of monitoring (in seconds)

# Understanding hybrid disk monitor resources

Hybrid disk monitor resources monitor a mirror partition device or mirror driver works properly.

## Note on hybrid disk monitor resources

This resource is automatically registered when a hybrid disk resource is added. A hybrid disk monitor resource corresponding to the hybrid disk resource is automatically registered. When this resource is deleted, be careful that auto mirror recovery cannot be executed.

Refer to "Automatically recovering from mirroring" in "Connecting mirror disks/hybrid disks manually" of "Chapter 12 Troubleshooting" for the details.

## Displaying and changing the hybrid disk monitor resource details

- 1. Click **Monitors** on the tree view displayed on the left side of the Builder window.
- **2.** List of the monitor resources is displayed in the table view on the right side of the screen. Right-click the target mirror disk monitor resource, and click the **Parameter** tab in the **Monitor Resource Property** window.
- **3.** On the **Parameter** tab, you can display and/or change the detailed settings by following the description below.

#### Note:

Do not change the settings shown below on the **Error Detection** tab.

The Error Detection tab settings:


Recovery object Hybrid disk resource name

Reactivation threshold Zero (Never)

Failover Target Server Stable operation server

Failover threshold Set as many as the number of the servers

Final Action No Operation




### Hybrid Disk Resource SuspendResume

The hybrid disk resource to be monitored is displayed.


#### **Browse**

Click this button to display the dialog box where you can select a hybrid disk resource to be monitored. Hybrid disk resources registered with the cluster are displayed in a tree view. You can select only hybrid disk resources in this view. Select a hybrid disk resource and click  $\mathbf{OK}$ .



# Displaying the hybrid disk monitor resource properties with the WebManager

- **1.** Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click an object for a hybrid disk monitor resource, , in the tree view. The following information is displayed in the list view.



Name: Hybrid disk monitor resource name

Comment: Comment of the hybrid disk monitor resource

Hybrid Disk Resource Name: Name of the hybrid disk resource to be monitored by the

hybrid disk monitor resource

Status: Hybrid disk monitor resource status

Server Name	Status
server1	Online
server2	Online

Server Name: Server name

Status: Status of the monitor resource on the given server

If you click the **Details** button, the following information is displayed in the pop-up dialog box.

Properties	Value
Type	hdw
Monitor Timing	Always
Target Resource	
Interval	30
Timeout	999
Retry Count	0
Final Action	No Operation
Execute Script before Final Action	Off
Recovery Target	hd_Z
Recovery Target Type	Resource
Reactivation Threshold	0
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Wait Time to Start Monitoring	10

Type: Monitor resource type

Monitor Timing: Timing for the monitor resource to start monitoring

Target Resource: Resource to be monitored

Interval: Interval between monitoring (in seconds)

Timeout: Time to elapse from detection of an error to establish

the monitor resource as error (in seconds)

Retry Count: The number of retries to be made from detection of an

error in the monitor target to establish the monitor

resource as error.

Final Action: Final action at detection of an error

Execute Script before Final Action: Whether or not script is executed when a failure is

detected

Recovery Target: Target to be recovered when an error is detected Recovery Target Type: Type of target to be recovered when an error is

detected

Reactivation Threshold: The number of reactivations to be made at detection

of an error

Failover Target Server: Determination method of Failover Target Server Failover Threshold: The number of failovers to be made at detection of an

error

Wait Time to Start Monitoring: Time to wait before starting monitoring (in seconds)

# Understanding hybrid disk TUR monitor resources

Hybrid disk TUR monitor resources monitor the disk specified by hybrid disk resource.

### Notes on hybrid disk TUR monitor resources

Note 1 This resource is automatically registered when a hybrid disk resource is added. Hybrid disk TUR monitor resources corresponding hybrid disk resources are automatically registered.

When this resource is deleted, be careful that auto mirror recovery cannot be executed.

Refer to "Automatically recovering from mirroring" in "Connecting mirror disks/hybrid disks manually" of "Chapter 12 Troubleshooting" for the details.

Note 2 You cannot run the SISI Test Unit Ready command on a disk or disk interface (HBA) that does not support it. Even if your hardware supports this command, consult the driver specifications because the driver may not support it.

Note 3 TUR monitor resources, compared to disk RW monitor resources, burdens OS and disks less.

Note 4 In some cases, Test Unit Ready may not be able to detect actual errors in I/O to media.

# Displaying and changing the hybrid disk TUR monitor resource details

- 1. Click **Monitors** on the tree view displayed on the left side of the Builder window.
- 2. List of the monitor resources is displayed in the table view on the right side of the screen. Right click the target disk TUR monitor resource, and click the **Parameter** tab in the **Monitor Resource Property** window.
- 3. On the **Parameter** tab, you can display and/or change the detailed settings by following the description below.

### Note:

Do not change the settings shown below on the **Error Detection** tab.

The Error Detection tab settings:

Recovery object Hybrid disk resource name


Reactivation threshold Zero (Never)

Failover Target Server Stable operation server

Failover threshold Set as many as the number of the servers

Final Action No Operation

Hybrid disk TUR monitor resource parameter tab




### Hybrid Disk Resource SuspendResume

Select a hybrid disk resource.


### **Browse**

Click this button to display the hybrid disk resources that can be registered.



# Displaying the hybrid disk TUR monitor resources properties with the WebManager

- 1. Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click a hybrid disk TUR monitor resources object, , in the tree view. The following information is displayed in the list view.



If you click the **Details** button, the following information is displayed in the pop-up dialog.

Properties	Value
Туре	hdtw
Monitor Timing	Always
Target Resource	
Interval	60
Timeout	300
Retry Count	0
Final Action	No Operation
Execute Script before Final Action	Off
Recovery Target	hd_Z
Recovery Target Type	Resource
Reactivation Threshold	0
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Wait Time to Start Monitoring	0

Type: Monitor resource type

Monitor Timing: Timing for the monitor resource to start monitoring

Target Resource: Resource to be monitored

Interval: Interval between monitoring (in seconds)

#### Chapter 7 Monitor resource details

Timeout: Time to elapse from detection of an error to establish the monitor

resource as error (in seconds).

Retry Count: The number of retries to be made from detection of an error in

the monitor target to establish the monitor resource as error

Final Action: Final action at detection of an error

Execute Script before Final Action:

Whether or not script is executed when a failure is detected

Recovery Target: Target to be recovered when an error is detected

Recovery Target Type: Type of target to be recovered when an error is detected Reactivation Threshold: The number of reactivations to be made at detection of an error

Failover Target Server: Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an error Wait Time to Start Monitoring: Time to wait before starting of monitoring (in seconds)

# **Understanding custom monitor resources**

Custom monitor resources monitor system by executing an arbitrary script.

## Monitoring by custom monitor resources


Custom monitor resources monitor system by an arbitrary script.

When Monitor Type is **Synchronous**, custom monitor resources regularly run a script and detect errors from its error code.

When Monitor Type is **Asynchronous**, custom monitor resources run a script upon start monitoring and detect errors if the script process disappears.

# Displaying and changing the details of the custom monitoring resources

- 1. Click **Monitors** on the tree view displayed on the left side of the Builder window.
- List of the monitor resources is displayed in the table view on the right side of the screen.
  Right click the target custom monitor resource, and click the **Parameter** tab in the **Monitor Resource Property** window.
- 3. On the **Parameter** tab, you can display and/or change the detailed settings by following the description below.



### **User Application**

Use an executable file (executable batch file or execution file) on the server as a script. For the file name, specify an absolute path or name of the executable file of the local disk on the server.

Each executable files is not included in the cluster configuration information of the Builder. They must be prepared on each server since they cannot be edited nor uploaded by the Builder.

#### Script created with this product

Specify a script file which is prepared by the Builder as a script with an absolute path of local disk on server.

File (Within 1023 bytes)

Specify a script to be executed (executable batch file or execution file) when you select **User Application**.

#### View

Click here to display the script file with a editor when you select **Script created with this product**. The information edited and stored with the editor is not reflected. You cannot display the script file if it is currently displayed or edited.

#### **Edit**


Click here to edit the script file with the editor when you select **Script created with this product**. Overwrite the script file to reflect the change. You cannot edit the script file if it is currently displayed or edited. You cannot modify the name of the script file.

#### Replace

Click here to replace the contents of a script file with the contents of the script file which you selected in the file selection dialog box when you select **Script created with this product**. You cannot replace the script file if it is currently displayed or edited. Select a script file only. Do not select binary files (applications), and so on.

#### Change

Click here to display the **Change Script Editor** dialog. You can change editor for displaying or editing a script to an arbitrary editor.



#### **Standard Editor**

Select here to use a standard editor (Notepad in Windows) as a script editor.

#### **External Editor**

Select here to specify an arbitrary script editor. Click **Browse** to specify the editor to be used.

### Monitor Type SuspendResume

Select a monitor type.

- Synchronous (Default)
  - Custom monitor resources regularly run a script and detect errors from its error code.
- Asynchronous

Custom monitor resources run a script upon start monitoring and detect errors if the script process disappears.

Normal Return Value (Within 1023 bytes) SuspendResume


When **Asynchronous** is selected for **Monitor Type**, set the values of script error code to be determined as normal. If you want to set two or more values here, separate them by commas like 0,2,3 or connect them with a hyphen to specify the range like 0-3.

Default value: 0

# Displaying the custom monitor resource properties with the Web Manager

. Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).

2. Click a custom monitor resources object, , in the tree view. The following information is displayed in the list view.



If you click **Details** button, the following information is displayed in the pop-up dialog box:

Common server2 server1	
Properties	Value
Туре	genw
Monitor Timing	Always
Target Resource	
Interval	60
Timeout	120
Retry Count	1
Final Action	No Operation
Execute Script before Final Action	Off
Recovery Target	ExpressCluster
Recovery Target Type	Itself
Reactivation Threshold	0
Failover Target Server	Stable Server
Failover Threshold	0
Wait Time to Start Monitoring	0
Monitor Type	Synchronous
Normal Return Value	0

Type: Monitor resource type

Monitor Timing: Timing for the monitor resource to start monitoring

Target Resource: Resource to be monitored

Interval: Interval between monitoring (in seconds)
Timeout: Time to elapse from detection of an error to

establish the monitor resource as error (in seconds)

Retry Count: The number of retries to be made from detection of an error

in the monitor target to establish the error as error

Final Action: Final action at detection of an error

Execute Script before Final Action: Whether or not script is executed when a failure is detected

Recovery Target: Target to be recovered when an error is detected

Recovery Target Type: Type of target to be recovered when an error is detected Reactivation Threshold: The number of times activation is retried when an

activation error is detected

Failover Destination Server Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an error

Wait Time to Start Monitoring: Time to wait before start monitoring (in seconds)

Monitor Type Execution method of monitor type

# **Understanding DB2 monitor resources**

DB2 monitor resources monitor DB2 database that runs on the server.

### **DB2** monitor resources

- **Note 1** For the supported DB2 versions, refer to the *Getting Started Guide*.
- Note 2 DLL interface (DB2CLI.DLL/DB2CLI64.DLL) needs to be installed on servers where monitoring is performed because DB2 CLI is used for monitoring. For target monitoring resources, specify a service resource or a script resource that starts DB2. Monitoring starts after the target resource is activated; however, if the database cannot be started right after the target resource is activated, adjust the time by using Wait Time to Start Monitoring.
- Note 3 A monitor table is created when monitoring is started and it is deleted when monitoring is stopped due to the stop of the failover group. When monitoring is temporarily stopped or when server fails before the failover group stops due to system error, the monitor table will not be deleted. It is not an error even if an alert message saying that "a monitor table exists" is displayed next time when monitoring is started.
- **Note 4** DB2 may produce operation logs for each monitoring. Configure DB2 settings if this needs to be adjusted.

### Monitoring by DB2 monitor resources


A monitor table is created on the database. Maximum of 10-digits numeric data is read and written by issuing SQL statements. As a result of monitoring, the following is considered as an error:

- (1) When connection to the database fails.
- (2) When an error is notified as a response to the issue of SQL statement.
- (3) When the written data and read data do not match.

The SQL statement to use is: create/drop/insert/update/select.

## Displaying and changing the disk DB2 monitor resource details

- 1. Click **Monitors** on the tree view displayed on the left side of the Builder window.
- 2. List of the monitor resources is displayed in the table view on the right side of the screen. Right click the target DB2 monitor resource, and click the **Parameter** tab in the **Monitor Resource Property** window.
- 3. On the **Parameter** tab, you can display and/or change the detailed settings by following the description below.



Database Name Within 255 bytes SuspendResume

Specify the database to be monitored. You must specify the database.

Default value: None

Instance Name Within 255 bytes SuspendResume

Specify the instance name of the database to be monitored. You must specify the instance name.

Default value: DB2

User Name Within 255 bytes SuspendResume

Specify the user name to log on to the database.

Default value: db2admin

Password Within 255 bytes SuspendResume

Specify the password to log on to the database. Click **Change** and enter the password in the dialog box.

Default value: None

Monitor Table Name Within 255 bytes SuspendResume

Specify the name of a monitor table created on the database. You must specify the name. Make sure not to specify the same name as the table used for operation because a monitor table will be created and deleted. Be sure to set the name different from the reserved word in SQL statements.

Default value: DB2WATCH

## Displaying the DB2 monitor resource properties with the WebManager

3. Start the WebManager

(http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).

displayed in the list view.



DB2 Monitor Name: db2w1	Details
Properties	Value
Name	db2w1
Comment	
Database Name	Sample
Instance	DB2
Monitor Table	DB2WATCH
Status	Normal
Resource Status on Each Se	rver
Server Name	Status
server1	Online
server2	Offline
NI DD	20 :4

Name: DB2 monitor resource name

Comment of the DB2 monitor resource Comment:

Database Name: The database to be monitored

Instance Name: The database instance to be monitored

A table name for monitoring Monitor Table Name:

Status of the DB2 monitor resource Status:

Server Name: Server name

Status: Status of the monitor resource on the given server

### If you click the **Details** button, the following information is displayed in the pop-up dialogue.

1 7 1 1 1
Value
db2w
Activating
db2
60
120
2
Stop the cluster service and shutdown OS
Off
failover1
Group
0
Stable Server
Number of Servers
0

Monitor resource type Type: Monitor Timing: Timing to start monitoring Target Resource: Resource to be monitored

Interval between monitoring (in seconds) Interval:

Section II Resource details

### Chapter 7 Monitor resource details

Time to elapse from detection of an error to establish the error

as error (in seconds).

Retry Count: The number of retries to be made from detection of an error

in the monitor target to establish the error as error

Final Action: Final action at detection of an error

Execute Script before Final Action:

Whether or not script is executed when a failure is detected

Recovery Target: Target to be recovered when an error is detected

Recovery Target Type: Type of target to be recovered when an error is detected Reactivation Threshold: The number of reactivations to be made at detection of an

error

Failover Target Server: Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an error Wait Time to Start Monitoring: Time to wait before starting of monitoring (in seconds)

# **Understanding FTP monitor resources**

FTP monitor resources monitor FTP services that run on the server. FTP monitor resources monitor FTP protocol and they are not intended for monitoring specific applications. FTP monitor resources monitor various applications that use FTP protocol.

### FTP monitor resources

- **Note 1** For monitoring target resources, specify service resources or script resources that start FTP monitor resources. Monitoring starts after target resource is activated. However, if FTP monitor resources cannot be started immediately after target resource is activated, adjust the time using **Wait Time to Start Monitoring.**
- **Note 2** FTP service may produce operation logs for each monitoring. Configure FTP settings if this needs to be adjusted.


## Monitoring by FTP monitor resources

FTP monitor resources connect to the FTP server and execute the command for acquiring the file list. As a result of monitoring, the following is considered as an error:

- (1) When connection to the FTP service fails.
- (2) When an error is notified as a response to the FTP command.

### Displaying and changing the FTP monitor resource details

- 1. Click **Monitors** on the tree view displayed on the left side of the Builder window.
- 2. List of the monitor resources is displayed in the table view on the right side of the screen. Right click the target FTP monitor resource, and click the **Parameter** tab in the **Monitor Resource Property** window.
- 3. On the **Parameter** tab, you can display and/or change the detailed settings by following the description below.



### IP Address (Within 255 bytes) SuspendResume

Specify the IP address of the FTP server to be monitored. You must specify this IP address. If it is multi-directional standby server, specify FIP.

Default value: 127.0.0.1

### **Port No.** (1-65535) **SuspendResume**

Specify the FTP port number to be monitored. You must specify a port number.

Default value: 21

User Name Within 255 bytes SuspendResume

Specify the user name to log on to FTP.

Default value: None

Password Within 255 bytes SuspendResume

Specify the password to log on to FTP. Click **Change** and enter the password in the dialog box.

Default value: None

# Displaying the FTP monitor resource properties with the WebManager

1. Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).

2. Click a FTP monitor resources object, , in the tree view. The following information is displayed in the list view.

FTP Monitor Name: ftpw1	Details
Properties	Value
Name	ftpw1
Comment	
IP Address	127.0.0.1
Port	21
Status	Normal
Resource Status on Each Server	
Server Name	Status
server1	Online
server2	Offline

Name: FTP monitor resource name

Comment: Comment of the FTP monitor resource
IP Address: IP address of the FTP server to be monitored
Port No.: Port number of the FTP to be monitored
Status: Status of the FTP monitor resource

Server Name: Server name

Status: Status of the monitor resource on the given server

ExpressCluster X 2.1 for Windows Reference Guide

### If you click the **Details** button, the following information is displayed in the pop-up dialogue.

Properties	Value
Type	ftpw
Monitor Timing	Activating
Target Resource	ftp
Interval	30
Timeout	60
Retry Count	3
Final Action	Stop the cluster service and shutdown OS
Execute Script before Final Action	Off
Recovery Target	failover1
Recovery Target Type	Group
Reactivation Threshold	0
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Wait Time to Start Monitoring	0

Type: Monitor resource type
Monitor Timing: Timing to start monitoring
Resource to be monitored

Interval: Interval between monitoring (in seconds)

Time to elapse from detection of an error to establish the error

as error (in seconds).

Retry Count: The number of retries to be made from detection of an error

in the monitor target to establish the error as error

Final Action: Final action at detection of an error

Execute Script before Final Action:

Whether or not script is executed when a failure is detected

Recovery Target: Target to be recovered when an error is detected

Recovery Target Type: Type of target to be recovered when an error is detected Reactivation Threshold: The number of reactivations to be made at detection of an

error

Failover Target Server Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an error Wait Time to Start Monitoring: Time to wait before starting of monitoring (in seconds)

# **Understanding HTTP monitor resources**

HTTP monitor resources monitor HTTP services that run on the server. HTTP monitor resources monitor HTTP protocol but they are not intended for monitoring specific applications. HTTP monitor resources monitor various applications that implement HTTP protocol.

### **HTTP** monitor resources

- Note 1 For monitoring target resources, specify service resources or script resources that start HTTP services. Monitoring starts after a target resource is activated. However, if HTTP service cannot be started immediately after the target resource is activated, adjust the time using Wait Time to Start Monitoring.
- **Note 2** HTTP service may produce operation logs for each monitoring operation. Configure HTTP settings if this needs to be adjusted.


## Monitoring by HTTP monitor resources

HTTP monitor resources connect to the HTTP server and execute the command for acquiring HTTP header. As a result of monitoring, the following is considered as an error:

- (1) When connection to the HTTP service fails.
- (2) When an error is notified as a response to the command.

## Displaying and changing the HTTP monitor resource details

- 1. Click **Monitors** on the tree view displayed on the left side of the Builder window.
- List of the monitor resources is displayed in the table view on the right side of the screen.
   Right click the target HTTP monitor resource, and click the **Parameter** tab in the **Monitor Resource Property** window.
- 3. On the **Parameter** tab, you can display and/or change the detailed settings by following the description below.



#### **Connecting Destination** (Within 255 bytes)

SuspendResume

You must specify the IP address of the HTTP server to be monitored and this IP address. If it is multi-directional standby server, specify FIP.

Default value: 127.0.0.1

### Port Number (1 – 65535) SuspendResume

You must specify the port number of the HTTP to be monitored.

Default value: 80 (HTTP) 443 (HTTPS)

### Monitor URI Within 255 bytes SuspendResume

Specify the URI of the HTTP to be monitored. If URI is not specified, the document root is monitored. It is not necessary to create a monitoring page. If a URI is specified, that URI is monitored. The specified URI needs to allow anonymous access.

Write the following in URI form from the DocumentRoot.

(Example) When the URI of the web page to be monitored is as follows:

http://WebServer:80/watch/sample.htm

/watch/sample.htm Default value: None

### Protocol SuspendResume

Configure protocol used for communication with HTTP server. In general, HTTP is selected. If you need to connect with HTTP over SSL, select HTTPS.

# Displaying the HTTP monitor resource properties with the WebManager

- 1. Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click an HTTP monitor resources object, in the tree view. The following information is displayed in the list view.

Properties	Value
Name	httpw
Comment	
Connecting Destination	127.0.0.1
Port	80
URI	
Protocal	HTTP
Status	Normal

Name: HTTP monitor resource name

Comment: Comment of the HTTP monitor resource
Connecting Destination: IP address of the HTTP server to be monitored
Port: Port number of the HTTP to be monitored

URI: URI to be monitored

Protocol: Protocol to be used for monitoring Status: Status of the HTTP monitor resource

Resource Status on Each Server	
Server Name	Status
server1	Online
server2	Offline

Server Name: Server name

Status: Status of the monitor resource on the given server

### If you click the **Details** button, the following information is displayed in the pop-up dialogue.

Properties	Value
Туре	httpw
Monitor Timing	Activating
Target Resource	http
Interval	30
Timeout	60
Retry Count	3
Final Action	Stop the cluster service and shutdown OS
Execute Script before Final Action	Off
Recovery Target	failover1
Recovery Target Type	Group
Reactivation Threshold	0
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Wait Time to Start Monitoring	0

Type: Monitor resource type
Monitor Timing: Timing to start monitoring
Resource to be monitored

Interval: Interval between monitoring (in seconds)

Time to elapse from detection of an error to establish the error

as error (in seconds).

Retry Count: The number of retries to be made from detection of an error

in the monitor target to establish the error as error

Final Action: Final action at detection of an error

Execute Script before Final Action:

Whether or not script is executed when a failure is detected

Recovery Target: Target to be recovered when an error is detected
Recovery Target Type: Type of target to be recovered when an error is detected

Reactivation Threshold: The number of reactivations to be made at detection of an

error

Failover Target Server The server to be the failover destination at detection of an

error

Failover Threshold: The number of failovers to be made at detection of an error Wait Time to Start Monitoring: Time to wait before starting of monitoring (in seconds)

# **Understanding IMAP4 monitor resources**

IMAP4 monitor resources monitor IMAP4 services that run on the server. IMAP4 monitor resources monitor IMAP4 protocol but they are not intended for monitoring specific applications. IMAP4 monitor resources monitor various applications that use IMAP4 protocol.

### **IMAP4** monitor resources

- **Note 1** For monitoring target resources, specify service resources or script resources that start IMAP4 services. Monitoring starts after target resource is activated. However, if IMAP4 services cannot be started immediately after a target resource is activated, adjust the time using **Wait Time to Start Monitoring.**
- **Note 2** IMAP4 services may produce operation logs for each monitoring. Configure IMAP4 settings if this needs to be adjusted.


## Monitoring by IMAP4 monitor resources

IMAP4 monitor resources connect to the IMAP4 server and execute the command to verify the operation. As a result of monitoring, the following is considered as an error:

- (1) When connection to the IMAP4 server fails.
- (2) When an error is notified as a response to the command.

## Displaying and changing the IMAP4 monitor resource details

- 1. Click **Monitors** on the tree view displayed on the left side of the Builder window.
- List of the monitor resources is displayed in the table view on the right side of the screen.
   Right click the target IMAP4 monitor resource, and click the **Parameter** tab in the **Monitor Resource Property** window.
- 3. On the **Parameter** tab, you can display and/or change the detailed settings by following the description below.



### IP Address (Within 255 bytes) SuspendResume

Specify the IP address of the IMAP4 server to be monitored. You must specify this IP address. If it is multi-directional standby server, specify FIP.

Default value: 127.0.0.1

### Port Number (1 – 65535) SuspendResume

Specify the port number of the IMAP4 to be monitored. You must specify this port number.

Default value: 143

User Name Within 255 bytes SuspendResume

Specify the user name to log on to IMAP4.

Default value: None

Password Within 255 bytes SuspendResume

Specify the password to log on to IMAP4. Click Change and enter the password in the dialog box.

Default value: None

### Authentication Method SuspendResume

Select the authentication method to log on to IMAP4. It must follow the settings of IMAP4 being used:

• AUTHENTICATE LOGIN (Default value)

The encryption authentication method that uses the AUTHENTICATE LOGIN command.

LOGIN

The plaintext method that uses the LOGIN command.

# Displaying the IMAP4 monitor resource properties with the WebManager

- 1. Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click an IMAP4 monitor resources object, in the tree view. The following information is displayed in the list view.

IMAP4 Monitor Name: imap4w1	Details
Properties	Value
Name	imap4w1
Comment	
IP Address	127.0.0.1
Port	143
Authentication Method	AUTHENTICATE LOGIN
Status	Normal
Resource Status on Each Server	
Server Name	Status
server1	Online
server2	Offline

Name: IMAP monitor resource name

Comment: Comment of the IMAP monitor resource IP Address: IP address of the IMAP server to be monitored Port No.: Port number of the IMAP to be monitored Certification Method Authentication method to connect to IMAP4.

Status: Status of the IMAP monitor resource

Server Name: Server name

Status: Status of the monitor resource on the given server

### If you click the **Details** button, the following information is displayed in the pop-up dialogue.

Properties	Value
Type	imap4w
Monitor Timing	Activating
Target Resource	imap4
Interval	30
Timeout	60
Retry Count	3
Final Action	Stop the cluster service and shutdown OS
Execute Script before Final Action	Off
Recovery Target	failover1
Recovery Target Type	Group
Reactivation Threshold	0
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Wait Time to Start Monitoring	0

Type: Monitor resource type
Monitor Timing: Timing to start monitoring
Resource: Resource to be monitored

Interval: Interval between monitoring (in seconds)

Time to elapse from detection of an error to establish the error

as error (in seconds).

Retry Count: The number of retries to be made from detection of an error

in the monitor target to establish the error as error

Final Action: Final action at detection of an error

Execute Script before Final Action:

Whether or not script is executed when a failure is detected

Recovery Target: Target to be recovered when an error is detected

Recovery Target Type: Type of target to be recovered when an error is detected Reactivation Threshold: The number of reactivations to be made at detection of an

error

Failover Target Server: Determination method of failover destination

ExpressCluster X 2.1 for Windows Reference Guide

Failover Threshold: Wait Time to Start Monitoring:

The number of failovers to be made at detection of an error Time to wait before starting of monitoring (in seconds)

# **Understanding ODBC monitor resources**

ODBC monitor resources monitor ODBC database that runs on the server.

### **ODBC** monitor resources

- **Note 1** Set the data source using the ODBC data source administrator on Windows because the ODBC driver is used for monitoring. Add the data source to the system data source.
- **Note 2** For monitoring target resources, specify service resources or script resources that start the database. Monitoring starts after target resource is activated. However, if the database cannot be started immediately after target resource is activated, adjust the time using **Wait Time to Start Monitoring**.
- **Note 3** A monitor table is created when monitoring is started and it is deleted when monitoring is stopped due to the stop of the failover group. When monitoring is temporarily stopped or when server fails before the failover group stops due to system error, the monitor table will not be deleted. It is not an error even if an alert message saying that "a monitor table exists" is displayed next time when monitoring is started.
- Note 4 ODBC database may produce operation logs for each monitoring. Configure the database settings if this needs to be adjusted.

### Monitoring by ODBC monitor resources

A monitor table is created in the database. Maximum of 10 digits numeric data is read and written by issuing SQL statements. As a result of monitoring, the following is considered as an error:

- (1) When connection to the database fails.
- (2) When an error is notified as a response to the issue of SQL statement.
- (3) When the written data and read data do not match.

The SQL statement to use is: create/drop/insert/update/select.

## Displaying and changing the ODBC monitor resource details

- 1. Click **Monitors** on the tree view displayed on the left side of the Builder window.
- List of the monitor resources is displayed in the table view on the right side of the screen.
   Right click the target ODBC monitor resource, and click the **Parameter** tab in the **Monitor Resource Property** window.
- 3. On the **Parameter** tab, you can display and/or change the detailed settings by following the description below.



Data Source Name Within 255 bytes SuspendResume

Specify the data source name to be monitored. You must specify the name.

Default value: None

User Name Within 255 bytes SuspendResume

Specify the user name to log on to the database. You do not have to specify if the user name is specified in the data source settings.

Default value: None

Password Within 255 bytes SuspendResume

Specify the password to log on to the database. Click **Change** and enter the password in the dialog box.

Monitor Table Name Within 255 bytes SuspendResume


Specify the name of a monitor table created on the database. You must specify the name. Make sure not to specify the same name as the table used for operation because a monitor table will be created and deleted. Be sure to set the name different from the reserved word in SQL statements.

Default value: ODBCWATCH

# Displaying the ODBC monitor resource properties with the WebManager

1. Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).

information is displayed in the list view.



ODBC Monitor Name: odbcw1	Details
Properties	Value
Name	odbcw1
Comment	
Data Source Name	Sample
Monitor Table	ODBCWATCH
Status	Normal

Resource Status on Each Server	
Server Name	Status
server1	Online
server2	Offline

Name: ODBC monitor resource name

Comment: Comment of the ODBC monitor resource

Data Source Name: Data source name to be monitored

Table name for monitoring Monitor Table Name:

Status of the ODBC monitor resource Status:

Server Name: Server name

Status: Status of the monitor resource on the given server

### If you click the **Details** button, the following information is displayed in the pop-up dialogue.

Properties	Value
Type	odbcw
Monitor Timing	Activating
Target Resource	odbc
Interval	60
Timeout	120
Retry Count	2
Final Action	Stop the cluster service and shutdown OS
Execute Script before Final Action	Off
Recovery Target	failover1
Recovery Target Type	Group
Reactivation Threshold	0
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Wait Time to Start Monitoring	0

Type: Monitor resource type Monitor Timing: Timing to start monitoring Target Resource: Resource to be monitored

Interval: Interval between monitoring (in seconds)

Timeout: Time to elapse from detection of an error to establish the error

as error (in seconds).

Retry Count: The number of retries to be made from detection of an error

in the monitor target to establish the error as error

Final Action: Final action at detection of an error

Execute Script before Final Action:

Whether or not script is executed when a failure is detected

Recovery Target: Target to be recovered when an error is detected

Recovery Target Type: Type of target to be recovered when an error is detected

ExpressCluster X 2.1 for Windows Reference Guide

Reactivation Threshold: The number of reactivations to be made at detection of an

error

Failover Target Server: Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an error

Wait Time to Start Monitoring: Time to wait before starting of monitoring (in seconds)

# **Understanding Oracle monitor resources**

Oracle monitor resources monitor Oracle database that runs on the server.

### **Oracle monitor resources**

- **Note 1** For the supported Oracle versions, refer to the *Getting Started Guide*.
- Note 2 Interface DLL (OCI.DLL) needs to be installed on the server where monitoring is performed because Oracle OCI is used for monitoring. For target a monitoring resource, specify a service resource or a script resource that can start Oracle. Monitoring starts after the target resource is activated; however, if the database cannot be started right after the target resource is activated, adjust the time by using Wait Time to Start Monitoring.
- Note 3 A monitor table is created when monitoring is started and it is deleted when monitoring is stopped due to the stop of the failover group. When monitoring is temporarily stopped or when the server fails before the failover group stops due to system error, the monitor table will not be deleted. It is not an error even if an alert message saying that "a monitor table exists" is displayed next time when monitoring is started.
- **Note 4** Oracle database may produce operation logs for each monitoring. Configure the Oracle settings if this needs to be adjusted.

### Monitoring by Oracle monitor resources


A monitor table is created on the database. Maximum of 10-digits numeric data is read and written by issuing SQL statements. As a result of monitoring, the following is considered as an error:

- (1) When connection to the database fails.
- (2) When an error is notified as a response to the issue of SQL statement.
- (3) When the written data and read data do not match.

The SQL statement to use is: create/drop/insert/update/select.

## Displaying and changing the Oracle monitor resource details

- 1. Click **Monitors** on the tree view displayed on the left side of the Builder window.
- List of the monitor resources is displayed in the table view on the right side of the screen. Right click the target Oracle monitor resource, and click the **Parameter** tab in the **Monitor Resource Property** window.
- 3. On the **Parameter** tab, you can display and/or change the detailed settings by following the description below.



### Monitor Type SuspendResume

Select the Oracle features to be monitored.

Monitor Listener and Instance (default)

Performance of connection process to database and to refer to/update database are monitored.

Monitor Listener only

Only performance of connection process to database is monitored. Select this option when you try to recover by restarting the Listener service upon connection error.

. Monitor Instance only

Only performance of process to refer to/update database is monitored. If an error occurs on the connection process database, the error is ignored. Select this option to configure recovery operation for the errors except for connection process in conjunction with Oracle monitor resource in **Monitor Listener only**.

### Connect String Within 255 bytes SuspendResume

Specify the connect string for the database to be monitored. You must specify the connect string.

Default value: None

### User Name Within 255 bytes SuspendResume

Specify the user name to log on to the database.

Default value: sys

#### Password Within 255 bytes SuspendResume

Specify the password to log on to the database. Click **Change** and enter the password in the dialog box.

Default value: None

Section II Resource details

### OS Authentication SuspendResume

Specify the authentication method to log on to the Oracle monitor. It must follow the Oracle monitor settings.

· When selected:

Use OS authentication.

• When cleared (default value):

Use database authentication.

### Authentication Method SuspendResume

Select the user authority to log on to the Oracle monitor. This must be set according to the authority of the specified user name.

• SYSDBA (Default value)

Connect with SYSDBA authority.

DEFAULT

Connect with general user authority.

### Monitor Table Name Within 255 bytes SuspendResume

Specify the name of a monitor table created on the database. You must specify the name. Make sure not to specify the same name as the table used for operation because a monitor table will be created and deleted. Be sure to set the name different from the reserved word in SQL statements.

Default value: ORAWATCH

### Character Set SuspendResume

Select the character set for Oracle. When the language for Oracle is not Japanese or English, select AMERICAN\_AMERICA.US7ASCII.

◆ (Following the setting of the application) (default)

The Oracle character set installed in the server is used.

♦ AMERICAN AMERICA.US7ASCII

Connect with general user authority.

# Displaying the Oracle monitor resource properties with the WebManager

- 1. Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click the Oracle monitor resources object, , in the tree view. The following information is displayed in the list view.

Oracle monitor Name: oraclew1	Details	
Properties	Value	
Name	oraclew1	
Comment		
Connect String	Sample	
OS authentication	Off	
Authentication Method	SYSDBA	
Monitor Table	ORAWATCH	
Status	Normal	
Resource Status on Each Server		
Server Name	Status	
server1	Online	
server2	Offline	

Name: Oracle monitor resource name

Comment: Comment of the Oracle monitor resource
Connect String: Connect string for the database to be monitored

OS Authentication: Method used to connect to the database to be monitored Authentication Method: Authentication method for the connection to the database to be

monitored

Monitor Table Name: Table name for monitoring

Status: Status of the Oracle monitor resource

Server Name: Server name

Status: Status of the monitor resource on the given server

#### If you click the **Details** button, the following information is displayed in the pop-up dialogue.

Properties	Value
Type	oraclew
Monitor Timing	Activating
Target Resource	appli
Interval	60
Timeout	120
Retry Count	2
Final Action	Stop the cluster service and shutdown OS
Execute Script before Final Action	Off
Recovery Target	failover1
Recovery Target Type	Group
Reactivation Threshold	0
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Wait Time to Start Monitoring	0
Character Set	(Following the setting of the application)
Monitor Method	Listener and Instance Monitor

Type: Monitor resource type
Monitor Timing: Timing to start monitoring
Resource to be monitored

Interval: Interval between monitoring (in seconds)

Timeout: Time to elapse from detection of an error to establish the error

as error (in seconds).

Retry Count: The number of retries to be made from detection of an error

in the monitor target to establish the error as error

Final Action: Final action at detection of an error

Section II Resource details

Execute Script before Final Action:

Whether or not script is executed when a failure is detected

Recovery Target: Target to be recovered when an error is detected

Recovery Target Type: Type of target to be recovered when an error is detected Reactivation Threshold: The number of reactivations to be made at detection of an

error

Failover Target Server: The server to be the failover target at detection of an error Failover Threshold: The number of failovers to be made at detection of an error Wait Time to Start Monitoring: Time to wait before starting of monitoring (in seconds)

Character Set Character set for Oracle

Monitor Method The Oracle features to be monitored.

# **Understanding OracleAS monitor resources**

OracleAS monitor resource monitors Oracle application server that operates on servers.

### **Note on OracleAS monitor resources**

For the supported versions of Oracle application server, see the *Getting Started Guide*.

For monitor target resources, specify service resources or script resources etc. that starts up OracleAS. After the target resource is activated, monitoring is started. When OracleAS cannot start running immediately after the target resource is activated, adjust the time in **Wait Time to Start Monitoring**.

If there is any component which does not start in OracleAS instance when monitor target resources are activated, edit opmn.xml file to change the status of the component to "disabled". For details on opmn.xml file, refer to OracleAS manual.

OracleAS may report operation log etc. for every monitoring operation, which should be controlled by the OracleAS settings.

### How OracleAS monitor resources perform monitoring


OracleAS monitor resource monitors the following:

It uses the OracleAS opmnctl command to monitor the application server.

If an error is detected in the application server status acquired, it is regarded as an error:

## Displaying and changing the OracleAS monitor resource details

- Click the Monitors icon on the tree view displayed on the left side of the Builder window.
- **2.** List of the monitor resources is displayed in the table view on the right side of the screen. Right-click the target OracleAS monitor resource, and click the **Parameter** tab in the **Properties** window.
- **3.** On the **Parameter** tab, you can see and/or change the detailed settings by following the description below.



### **Instance Name** (Within 255bytes)

Specify the instance to be monitored. You must specify the instance.

Default value: None

### Install Path (Within 1023 bytes)

Specify the Oracle application install path. You must specify the path.

Default value: C:\product\10.1.3.2\companionCDHome 1

### Monitor Type SuspendResume

Select the OracleAS features to be monitored.

opmn process and component monitor

Both opmn process activation/deactivation monitoring and component status monitoring are performed.

opmn process monitor

Only opmn process activation/deactivation monitoring is performed.

component monitor

Only component status monitoring is performed.

#### Component Monitor SuspendResume

Select whether you specify monitor target component individually when **opmn process and component monitor** or **component monitor** is selected as Monitor Type.

All (default)

All components are monitored.

**Individual** 

Only the component specified in Component List.

Component List (Within 1023 byte) SuspendResume

Enter a target component name of **component monitor**. If you want to specify two or more components, separate them by comma ",". Make sure to set this when **Individual** is selected in **Component Monitor**.

# Displaying and changing the OracleAS monitor resource properties with the WebManager

- **1.** Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. When you click an object for Oracle monitor resource in the tree view, the following information is displayed in the list view.

OracleAS Monitor Name: ora	acleasw Details
Properties	Value
Name	oracleasw
Comment	
Instance	Sample
Status	Normal
Resource Status on Each S	erver
Server Name	Status
Server Name	
Server Name server1	Status
Server Name server1 server2	Status Online
Server Name server1 server2 Name	Status Online Offline
Server Name server1 server2 Name Comment	Online Offline OracleAS monitor resource name
	Online Offline OracleAS monitor resource name OracleAS monitor resource comment
Server Name server1 server2 Name Comment Instance	Online Offline OracleAS monitor resource name OracleAS monitor resource comment Name of the instance to be monitored

If you click the **Details** button, the following information is displayed in the pop-up dialog.

Properties	Value
Type	oracleasw
Monitor Timing	Activating
Target Resource	appli
Interval	60
Timeout	120
Retry Count	1
Final Action	Stop the cluster service and shutdown OS
Execute Script before Final Action	Off
Recovery Target	failover1
Recovery Target Type	Group
Reactivation Threshold	0
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Wait Time to Start Monitoring	0
Install Path	C:\product\10.1.3.2\companionCDHome_1
Component List	
Monitor Method	component monitor

Type Monitor resource type **Monitor Timing** Timing to start monitoring Target Resource Resource to be monitored Interval (sec) Interval between monitoring

Timeout (sec) Time to elapse from detection of an error to establish

Retry Count The number of retries to be made from detection of an error in

the monitor target to establish the error as an error

Final action at detection of an error Final Action

Execute Script before Final Action:

Whether or not script is executed when a failure is detected

Target to be recovered when an error is detected

Recovery Target Recovery Target Type Type of target to be recovered when an error is detected Reactivation Threshold The number of reactivations to be made at detection of an

Failover Target Server The server to be the failover target at detection of an error Failover Threshold The number of failovers to be made at detection of an error Wait Time to Start Monitoring (sec): Time to wait before starting monitoring (in seconds)

Install Path Install path of OracleAS

Component List A target component name of component monitor.

Monitor Method The OracleAS features to be monitored.

## Understanding OfficeScan CL monitor resource

OfficeScan CL monitor resource is a monitor resource that monitors OfficeScan Client operating on servers.

### Notes on OfficeScan CL monitor resource

Refer to Startup Guide for the operation checked OfficeScan versions.

If OfficeScan CL monitor detects issues, this monitor restarts OfficeScan NT Listener service as described below. Then, OfficeScan CL monitor may detect timeout error if it takes long time to restart the service. Please set sufficient timeout (default: 120 sec) for this monitor resource.

### How OfficeScan CL monitor resource performs monitoring

OfficeScan CL monitor resource monitors the following issues.

- ♦ Monitors whether or not OfficeScan NT Listener service is active.
- ♦ Monitors the connection status between OfficeScan Client and Server.

If OfficeScan CL monitor detects errors about above issues, this monitor restarts OfficeScan NT Listener service to solve them. If it failed to solve errors, error message will be appeared on WebManager.

In addition, this monitor restarts OfficeScan NT Listener service to refresh the firewall of OfficeScan Client when floating IP and virtual IP resource are activated. Then, it will be possible to access the server via floating IP and virtual IP address.

## Displaying and changing OfficeScan CL monitor resource details

There is no detail configuration in OfficeScan CL monitor resource.

# Displaying OfficeScan CL monitor resource properties with Web Manager

- **1.** Start up Web Manager. (http://FIP address:portnumber of *Web manager group*(default is 29003)).
- 2. In the tree view, click OfficeScan CL monitor resource object. The following contents are displayed in the list view.

Value

Name	oscw
Comment	
Status	Normal
Name	OfficeScan CL monitor resource name
Comment	OfficeScan CL monitor resource comment
Status	OfficeScan CL monitor resource status

Properties

Resource Status on Each Server	
Server Name Status	
server1	Online
server2	Offline

Server name Server name

Status: Status of monitor resource on each server

Furthermore, if you click the **Details** button, the following information is displayed in the pop-up dialogue.

Properties	Value
Type	oscw
Monitor Timing	Always
Target Resource	
Interval	60
Timeout	120
Retry Count	1
Final Action	No Operation
Execute Script before Final Action	Off
Recovery Target	cluster
Recovery Target Type	Itself
Reactivation Threshold	0
Failover Target Server	Stable Server
Failover Threshold	0
Wait Time to Start Monitoring	0

Type: Monitor resource type

Monitor Timing: Timing to start monitor resource
Target Resource: Resource to be monitored

Interval: Interval between monitoring (Seconds)

Timeout: Timeout period to judge the target monitor resource as an

error after detecting the error(Seconds).

Retry Count: The number of retry to judge the target monitor resource as an

error after detecting the error.

Final Action: Final action at error detection

Execute Script before Final Action:

Whether or not to execute the scripts at failure detection
Recovery Target:
Recovery Target Type:
Reactivation Threshold:
The number of reactivation to be made at error detection
Threshold:
The number of failover Destination Server
The number of failover to be made at error detection
The number of failover to be made at error detection
Time to wait before starting of monitoring (Seconds)

# **Understanding OfficeScan SV monitor resource**

OfficeScan SV monitor resource is a monitor resource that monitors OfficeScan Server operating on servers.

### Notes on OfficeScan SV monitor resource

Properties

Refer to **Startup Guide** for the operation checked OfficeScan versions.

### How OfficeScan SV monitor resource perform monitoring

OfficeScan SV monitor resource monitors following issues.

♦ Stall monitoring of virus checking pattern distribution function.

### Displaying and changing OfficeScan SV monitor resource details

There is no detail configuration in OfficeScan SV monitor resource.

# Displaying OfficeScan SV monitor resource properties with Web Manager

- **1.** Start up Web Manager (http://FIP address:portnumber of *Web manager group*(default is 29003)).
- 2. In the tree view, click OfficeScan CL monitor resource object. The following contents is displayed in the list view.

Value

Name	ossw
Comment	
Status	Normal
Name	OfficeScan SV monitor resource name
Comment	OfficeScan SV monitor resource comment
Status	OfficeScan SV monitor resource status

Resource Status on Each S	erver
Server Name	Status
server1	Online
server2	Offline
Server name	Server name
Status:	Status of monitor resource on each ser

Furthermore, if you click the **Details** button, the following information is displayed in the pop-up dialogue.

Properties	Value
Type	ossw
Monitor Timing	Activating
Target Resource	service_MasterService
Interval	30
Timeout	60
Retry Count	3
Final Action	Stop the cluster service and shutdown OS
Execute Script before Final Action	Off
Recovery Target	failover
Recovery Target Type	Group
Reactivation Threshold	0
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Wait Time to Start Monitoring	0

Type: Monitor resource type Monitor Timing: Timing to start monitoring Target Resource: Resource to be monitored

Interval: Interval between monitoring (Seconds)

Timeout: Timeout period to judge the target monitor resource as an

error after detecting the error(Seconds).

Retry Count: The number of retry to judge the target monitor resource as an

error after detecting the error.

Final Action: Final action at detection of an error

Execute Script before Final Action:

Whether or not script is executed when a failure is detected

Recovery Target: Target to be recovered when an error is detected

Recovery Target Type: Type of target to be recovered when an error is detected Reactivation Threshold: The number of reactivation to be made at detection of an error

Determination method of Failover Destination Server Failover Destination Server: Failover Threshold: The number of failover to be made at detection of an error Time to wait before starting of monitoring (in seconds)

# **Understanding POP3 monitor resources**

POP3 monitor resources monitor POP3 services that run on the server. POP3 monitor resources monitor POP3 protocol but they are not intended for monitoring specific applications. POP3 monitor resources monitor various applications that use POP3 protocol.

### **POP3** monitor resources

- Note 1 For monitoring target resources, specify service resources or script resources that start POP3 services. Monitoring starts after target resource is activated. However, if POP3 services cannot be started immediately after target resource is activated, adjust the time using Wait Time to Start Monitoring.
- **Note 2** POP3 services may produce operation logs for each monitoring. Configure the POP3 settings if this needs to be adjusted.


### Monitoring by POP3 monitor resources

POP3 monitor resources connect to the POP3 server and execute the command to verify the operation. As a result of monitoring, the following is considered as an error:

- (1) When connection to the POP3 server fails.
- (2) When an error is notified as a response to the command.

## Displaying and changing the POP3 monitor resource details

- 1. Click **Monitors** on the tree view displayed on the left side of the Builder window.
- 2. List of the monitor resources is displayed in the table view on the right side of the screen. Right click the target POP3 monitor resource, and click the **Parameter** tab in the **Monitor Resource Property** window.
- 3. On the **Parameter** tab, you can display and/or change the detailed settings by following the description below.



### IP Address (Within 255 bytes) SuspendResume

Specify the IP address of the POP3 server to be monitored. You must specify this IP address. If it is multi-directional standby server, specify FIP.

Default value: 127.0.0.1

#### **Port Number** (1 – 65535) SuspendResume

Specify the POP3 port number to be monitored. You must specify this port number.

Default value: 110

#### User Name Within 255 bytes SuspendResume

Specify the user name to log on to POP3.

Default value: None

### Password Within 255 bytes SuspendResume

Specify the password to log on to POP3. Click **Change** and enter the password in the dialog box.

Default value: None

#### Authentication Method SuspendResume

Select the authentication method to log on to POP3. It must follow the settings of POP3 being used:

APOP (Default value)

The encryption authentication method that uses the APOP command.

USER/PASS

The plaintext method that uses the USER/PASS command.

# Displaying the POP3 monitor resource properties with the WebManager

- 1. Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click the POP3 monitor resources object, , in the tree view. The following information is displayed in the list view.

POP3 Monitor Name: pop3w1	Details	
Properties	Value	
Name	pop3w1	
Comment		
IP Address	127.0.0.1	
Port	110	
Authentication Method	APOP	
Status	Normal	
Resource Status on Each Server		
Server Name	Status	
server1	Online	
server2	Offline	

Name: POP3 monitor resource name

Comment: Comment of the POP3 monitor resource
IP Address: IP address of the POP3 server to be monitored
Port No.: Port number of the POP3 to be monitored
Authentication Method: Authentication method to connect to POP3
Status: Status of the POP3 monitor resource

Server Name: Server name

Status: Status of the monitor resource on the given server

### If you click the **Details** button, the following information is displayed in the pop-up dialogue.

,	
Properties	Value
Туре	pop3w
Monitor Timing	Activating
Target Resource	рор3
Interval	30
Timeout	60
Retry Count	3
Final Action	Stop the cluster service and shutdown OS
Execute Script before Final Action	Off
Recovery Target	failover1
Recovery Target Type	Group
Reactivation Threshold	0
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Wait Time to Start Monitoring	0

Type: Monitor resource type
Monitor Timing: Timing to start monitoring
Resource to be monitored

Interval: Interval between monitoring (in seconds)

### Chapter 7 Monitor resource details

Time to elapse from detection of an error to establish the error

as error (in seconds).

Retry Count: The number of retries to be made from detection of an error

in the monitor target to establish the error as error

Final Action: Final action at detection of an error

Execute Script before Final Action:

Whether or not script is executed when a failure is detected

Recovery Target: Target to be recovered when an error is detected

Recovery Target Type: Type of target to be recovered when an error is detected Reactivation Threshold: The number of reactivations to be made at detection of an

error

Failover Target Server: Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an error Wait Time to Start Monitoring: Time to wait before starting of monitoring (in seconds)

# **Understanding PostgreSQL monitor resources**

PostgreSQL monitor resources monitor PostgreSQL database that runs on the server.

### PostgreSQL monitor resources

- **Note 1** For information on the supported PostgreSQL/PowerGres versions, refer to the *Getting Started Guide*.
- **Note 2** Interface DLL (LIBPQ.DLL) needs to be installed on the server where monitoring is performed because PostgreSQL/PowerGres library is used for monitoring. Specify the path of this DLL to the environmental variable when monitoring PostgreSQL.
- Note 3 For a target monitoring resource, specify a service resource that can start PostgreSQL/PowerGres. Monitoring starts after the target resource is activated; however, if the database cannot be started right after the target resource is activated, adjust the time by using Wait Time to Start Monitoring.
- Note 4 A monitor table is created when monitoring is started and it is deleted when monitoring is stopped due to the stop of the failover group. When monitoring is temporarily stopped or when server fails before the failover group stops due to system error, the monitor table will not be deleted. It is not an error if an alert message saying that "a monitor table exists" is displayed next time when monitoring is started.
- **Note 5** PostgreSQL/PowerGres may produce operation logs for each monitoring. Configure the PostgreSQL/PowerGres settings if this needs to be adjusted.
- **Note 6** Because PostgreSQL is open-source software (OSS), its operation is checked but not guaranteed. Make sure to use PostgreSQL after evaluating it by yourself.

## Monitoring by PostgreSQL monitor resources


A monitor table is created on the database. Maximum of 10-digits numeric data is read and written by issuing SQL statements. As a result of monitoring, the following is considered as an error:

- (1) When connection to the database fails.
- (2) When an error is notified as a response to the issue of SQL statement.
- (3) When the written data and read data do not match.

The SQL statement to use is: create/drop/insert/update/select.

## Displaying and changing the PostgreSQL monitor resource details

- 1. Click **Monitors** on the tree view displayed on the left side of the Builder window.
- 2. List of the monitor resources is displayed in the table view on the right side of the screen. Right click the target PostgreSQL monitor resource, and click the **Parameter** tab in the **Monitor Resource Property** window.
- 3. On the **Parameter** tab, you can display and/or change the detailed settings by following the description below.



Database Name Within 255 bytes SuspendResume

Specify the database name to be monitored. You must specify the name.

Default value: None

#### IP Address SuspendResume

Specify the IP address of the database server to be monitored. You must specify this IP address.

Default value: 127.0.0.1

#### Port No. SuspendResume

Specify the PostgreSQL port number to be monitored. You must specify this port number.

Default value: 5432

#### User Name Within 255 bytes SuspendResume

Specify the user name to log on to the database.

Default value: postgres

### Password Within 255 bytes SuspendResume

Specify the password to log on to the database. Click **Change** and enter the password in the dialog box.

Default value: None

### Monitor Table Name Within 255 bytes SuspendResume

You must specify the name of a monitor table created in the database. Make sure not to specify the same name as the table used for operation because a monitor table will be created and deleted. Be sure to set the name different from the reserved word in SQL statements.

Default value: PSQLWATCH

# Displaying the PostgreSQL monitor resource properties with the WebManager

- 1. Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click the PostgreSQL monitor resources object, in the tree view. The following information is displayed in the list view.

PostgreSQL Monitor Name:	psqlw1	Details
Properties		Value
Name	psqlw1	
Comment		
Database Name	Sample	
IP Address	127.0.0.1	
Port	5432	
Monitor Table	PSQLWATO	H
Status	Normal	
Resource Status on Each Se	erver	
Server Name		Status
server1	Online	
server2	Offline	

Name: PostgreSQL monitor resource name

Comment: Comment of the PostgreSQL monitor resource

Database name: Database name to be monitored

IP Address: IP address of the PostgreSQL server to be monitored Port No.: Port number of the PostgreSQL to be monitored

Monitor Table Name: Table name for monitoring

Status: Status of the PostgreSQL monitor resource

Server Name: Server name

Status: Status of the monitor resource on the given server

If you click the **Details** button, the following information is displayed in the pop-up dialogue.

Properties	Value
Туре	psqlw
Monitor Timing	Activating
Target Resource	psql
Interval	60
Timeout	120
Retry Count	2
Final Action	Stop the cluster service and shutdown OS
Execute Script before Final Action	Off
Recovery Target	failover1
Recovery Target Type	Group
Reactivation Threshold	0
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Wait Time to Start Monitoring	0

Type: Monitor resource type Monitor Timing: Timing to start monitoring Target Resource: Resource to be monitored

Interval between monitoring (in seconds) Interval:

Timeout: Time to elapse from detection of an error to establish the error

as error (in seconds).

Retry Count: The number of retries to be made from detection of an error

in the monitor target to establish the error as error

Final action at detection of an error Final Action:

Execute Script before Final Action:

Whether or not script is executed when a failure is detected

Recovery Target: Target to be recovered when an error is detected

Recovery Target Type: Type of target to be recovered when an error is detected Reactivation Threshold:

The number of reactivations to be made at detection of an

error

Failover Target Server: Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an error Wait Time to Start Monitoring: Time to wait before starting of monitoring (in seconds)

# **Understanding SMTP monitor resources**

SMTP monitor resources monitor SMTP services that run on the server. SMTP monitor resources monitor SMTP protocol but hey are not intended for monitoring specific applications. SMTP monitor resources monitor various applications that use SMTP protocol.

### **SMTP** monitor resources

- Note 1 For monitoring target resources, specify service resources or script resources that start SMTP. Monitoring starts after target resource is activated. However, if the database cannot be started immediately after target resource is activated, adjust the time using Wait Time to Start Monitoring.
- **Note 2** SMTP services may produce operation logs for each monitoring. Configure the SMTP settings if this needs to be adjusted.


## Monitoring by SMTP monitor resources

POP3 monitor resources connect to the POP3 server and execute the command to verify the operation. As a result of monitoring, the following is considered as an error:

- (1) When connection to the SMTP server fails.
- (2) When an error is notified as a response to the command.

## Displaying and changing the SMTP monitor resource details

- 1. Click **Monitors** on the tree view displayed on the left side of the Builder window.
- 2. List of the monitor resources is displayed in the table view on the right side of the screen. Right click the target SMTP monitor resource, and click the **Parameter** tab in the **Monitor Resource Property** window.
- 3. On the **Parameter** tab, you can display and/or change the detailed settings by following the description below.



### IP Address SuspendResume

You must specify the IP address of the SMTP server to be monitored. Default value: 127.0.0.1

### Port No. SuspendResume

Specify the port number of the SMTP to be monitored. You must specify this port number.

Default value: 25

#### User Name Within 255 bytes SuspendResume

Specify the user name to log on to SMTP. If no user name is specified, SMTP authentication is not performed.

Default value: None

### Password Within 255 bytes SuspendResume

Specify the password to log on to SMTP. Click **Change** and enter the password in the dialog box.

Default value: None

#### Authentication Method SuspendResume

Select the authentication method to log on to the SMTP. It must follow the settings of SMTP being used:

• CRAM-MD5 (Default value)

The encryption authentication method that uses the CRAM-MD5 command.

LOGIN

The plaintext method that uses the LOGIN command.

E-mail Address Within 255 bytes SuspendResume

Specify the email address used for monitoring. If nothing is specified, monitoring is performed using the command to verify the operation. The command that uses a dummy e-mail address is executed internally. If an email address is specified, monitoring is performed by actually sending e-mails to the specified e-mail address. It is recommended to have an e-mail address dedicated to monitoring.

Default value: None

# Displaying the SMTP monitor resource properties with the WebManager

- 1. Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click the SMTP monitor resources object, , in the tree view. The following information is displayed in the list view.

SMTP Monitor Name: smtpw	1 Details
Properties	Value
Name	smtpw1
Comment	
IP Address	127.0.0.1
Port	25
Authentication Method	CRAM-MD5
Mail Address	
Status	Normal
Resource Status on Each Se	rver
Server Name	Status
server1	Online
server2	Offline

Name: SMTP monitor resource name

Comment: Comment of the SMTP monitor resource
IP Address: IP address of the SMTP server to be monitored
Port No.: Port number of the SMTP to be monitored

Authentication Method: Authentication method to connect to SMTP (If user name for SMTP

authentication is not set, what is displayed here is not effective)

E-mail Address: E-mail address for monitoring

Status: Status of the SMTP monitor resource

Server Name: Server name

Status: Status of the monitor resource on the given server

If you click the **Details** button, the following information is displayed in the pop-up dialogue.

Properties	Value
Туре	smtpw
Monitor Timing	Activating
Target Resource	smtp
Interval	30
Timeout	60
Retry Count	3
Final Action	Stop the cluster service and shutdown OS
Execute Script before Final Action	Off
Recovery Target	failover1
Recovery Target Type	Group
Reactivation Threshold	0
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Wait Time to Start Monitoring	0

Type: Monitor resource type
Monitor Timing: Timing to start monitoring
Resource to be monitored

Interval: Interval between monitoring (in seconds)

Timeout: Time to elapse from detection of an error to establish the error

as error (in seconds).

Retry Count: The number of retries to be made from detection of an error

in the monitor target to establish the error as error

Final Action: Final action at detection of an error

Execute Script before Final Action:

Whether or not script is executed when a failure is detected

Recovery Target: Target to be recovered when an error is detected
Recovery Target Type: Type of target to be recovered when an error is detected

Reactivation Threshold: The number of reactivations to be made at detection of an

error

Failover Target Server: Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an error Wait Time to Start Monitoring: Time to wait before starting of monitoring (in seconds)

## **Understanding SQL Server monitor resources**

SQL Server monitor resources monitor SQL Server database that runs on the server.

### **SQL Server monitor resources**

- **Note 1** For information on the supported SQL Server versions, refer to the *Getting Started Guide*.
- Note 2 For target monitoring resource, specify a service resource that can start SQL Server. Monitoring starts after the target resource is activated; however, if the database cannot be started right after the target resource is activated, adjust the time by using Wait Time to Start Monitoring.
- Note 3 A monitor table is created when monitoring is started and it is deleted when monitoring is stopped due to the stop of the failover group. When monitoring is temporarily stopped or when server fails before the failover group stops due to system error, the monitor table will not be deleted. It is not an error if an alert message saying that "a monitor table exists" is displayed next time when monitoring is started.
- **Note 4** SQL Server may produce operation logs for each monitoring. Configure the SQL Server settings if this needs to be adjusted.

### Monitoring by SQL Server monitor resources


A monitor table is created on the database. Maximum of 10-digits numeric data is read and written by issuing SQL statements. As a result of monitoring, the following is considered as an error:

- (1) When connection to the database fails.
- (2) When an error is notified as a response to the issue of SQL statement.
- (3) When the written data and read data do not match.

The SQL statement to use is: create/drop/insert/update/select.

## Displaying and changing the SQL Server monitor resource details

- 1. Click **Monitors** on the tree view displayed on the left side of the Builder window.
- 2. List of the monitor resources is displayed in the table view on the right side of the screen. Right click the target SQL Server monitor resource, and click the **Parameter** tab in the **Monitor Resource Property** window.
- 3. On the **Parameter** tab, you can display and/or change the detailed settings by following the description below.



Database Name Within 255 bytes SuspendResume

Specify the database name to be monitored. You must specify the name.

Default value: None

Instance Name Within 255 bytes SuspendResume

Specify the database instance name. You must specify the instance name.

Default value: MSSQLSERVER

User Name Within 255 bytes SuspendResume

Specify the user name to log on to the database. If the user name is not specified, Windows authentication is used.

Default value: SA

Password Within 255 bytes SuspendResume

Specify the password to log on to the database. Click **Change** and enter the password in the dialog box.

Default value: None

Monitor Table Name Within 255 bytes SuspendResume

Specify the name of a monitor table created on the database. You must specify the name. Make sure not to specify the same name as the table used for operation because a monitor table will be created and deleted. Be sure to set the name different from the reserved word in SQL statements.

Default value: SQLWATCH

ODBC Driver Name (Within 255 bytes) SuspendResume

Select the driver name of the target database shown in the **ODBC** tab when you click **Start** -> **Administrative Tools** -> **Data Sources (ODBC)**. Select **SQL Native Client** in SQL Server 2005. Select **SQL Server Native Client 10.0** in SQL Server 2008.

Default value: SQL Native Client

# Displaying the SQL Server monitor resource properties with the WebManager

- 1. Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click the SQL Server monitor resources object, , in the tree view. The following information is displayed in the list view.

SQL Server Monitor Name: sqlse	rverw1 Details	
Properties	Value	
Name	sqlserverw1	
Comment		
Database Name	Sample	
Instance	MSSQLSERVER	
Monitor Table	SQLWATCH	
Status	Normal	
Resource Status on Each Server		
Server Name	Status	
server1	Online	
server2	Offline	

Name: SQL Server monitor resource name

Comment: Comment of the SQL Server monitor resource

Database name: Database name to be monitored

Instance Name: Instance name of the database to be monitored

Monitor Table Name: Table name for monitoring

Status: Status of the SQL Server monitor resource

Server Name: Server name

Status: Status of the monitor resource on the given server

If you click the **Details** button, the following information is displayed in the pop-up dialogue.

Properties	Value	
Type	sqlserverw	
Monitor Timing	Activating	
Target Resource	appli	
Interval	60	
Timeout	120	
Retry Count	2	
Final Action	Stop the cluster service and shutdown OS	
Execute Script before Final Action	Off	
Recovery Target	failover1	
Recovery Target Type	Group	
Reactivation Threshold	0	
Failover Target Server	Stable Server	
Failover Threshold	Number of Servers	
Wait Time to Start Monitoring	0	
ODBC Driver Name	SQL Native Client	

Type: Monitor resource type
Monitor Timing: Timing to start monitoring
Resource to be monitored

Interval: Interval between monitoring (in seconds)

Timeout: Time to elapse from detection of an error to establish the error

as error (in seconds).

Retry Count: The number of retries to be made from detection of an error

in the monitor target to establish the error as error

Final Action: Final action at detection of an error

Execute Script before Final Action:

Whether or not script is executed when a failure is detected

Recovery Target: Target to be recovered when an error is detected

Recovery Target Type: Type of target to be recovered when an error is detected Reactivation Threshold: The number of reactivations to be made at detection of an

error

Failover Target Server: Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an error Wait Time to Start Monitoring: Time to wait before starting of monitoring (in seconds)

ODBC Driver Name: The driver name of the target database

# **Understanding Tuxedo monitor resources**

Tuxedo monitor resources monitor Tuxedo that runs on the server.

### **Tuxedo monitor resources**

- **Note 1** For the supported versions of Tuxedo application server, see the *Getting Started Guide*.
- Note 2 For target monitoring resource, specify a script resource that can start Tuxedo.

  Monitoring starts after the target resource is activated; however, if Tuxedo cannot be started right after the target resource is activated, adjust the time by using Wait Time to Start Monitoring.
- **Note 3** Tuxedo may produce operation logs for each monitoring. Configure the Tuxedo settings if this needs to be adjusted.


### Monitoring by Tuxedo monitor resources

Tuxedo monitor resources connect to the Tuxedo and execute API to verify the operation. As a result of monitoring, the following is considered as an error:

(1) When an error is reported during the connection to the application server and/or the acquisition of the status.

# Displaying and changing the Tuxedo monitor resource details

- 3. Click **Monitors** on the tree view displayed on the left side of the Builder window.
- 4. List of the monitor resources is displayed in the table view on the right side of the screen. Right click the target Tuxedo monitor resource, and click the **Parameter** tab in the **Monitor Resource Property** window.
- 5. On the **Parameter** tab, you can display and/or change the detailed settings by following the description below.



Application Server Name Within 255 bytes SuspendResume

Specify the application server name to be monitored. You must specify the name.

Default value: BBL

Config File Within 1023 bytes SuspendResume

Specify the placement file name of Tuxedo. You must specify the name.

Default value: None

# Displaying the Tuxedo monitor resource properties with the WebManager

- **1.** Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click the Tuxedo monitor resources object, , in the tree view. The following information is displayed in the list view.

Tuxedo Monitor Name: tuxw		Details
Properties	Value	
Name	tuxw	
Comment		
Application Server Name	BBL	
Status	Normal	
Resource Status on Each Se	erver	
Resource Status on Each Se Server Name	erver Status	;
		;

Name: Tuxedo monitor resource name

Comment: Comment of the Tuxedo monitor resource
Application Server Name: Application server name to be monitored
Status: Status of the Tuxedo monitor resource

Server Name: Server name

Status: Status of the monitor resource on the given server

If you click the **Details** button, the following information is displayed in the pop-up dialogue.

Properties	Value	
Type	tuxw	
Monitor Timing	Activating	
Target Resource	tuxedo	
Interval	60	
Timeout	120	
Retry Count	2	
Final Action	Stop the cluster service and shutdown OS	
Execute Script before Final Action	Off	
Recovery Target	failover1	
Recovery Target Type	Group	
Reactivation Threshold	0	
Failover Target Server	Stable Server	
Failover Threshold	Number of Servers	
Wait Time to Start Monitoring	0	
Config File	E:\tuxedo\tuxconfig	

Type: Monitor resource type
Monitor Timing: Timing to start monitoring
Resource to be monitored

Interval: Interval between monitoring (in seconds)

Timeout: Time to elapse from detection of an error to establish the error

as error (in seconds).

Retry Count: The number of retries to be made from detection of an error

in the monitor target to establish the error as error

Final Action: Final action at detection of an error

Execute Script before Final Action:

Whether or not script is executed when a failure is detected

Recovery Target: Target to be recovered when an error is detected

Recovery Target Type: Type of target to be recovered when an error is detected Reactivation Threshold: The number of reactivations to be made at detection of an

error

Failover Target Server: Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an error Wait Time to Start Monitoring: Time to wait before starting of monitoring (in seconds)

Config File: Configuration file path of Tuxedo

## **Understanding Websphere monitor resources**

Websphere monitor resources monitor WebSphere that runs on the server.

## Websphere monitor resources

- **Note 1** For the supported versions of WebSphere application server, see the *Getting Started Guide*.
- Note 2 For target monitoring resource, specify a service resource that can start WebSphere. Monitoring starts after the target resource is activated; however, if the database cannot be started right after the target resource is activated, adjust the time by using Wait Time to Start Monitoring.
- **Note 3** A Java Runtime Environment is required to start monitoring with this command. The application server system uses Java functions. Therefore if Java stalls, it may be recognized as an error.
- **Note 4** WebSphere may produce operation logs for each monitoring. Configure the Websphere settings if this needs to be adjusted.


### Monitoring by Websphere monitor resources

Websphere monitor resources use the serverStatus.bat command to verify the operation. As a result of monitoring, the following is considered as an error:

(1) When an error is reported with the state of the acquired application server.

# Displaying and changing the Websphere monitor resource details

- 1. Click **Monitors** on the tree view displayed on the left side of the Builder window.
- 2. List of the monitor resources is displayed in the table view on the right side of the screen. Right click the target Websphere monitor resource, and click the **Parameter** tab in the **Monitor Resource Property** window.
- 3. On the **Parameter** tab, you can display and/or change the detailed settings by following the description below.



**Application Server Name** Within 255 bytes SuspendResume

Specify the application server name to be monitored. You must specify the name.

Default value: server1

Profile Name Within 1023 bytes SuspendResume

Specify the profile name of WebSphere. You must specify the name.

Default value: default

User Name Within 255 bytes SuspendResume

Specify the user name of WebSphere. You must specify the name.

Default value: None

Password Within 255 bytes SuspendResume

Specify the password of WebSphere. You must specify the password.

Default value: None

Install Path Within 1023 bytes SuspendResume

Specify the installation path of WebSphere. You must specify the path.

 $Default\ value:\ C: \ Program\ Files \ IBM \ WebSphere \ AppServer$ 

# Displaying the Websphere monitor resource properties with the WebManager

- **1.** Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click the Websphere monitor resources object, , in the tree view. The following information is displayed in the list view.

Websphere Monitor Name: w	/asw	Details
Properties		Value
Name	wasw	
Comment		
Application Server Name	server1	
Status	Normal	
Danas was Otatus an Each Oa		
Resource Status on Each Se	rver	
Server Name		Status
server1	Online	
server2	Offline	

Name: Websphere monitor resource name

Comment: Comment of the Websphere monitor resource
Application Server Name: Application server name to be monitored
Status: Status of the Websphere monitor resource

Server Name: Server name

Status: Status of the monitor resource on the given server

#### If you click the **Details** button, the following information is displayed in the pop-up dialogue.

Properties	Value
Туре	wasw
Monitor Timing	Activating
Target Resource	websphere
Interval	60
Timeout	120
Retry Count	2
Final Action	Stop the cluster service and shutdown OS
Execute Script before Final Action	Off
Recovery Target	failover1
Recovery Target Type	Group
Reactivation Threshold	0
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Wait Time to Start Monitoring	0
Profile Name	default
Install Path	C:\Program Files\IBM\WebSphere\AppServer

Type: Monitor resource type
Monitor Timing: Timing to start monitoring
Resource to be monitored

Interval: Interval between monitoring (in seconds)

Timeout: Time to elapse from detection of an error to establish the error

as error (in seconds).

Retry Count: The number of retries to be made from detection of an error

in the monitor target to establish the error as error

Final Action: Final action at detection of an error

Execute Script before Final Action:

Recovery Target:

Whether or not script is executed when a failure is detected

Target to be recovered when an error is detected

Recovery Target Type: Type of target to be recovered when an error is detected Reactivation Threshold: The number of reactivations to be made at detection of an

error

Failover Target Server: Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an error Wait Time to Start Monitoring: Time to wait before starting of monitoring (in seconds)

Profile Name Profile name of WebSphere Install Path Install path of WebSphere

## **Understanding Weblogic monitor resources**

Weblogic monitor resources monitor WebLogic that runs on the server.

#### Weblogic monitor resources

- **Note 1** For the supported versions of WebLogic application server, see the *Getting Started Guide*.
- Note 2 For target monitoring resource, specify a script resource that can start Weblogic. Monitoring starts after the target resource is activated; however, if WebLogic cannot be started right after the target resource is activated, adjust the time by using Wait Time to Start Monitoring.
- **Note 3** A Java Runtime Environment is required to start monitoring with this command. The application server system uses Java functions. Therefore if Java stalls, it may be recognized as an error.
- **Note 4** WebLogic may produce operation logs for each monitoring. Configure the WebLogic settings if this needs to be adjusted.


#### Monitoring by Weblogic monitor resources

Weblogic monitor resources use the webLogic.Admin (Ping) command to verify the operation. As a result of monitoring, the following is considered as an error:

(1) When an error is reported as the response to the Ping.

# Displaying and changing the Weblogic monitor resource details

- 1. Click **Monitors** on the tree view displayed on the left side of the Builder window.
- List of the monitor resources is displayed in the table view on the right side of the screen.
   Right click the target Weblogic monitor resource, and click the **Parameter** tab in the **Monitor Resource Property** window.
- 3. On the **Parameter** tab, you can display and/or change the detailed settings by following the description below.



IP Address Within 80 bytes SuspendResume

Specify the IP address of the server to be monitored. You must specify the IP address.

Default value: 127.0.0.1

Port 1024 to 65535) SuspendResume

Specify the port number used to connect to the server. You must specify the number.

Default value: 7002

#### Account Shadow SuspendResume

When you specify a user name and a password directly, select **Off**. If not, select **On**. You must specify the setting.

Default value: Off

Config File Within 1023 bytes SuspendResume

Specify the file in which the user information is saved. You must specify the file if **Account Shadow** is **On**.

Default value: None

**Key File** Within 1023 bytes SuspendResume

Specify the file in which the password required to access to a config file path is saved. Specify the full path of the file. You must specify the file if **Account Shadow** is **On**.

Default value: None

User Name Within 255 bytes SuspendResume

Specify the user name of WebLogic. You must specify the file if **Account Shadow** is **Off**.

Default value: weblogic

Section II Resource details

Password Within 255 bytes SuspendResume

Specify the password of WebLogic.

Default value: weblogic

#### Authority Method SuspendResume

Specify the authentication method when connecting to an application server. You must specify the method.

Default value: DemoTrust

Key Store File Within 1023 bytes SuspendResume

Specify the authentication file when authenticating SSL. You must specify this when the authentication method is **CustomTrust**.

Default value: None

Install Path Within 1023 bytes SuspendResume

Specify the installation path of WebLogic. You must specify the path.

Default value: C:\bea\weblogic92

# Displaying the Weblogic monitor resource properties with the WebManager

- **1.** Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click the Weblogic monitor resources object, , in the tree view. The following information is displayed in the list view.

Weblogic Monitor Name: wlsw	Details
Properties	Value
Name	wisw
Comment	
IP Address	127.0.0.1
Port	7002
Status	Normal
Barrer State on Freih Sann	
Resource Status on Each Serve	er
Server Name	Status
server1	Online
server2	Offline

Name: Weblogic monitor resource name

Comment: Comment of the Weblogic monitor resource
IP Address: IP address of the Weblogic monitor resource
Port: Port number of the Weblogic monitor resource

Status: Status of the Weblogic monitor resource

Server Name: Server name

Status of the monitor resource on the given server Status:

#### If you click the **Details** button, the following information is displayed in the pop-up dialogue.

Properties	Value
Type	wisw
Monitor Timing	Activating
Target Resource	weblogic
Interval	60
Timeout	120
Retry Count	2
Final Action	Stop the cluster service and shutdown OS
Recovery Target	failover1
Execute Script before Final Action	Off
Recovery Target Type	Group
Reactivation Threshold	0
Failover Target Server	Stable Server
Failover Threshold	Number of Servers
Wait Time to Start Monitoring	0
Authority Method	DemoTrust
Install Path	C:\bea\weblogic92

Type: Monitor resource type Monitor Timing: Timing to start monitoring Target Resource: Resource to be monitored

Interval: Interval between monitoring (in seconds)

Timeout: Time to elapse from detection of an error to establish the error

as error (in seconds).

Retry Count: The number of retries to be made from detection of an error

in the monitor target to establish the error as error

Final action at detection of an error Final Action:

Execute Script before Final Action:

Whether or not script is executed when a failure is detected

Recovery Target: Target to be recovered when an error is detected

Recovery Target Type: Type of target to be recovered when an error is detected Reactivation Threshold: The number of reactivations to be made at detection of an

error

Failover Target Server: Determination method of Failover Target Server

Failover Threshold: The number of failovers to be made at detection of an error Wait Time to Start Monitoring: Time to wait before starting of monitoring (in seconds)

Authority Method Authority method of WebLogic

Install Path Install path of WebLogic

# **Understanding WebOTX monitor resources**

WebOTX monitor resources monitor WebOTX that runs on the server.

#### **WebOTX** monitor resources

- **Note 1** For the supported versions of WebOTX application server, see the *Getting Started Guide*.
- Note 2 For target monitoring resource, specify a script resource that can start WebOTX. Monitoring starts after the target resource is activated; however, if WebOTX cannot be started right after the target resource is activated, adjust the time by using Wait Time to Start Monitoring.
- **Note 3** A Java environment is required to start monitoring with this command. The application server system uses Java functions. Therefore if Java stalls, it may be recognized as an error.
- **Note 4** WebOTX may produce operation logs for each monitoring. Configure the WebOTX settings if this needs to be adjusted.


### Monitoring by WebOTX monitor resources

WebOTX monitor resources use the serverStatus.bat command to verify the operation. As a result of monitoring, the following is considered as an error:

(1) When an error is reported with the state of the acquired application server.

# Displaying and changing the WebOTX monitor resource details Websphere

- 1. Click **Monitors** on the tree view displayed on the left side of the Builder window.
- 2. List of the monitor resources is displayed in the table view on the right side of the screen. Right click the target Weblogic monitor resource, and click the **Parameter** tab in the **Monitor Resource Property** window.
- 3. On the **Parameter** tab, you can display and/or change the detailed settings by following the description below.



Connecting Destination Within 255 bytes SuspendResume

Specify the server name of the server to be monitored. You must specify the name.

Default value: localhost

Port Number 1024 to 65535) SuspendResume

Specify the port number used to connect to the server. You must specify the number.

Default value: 6212

User Name Within 255 bytes SuspendResume

Specify the user name of WebOTX. You must specify the name.

Default value: None

Password Within 255 bytes SuspendResume

Specify the password of WebOTX.

Default value: None

# Displaying the WebOTX monitor resource properties with the WebManager

- **1.** Start the WebManager (http://FIP\_address\_for\_the\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click the Weblogic monitor resources object, , in the tree view. The following information is displayed in the list view.

WebOTX Monitor Name: obv	w Details	
Properties	Value	
Name	otxw	
Comment		
Connecting Destination	localhost	
Port	6212	
Status	Normal	
D		
Resource Status on Each S	erver	
Server Name	Status	

Name: Weblogic monitor resource name

Comment: Comment of the Weblogic monitor resource

Connecting Destination: Server name for connecting of the WebOTX monitor resource

Port: Port number of the WebOTX monitor resource Status: Status of the WebOTX monitor resource

Server Name: Server name

Status: Status of the monitor resource on the given server

If you click the **Details** button, the following information is displayed in the pop-up dialogue.

Properties	Value	
Type	otxw	
Monitor Timing	Activating	
Target Resource	webotx	
Interval	60	
Timeout	120	
Retry Count	1	
Final Action	Stop the cluster service and shutdown OS	
Execute Script before Final Action	Off	
Recovery Target	failover1	
Recovery Target Type	Group	
Reactivation Threshold	0	
Failover Target Server	Stable Server	
Failover Threshold	Number of Servers	
Wait Time to Start Monitoring	0	

Type: Monitor resource type
Monitor Timing: Timing to start monitoring
Resource to be monitored

Interval: Interval between monitoring (in seconds)

Time to elapse from detection of an error to establish the error

as error (in seconds).

Retry Count: The number of retries to be made from detection of an error

in the monitor target to establish the error as error

Final Action: Final action at detection of an error

Execute Script before Final Action:

Recovery Target:

Whether or not script is executed when a failure is detected

Target to be recovered when an error is detected

Recovery Target Type: Type of target to be recovered when an error is detected Reactivation Threshold: The number of reactivations to be made at detection of an

error

Failover Threshold: The number of failovers to be made at detection of an error Wait Time to Start Monitoring: Time to wait before starting of monitoring (in seconds)

# **Chapter 8** Heartbeat resources

This chapter provides detailed information on heartbeat resources.


#### This chapter covers:

•	Heartbeat resources ····	· 7:	32
•	Understanding kernel mode LAN heartbeat resources ·····	. 72	33

## **Heartbeat resources**

Servers in a cluster monitor if other servers in the cluster are activated. For this monitoring, heartbeat resources are used.

Heartbeat device types are:



- (1) LAN heartbeat resource dedicated to interconnect (kernel mode)
- (2) Public LAN heartbeat (kernel mode)

Heartbeat resource name	Abbreviation	Functional overview
Kernel mode LAN heartbeat resource (1)(2)	lankhb	A kernel mode module uses a LAN to monitor if servers are activated.  Used for communication within the cluster as well.

♦ You need to set at least one LAN heartbeat resource. It is recommended to set two or more LAN heartbeat resources.

It is recommended to set both interconnect-dedicated LAN heartbeat resource and public LAN heartbeat resource together.

# Understanding kernel mode LAN heartbeat resources

#### Kernel mode LAN heartbeat resources


Kernel mode LAN heartbeat resources achieve heartbeat functions using the kernel mode driver module. Kernel mode LAN heartbeat resources are less burdened and help to reduce misidentification of disconnection of interconnect by using the kernel mode driver.

#### Settings of the kernel mode LAN heartbeat resources

For details on settings of the kernel mode LAN heartbeat resources, refer to "Heartbeat I/F tab" in Chapter 3, "Functions of the Builder."

#### Notes on the kernel mode LAN heartbeat resources

- ◆ It is recommended to specify two or more kernel mode LAN heartbeat resources; the one dedicated to interconnect and the one shared with interconnect and public.
- ◆ The communication data of alert synchronization is transmitted over the interconnect interface. You should consider network traffic when you make settings.
- ◆ You can set the same IP address to the interconnect LAN interface and the public LAN interface. If you do this, communication data of alert synchronization is transmitted.



# Displaying the properties of kernel mode LAN heartbeat resources with the WebManager

- **1.** Start the WebManager. (http://FIP\_address\_for\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click the kernel mode LAN heartbeat resources object, , in the tree view. The following information is displayed in the list view.

Kernel Mode LAN Heartbeat Name: lankhb1		Details
Server Name		us
server1	Online	
server2	Online	

Server Name: Server name

Status: Status of the heartbeat resource on the given server

If you click the **Details** button, the following information is displayed in the dialog box.

Properties	Value
Name	lankhb1
Type	lankhb
Comment	LAN Heartbeat
Status	Normal
IP Address	10.0.0.1

Name: Kernel mode LAN heartbeat resource name Type: Kernel mode LAN heartbeat resource type

Comment: Comment of the Kernel mode LAN heartbeat resource Status: Status of all kernel mode LAN heartbeat resources

IP Address: IP address of the LAN used for kernel mode LAN heartbeat

# Chapter 9 Details on network partition resolution resources

This chapter provides detailed information on network partition resolution resources.

#### This chapter covers:

•	Network partitions	····736
•	Understanding the network partition resolution resources	
•	Understanding network partition resolution by COM method	
•	Understanding network partition resolution by DISK method	741
•	Understanding network partition resolution by PING method	
•	Understanding network partition resolution by majority method	····746
•	Understanding network partition resolution by COM method and DISK method	748
•	Understanding network partition resolution by PING method and DISK method	748
•	Not resolving network partition	748


# **Network partitions**

Network partitioning, or "Split Brain" syndrome, refers to the status where all communication channels have problems and the network between servers is partitioned.

In a cluster system that is not equipped with solutions for "Split Brain Syndrome," a failure on a communication channel cannot be distinguished from an error on a server. This can cause data corruption brought by access from multiple servers to the same resource. ExpressCluster, on the other hand, uses resources for network partition resolution to distinguish a failure on a server from "Split Brain Syndrome" when a heartbeat from a server is lost. If the lack of heartbeat is determined to be caused by the server's failing, the system performs a failover by activating each resource and rebooting applications on a server running normally. When the lack of heartbeat is determined to be caused by "Brain Split" syndrome, emergency shutdown is executed because protecting data has higher priority over continuity of the operation.

# Understanding the network partition resolution resources

Servers in a cluster monitor other servers by using heartbeat resources. When all heartbeat resources are disconnected or other server is shut down by a server not in a cluster, the network partition is solved using network partition resolution resources. The following four types of network partition resolution resources are provided.




Network partition resolution resources	Abbreviation	Function Overview
COM network partition resolution resource (COM method)	comnp	A network partition is solved by connecting two servers with COM cable.
DISK network partition resolution resource (DISK method)	disknp	A network partition is solved by using a dedicated disk partition on the shared disk.
PING network partition resolution resource (PING method)	pingnp	A network partition is solved by determining a server that can communicate using the ping command.
Majority network partition resolution resource (Majority method)	majonp	A network partition is solved by the number of servers that can make connection among three or more servers.

A network partition resolution resource that can be selected is different depending on a server configuration in a cluster. Select one of the following network partition resolution methods:


Cluster server configuration	Network partition resolution method
'	(Listed in the order of our recommendation)
Mirror disk resource exists	Number of servers: 2
	- COM method and DISK method
	- PING method and DISK method
	- DISK method
	Number of servers: 3 or more servers
	- PING method and DISK method
	- DISK method
	- Majority method
Mirror disk resource exists but	Number of servers: 2
disk resource does not exist	- PING method
	- No network partition resolution
	Number of servers: 3 or more servers
	- PING method
	- Majority method
	- No network partition resolution
Neither disk resource nor mirror	Number of servers: 2
disk resource does not exist	- COM method
	- PING method
	- No network partition resolution
	Number of servers: 3 or more servers
	- PING method
	- Majority method
	- No network partition resolution

• For example, if both server1 and server2 use disk resource and mirror disk resource, the combination of DISK method and PING method, or a DISK method can be selected as a network partition resolution resource.

Disk resource and mirror disk resource



• When servers that can be started by disk resource and mirror disk resource differ, the network partition resolution resource needs to be set in each server. For example, if server1 and server2 use a shared disk, and server2 and server3 use a mirror disk, the combination of COM method and DISK method, PING method and DISK method, DISK method can be selected as network partition resolution resource for server1 and server2. PING method or COM method can be selected for server2 and server3.




# **Understanding network partition resolution by COM** method

### Settings of the COM network partition resolution resources

To use COM network partition resolution resources, prepare a serial cross cable to connect two servers.

The COM network partition resolution resources shut down a server with less priority when a network partition is detected.



For more information, refers to "COM I/F tab" in Chapter 3, "Function of the Builder."

#### **COM** network partition resolution resources

- **Note 1** COM network partition resolution resource can be used between two servers. When mirror disk resources are used, be sure not to use COM network partition resolution resource.
- Note 2 Emergent shut down takes places in all servers if all heartbeats are disconnected while the COM channel is having an error (for example COM port or serial cross cable.)
- **Note 3** If failures occur in all network channels between cluster servers and the COM channel simultaneously, both active and standby servers fail over. This can cause data corruption due to access to the same resource from multiple servers.

# Displaying the properties of COM network partition resolution resources with the WebManager

- **1.** Start the WebManager. (http://FIP\_address\_for\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click the COM network partition resolution resource object, , in the tree view. The following information is displayed in the list view.

COM Network Partition Resolution Resource		Details
Server Name	Stati	ıs
server1	Online	
server2	Online	

Server Name: Server name

Status: Status of the network partition resource on the given server

If you click the **Details** button, the following information is displayed in the dialog box.

Properties	Value
Name	comnp1
Type	comnp
Comment	com resolution
Status	Normal
Port Name	COM1

Name: COM network partition resolution resource name Type: COM network partition resolution resource type

Comment: Comment of the COM network partition resolution resource Status: Status of all COM network partition resolution resources Port Name: Port name used for COM network partition resolution


# Understanding network partition resolution by DISK method

#### Settings of the DISK network partition resolution resources

The following settings are required to use DISK network partition resolution resource:


- ◆ Allocate a dedicated disk partition for disk heartbeat resource on the shared disk. It is not necessary to format the partition.
- ◆ Allocate driver letters for the disk partition on the shared disk. The drive letters must be the same for all the servers.

DISK network partition resolution resources cause an emergency shutdown in servers that cannot communicate with the first priority server when a network partition is detected.



When a cluster is configured with two or more servers, DISK network partition resolution resources can be used as described below. DISK network partition resolution resources can be set to be used by servers that use the shared disk in a cluster.

For more information, refers to "Disk I/F tab" in Chapter 3, "Function of the Builder."



#### DISK network partition resolution resources

- **Note 1** It is recommended to use DISK network partition resolution resources when a shared disk is used.
- **Note 2** Configure DISK network partition resolution resources considering burden on the disk because they regularly perform read/write operations to the disk.
- **Note3** For disk heartbeat partitions to be used in DISK network partition resolution resources, use partitions that are configured to be managed in cluster in the HBA settings.
- **Note 4** If a failure has occurred on all network channels while all disk heartbeat partitions can be accessed normally, a network partition is detected. Then failover takes place in the master server and a server that can communicate with the master server. Emergent shutdown takes place in the rest of servers.
- Note 5 If heartbeat from other server is lost while all disk heartbeat partitions cannot be accessed normally, solving the network partition fails and a failover does not take place. In this case, emergency shutdown takes place even in servers working properly.
- Note 6 In a cluster configuration with multiple disk heartbeat partitions, if some disk heartbeat partitions have errors and heartbeat from other server is lost, the server status becomes Suspension (Network Partition Unsolved). Better availability is provided by keeping servers alive. However, no group can be started in servers whose status is Suspension (Network Partition Unsolved). Once all disk heartbeat partitions are recovered to be accessed normally, the server status becomes Online.
- Note 7 When the I/O time to the shared disk takes longer than I/O Wait Time of DiskNP resource configured in cluster properties, a failover may not be performed due to time-out of solving a network partition.
- Note 8 Solving a network partition with this method takes longer compared to other methods because delay in disk I/O needs to be taken into account. The time required to solve a network partition takes twice as long as the longer time of the heartbeat time-out and Disk I/O Wait Time configured in cluster properties.

# Displaying the properties of DISK network partition resolution resources with the WebManager

- **1.** Start the WebManager. (http://FIP\_address\_for\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click the DISK network partition resolution resource object, in the tree view. The following information is displayed in the list view.

DISK Network Partition Resolution Resource Details		Details
Server Name	Sta	tus
server1	Online	
server2	Online	

Server Name: Server name

Status: Status of the network partition resource on the given server

If you click the **Details** button, the following information is displayed in the dialog box.

Properties	Value
Name	disknp1
Type	disknp
Comment	disk resolution
Status	Normal
Volume Mount Point	W:\
Disk I/O Wait Time	80

Name: DISK network partition resolution resource name Type: DISK network partition resolution resource type

Comment: Comment of the DISK network partition resolution resource Status: Status of all DISK network partition resolution resources

Volume Mount Point: Drive letters of disk heartbeat partition


Disk I/O Wait Time: Read/Write wait time for DISK network partition resolution

# Understanding network partition resolution by PING method

#### Settings of the PING network partition resolution resources

To use PING network partition resolution resources, a device that is always active to receive and respond to the ping command (hereafter described as ping device) is required.

When the heartbeat from another server is lost but the ping device is responding to the ping command, the remote server is down. Failover starts. If there is no response to the ping command, it is determined that the local server is isolated from the network due to "Split Brain Syndrome," and emergency shutdown takes place.



For more information, refers to "Ping I/F tab" in Chapter 3, "Function for the Builder."

#### PING network partition resolution resource

**Note 1** When the status where no response returns from the ping command continues before heartbeat is lost, which is caused by a failure in the ping device, the network partitions cannot be solved.

If heartbeat is lost in this status, a failover takes place in all servers. Because of this, using this method in a cluster with a shared disk can cause data corruption due to access to a resource from multiple servers. Make sure to use both PING network partition resolution resources and DISK network partition resolution resources when a shared disk is used. When you use Ping network partition resource, specify transmittable and receivable addresses through interconnect LAN that is registered to the configuration data.

# Displaying the properties of PING network partition resolution resources with the WebManager

- **1.** Start the WebManager. (http://FIP\_address\_for\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click the PING network partition resolution resource object, , in the tree view. The following information is displayed in the list view.

PING Network Partition Resolution Resourc		Details
Server Name	Stati	us
server1	Online	
server2	Online	

Server Name: Server name

Status: Status of the network partition resource on the given server

If you click the **Details** button, the following information is displayed in the dialog box.

Properties	Value
Name	pingnp1
Type	pingnp
Comment	ping resolution
Status	Normal
IP Addresses	192.168.0.254
Ping Interval	5
Ping Timeout	3
Ping Retry Threshold	3

Name: PING network partition resolution resource name Type: PING network partition resolution resource type

Comment: Comment of the PING network partition resolution resource Status: Status of all PING network partition resolution resources

IP Addresses: List of IP addresses of the ping device


Ping Interval: Interval for PING network partition resolution resource
Ping Timeout: Timeout for PING network partition resolution resource

Ping Retry Threshold: Threshold value for retrying PING network partition resolution resource

# Understanding network partition resolution by majority method

#### Settings of the majority network partition resolution resources

This method prevents data corruption caused by "Split Brain Syndrome" by shutting down a server that can no longer communicate with the majority of the servers in the entire cluster because of network failure.



For more information, refers to "Majority I/F tab" in Chapter 3, "Function of the Builder."

## Majority network partition resolution resources

- **Note 1** This method can be used in a cluster with three or more nodes.
- **Note 2** If majority of the servers are down, emergency shutdown takes place in rest of the servers working properly. When communication with exactly half of the servers in the entire cluster is failing, emergency shutdown takes place in a server that cannot communicate with the top priority server.
- **Note 3** If all servers are isolated form the network due to a hub error, emergency shutdown takes place in all servers.

# Displaying the properties of majority network partition resolution resources with the WebManager

- **1.** Start the WebManager. (http://FIP\_address\_for\_WebManager\_group: port\_number (the default value is 29003)).
- 2. Click the majority network partition resolution resource object, \*\*\*, in the tree view. The following information is displayed in the list view.

Majority Network Partition Resolution Resour		Details
Server Name	Star	tus
server1	Online	
server2	Online	

Server Name: Server name

Status: Status of the network partition resource on the given server

If you click the **Details** button, the following information is displayed in the dialog box.

Properties	Value
Name	majonp1
Type	majonp
Comment	majo resolution
Status	Normal

Name: Majority network partition resolution resource name Type: Majority network partition resolution resource type

Comment: Comment of the majority network partition resolution resource Status: Status of all majority network partition resolution resources

# Understanding network partition resolution by COM method and DISK method

A network partition is solved by combining COM network partition resolution resources and DISK network partition resolution resources.

When the COM channel (such as a COM port and serial cross cable) is working properly, this method works in the same way as the COM method. When an error occurs on the COM channel, this method switches to the shared disk method. This mechanism allows for higher availability than using only the COM method. The method also resolves achieves network partition faster than using the disk method alone.

# Understanding network partition resolution by PING method and DISK method

A network partition is solved by combining PING network partition resolution resources and DISK network partition resolution resources.

When communication with ping device is working properly, this method works in the same way as the PING method. This mechanism allows for higher availability than using the PING method alone. The method also solves network partition faster than using only the disk method.

This method works as PING + DISK method when the server which uses PING network partition resolution resources and the server which uses DISK network partition resolution resources are identical. For example, in the clusters of hybrid disk configuration, when DISK network partition resolution resources used by a particular server group and PING network resolution resources used by the whole clusters are configured, these resources work independently. In such a case, to configure the resources to work in PING+DISK method, it is required to add PING network resolution resources to be used only by the same server group as DISK network partition resolution resources.

## Not resolving network partition

- This method can be selected in a cluster that does not use a shared disk.
- If a failure occurs on all network channels between servers in a cluster, all servers failover.

# **Chapter 10** Other monitor settings

This chapter provides information on other monitor settings.

#### This chapter covers:

•	Forced Outage Function ·····	750
•	Chassis Identify	752
•	Alert Service	754

## The forced stop function

## What is the forced stop function?

The forced stop function forcibly stops the failing server from one of the rest of servers working normally by using the IPMI function when it is recognized that the server is failing.

### Conditions for performing forced stop

- Forced stop is not performed when:
  - · The failover group successfully stops before the server fails
  - The server is shut down by the clpdown command, the OS shutdown command or WebManager and the failover group successfully stops
  - The cluster is stopped by the clpcl command or WebManager and the failover group successfully stops
  - The server fails and there is no failover group to perform failover from the failing server to another server (including when the failover group is not activated in the failing server)
- Forced stop is performed when the server is failing and there is a failover group to perform failover from the failing server to another server

### Commands to be used for forced stop

The hwreset command in IPMI Management Utilities (ipmiutil) is used to forcible stop a server. When the hwreset command cannot be used, this function cannot be used either.

Specify the following option values for the hwreset command execution in the **BMC** tab of **Server Properties**.

The hwreset command option	Configured in the BMC tab of the server properties
-N [target IP address]	IP address
-U [user name]	User name
-P [password]	Password

## Displaying and changing the details of forced stop

For the forced stop settings, refer to "Recovery tab" in "Chapter 3 Function of the Builder". For parameters for when the hwreset is executed, refer to "BMC tab".

## Notes on the forced stop

◆ About ipmiutil When you use this function, it is necessary to install ipmiutil 2.0.0 or later in each cluster server. For information on how to get ipmiutil and how to install it, refer to "Setup of BMC and ipmiutil" in "Chapter 1 Determining a system configuration" in the *ExpressCluster X Installation and Configuration Guide*.

#### ◆ Impacts on forced stop

When you use the forced stop function, the following functions are influenced because power off, reset, power cycle or NMI is forcibly performed regardless of the OS or server status.

#### · Dump collection

Since it is not recognized that dump files are being collected, power off, reset or power cycle is performed even though dump collection is being performed, so dump collection does not complete.

#### · Power on within heartbeat timeout

When the server is powered on again for the purpose of maintenance etc. within heartbeat timeout, power off, reset, power cycle or NMI may occur after heartbeat timeout has elapsed.

#### ◆ BMC network settings

Configure the settings so that the IP address of the LAN port for BMC management and the IP address which OS uses can communicate with each other. This function cannot be used when BMC is not installed in the server, or in the environment where the network for the BMC management is blocked.

Configure the same IP address that is configured for the LAN port for the BMC management to the BMC tab of the server properties.

See the server's manuals etc. for information on how to configure the IP address of the LAN port for the BMC management etc.

#### ◆ Power Options settings of the OS

When power off or power cycle is executed by BMC, operation specified in **Power Options** of the OS (e.g. sleep, hibernation and shutdown) may be executed.

These settings can be referred to and configured by the following instruction:

Windows 2003: Open **Power Options** in **Control Panel** and select **Advanced** tab,

Power buttons and When I press the power button on my computer

Windows 2008: Open **Power Options** in **Control Panel** and select **Choose what the power button does**, **Power button settings** and **When I press the power button:** 

When Forced stop is used in ExpressCluster, it is recommended that this setting is configured as **No Operation**.

# **Chassis Identify**

### What is chassis identify?

This function allows another normal server to report the server failure by blinking the chassis ID lamp using the IPMI function when it recognizes that the server is failing

### Conditions for chassis ID lamp to blink

- ◆ The chassis ID lamp does not blink when:
  - Statuses other than server status becomes abnormal
  - The cluster shuts down
  - · All the servers in the cluster fail
    If the servers do not fail simultaneously, they blink for 250 seconds at the maximum, and eventually the chassis ID lamps of all servers go off.
  - · BMC of the failing server cannot communicate with a normal server
  - There is a normal server in the cluster but ExpressCluster is stopped
- ◆ The chassis ID lamp blinks when (the above conditions for not blinking are given priority over these conditions when they overlap):
  - · When some servers in the cluster fail due to some abnormality
  - · When some servers in the cluster are shut down by the shutdown command of the OS.
  - When some servers in the cluster are made to shut down by the clpdown command or WebManager
  - When ExpressCluster is stopped by the clpcl command or WebManager in some servers in the cluster
  - · When some servers in the cluster are started while ExpressCluster Server service is configured as manual start
- Chassis ID lamp stops blinking and goes off when there are normal servers in the cluster, and the server status of the failing server returns to normal

## Behavior of the chassis ID lamp blinking when the cluster stops

If the chassis ID lamp of a server in the cluster is in blinking when the cluster stops, the chassis ID lamp may keep blinking for 250 seconds at the maximum.

## Commands to be used for chassis identify

The alarms command of IPMI Management Utilities (ipmiutil) is used to control the chassis ID lamp. When the alarms command cannot be executed, this function cannot be used.

Specify the following option values for the alarms command execution in the **BMC** tab of **Server Properties**.

The alarms command option	Configured in the BMC tab of the server properties
-N [target IP address]	IP address
-U [user name]	Use name
-P [password]	Password

#### Displaying and changing the chassis identify details

For the chassis identify settings, refer to "Alert service tab" in "Chapter 3 Functions of the Builder". For the parameters for executing the alarms command, refer to "BMC tab".

### Notes on chassis identify

#### ♦ About ipmiutil

To use this function, it is necessary to install ipmiutil 2.0.0 or later in each cluster server. For how to obtain ipmiutil and how to install it, see "Setup of BMC and ipmiutil" in "Chapter 1 Determining a system configuration" in the *ExpressCluster X Installation and Configuration Guide*.

#### ◆ BMC network settings

Configure the settings so that the IP address of the LAN port for BMC management and the IP address which OS uses can communicate with each other. This function cannot be used when BMC is not installed in the server, or in the environment where the network for the BMC management is blocked.

Configure the same IP address that is configured for the LAN port for the BMC management to the BMC tab of the server properties.

See the server's manuals etc. for how to configure the IP address of the LAN port for the BMC management etc.

### **Alert Service**

#### What is Alert Service?

ExpressCluster Alert Service is a function to report failures found in operations on ExpressCluster to system administrators in remote locations.

Failures are reported in two ways, each serving a different purpose.


(1) E-mail report

Alert messages in the WebManager are sent by e-mail to administrators.

(2) Warning light

The warning light is a visual display of the status of the server. When the server shuts down successfully, the warning light goes off.

The e-mail report and the warning light function work independently of each other.



Alert Service allows you to:

- Receive information about failures while not physically located in the place where management PC is. This is achieved via e-mail reporting function.
- Receive e-mail messages on your mobile phone.
- Visually be alerted of failures by viewing a light.

#### **Notes on Alert Service**

- ◆ To use this function, ExpressCluster X Alert Service 2.0/2.1 is required.
- ◆ The task of Alert Service is to send the first report of failure but not to examine or find the cause of failure. When a failure occurs, instead of using the Alert Service, try other methods, such as viewing ExpressCluster logs or syslog, to find out the cause of the error.
- ◆ When the warning light function is used in Windows Server 2008, it is necessary to set up the subsystem for UNIX base application (SUA).

#### Mail report actions

- ◆ Alert Service sends the same messages as the WebManager. For the alert messages to be reported by e-mail, see "Messages reported by event log and alert" in "Chapter 13 Error messages".
- ◆ You can change the alerts that are reported by e-mail. For more information, see "Alert service tab" in "Chapter 3 Functions of the Builder".

### **Warning Light status**

A warning light changes its status when:

(1) the server is started

When the server starts up successfully, warning light changes to green.

(2) when the server shuts down

When the server shuts down successfully, warning light goes off.

(3) when the server fails

When the server fails, its warning light flashes in red. If all servers in the cluster fail, the warning light of the server that failed last will not work because the warning light is controlled by a normal server that monitors other servers.

Once a lamp is lit or starts flashing, it will not go off until the cluster shuts down. Run the clpdn1000s command introduced in the following section to put the light out. For more information on the clpdn1000s command, see "ExpressCluster command reference" in the *Reference Guide*.

## Behavior of reporting icon

The icons indicate the server status. Depending on the server status, the icon displayed may change or blink.



When you point the cursor to the icon, a chip is displayed.



When the server status changes, a balloon is displayed.



Icons, chips and balloons are displayed as the following:

Icons	Title of chips / balloons	Description in balloons
<b>O</b>	ExpressCluster(*)	None
C	Service is stopped	The ExpressCluster Server service is stopped.
C	Service is starting	The ExpressCluster Server service is starting.
C	Service is terminating	The ExpressCluster Server service is about to terminate.
<b>G</b> ⇔ C	ExpressCluster is starting	ExpressCluster is starting up. Wait until all nodes are started.
	Operating normally	ExpressCluster is running normally.
<b>E</b>	Abnormal resource	Check the resource marked as abnormal on the WebManager.
<b>O</b>	<b>⊗</b> Isolated	Recover the server to the cluster.
C	Stopped	ExpressCluster is stopped.
C	SCluster suspended	The cluster is being suspended.
C	Cluster resumed	The cluster is being resumed.

<sup>(\*)</sup> Before ExpressCluster is started, the "ExpressCluster" chip may be displayed for a while.

# **Section III** Maintenance information

This section provides information on operation and maintenance of the ExpressCluster system.

- Chapter 11 The system maintenance information
- Chapter 12 Troubleshooting
- Chapter 13 Error messages

# Chapter 11 The system maintenance information

This chapter provides information you need for maintenance of your ExpressCluster system. Resources to be managed are described in detail.

#### This chapter covers:


Directory structure of ExpressCluster	.760
Communication ports	.762
Changing the disk configuration ~For a mirror disk~	.775
Linking to ESMPRO Agent	.779
Setting the UPS	. 780
Restoring the system disk	. 780
Replacing the shared disk	.783
Replacing the mirror disk	.784
Replacing FibreChannel HBA / SCSI controller	.785
	Directory structure of ExpressCluster  Communication ports  What causes ExpressCluster to shut down servers  Configuring the settings to temporarily prevent execution of failover  How to replace a server with a new one  Replacing the network card  Changing the disk configuration ~For a shared disk~  Changing the disk configuration ~For a mirror disk~  Backing up/restoring data  Performing a snapshot backup  Linking to ESMPRO Agent  Setting the UPS  Restoring the system disk  Replacing the shared disk  Replacing the mirror disk  Replacing FibreChannel HBA / SCSI controller  Information required for inquiry

# **Directory structure of ExpressCluster**

#### Note:

You will find executable files and script files that are not described in Chapter 4, "ExpressCluster command reference" under the installation directory. Run these files only with ExpressCluster. Any failures or trouble caused by executing them by applications other than ExpressCluster are not supported.

ExpressCluster directories are structured as described below:



1. Directory for alert synchronization

This directory stores ExpressCluster Alert Synchronization's modules and management files.

**2.** Directory for cluster modules

This directory stores the ExpressCluster Server's executable files and libraries.

3. Directory for cluster configuration data

This directory stores the cluster configuration files and policy file of each module.

**4.** Directory for event logs

This directory stores libraries that are related to the ExpressCluster event logs.

**5.** Directory related to Help

This directory stores the ExpressCluster help information.

**6.** Directory for licenses

This directory stores licenses for licensed products.

7. Directory for module logs

This directory stores logs produced by each module.

**8.** Directory for report messages (alert, event log)

This directory stores alert and event log messages reported by each module.

- **9.** Directory for the registry
- 10. Directory for script resource scripts of group resources

This directory stores script resource scripts of group resources.

11. Directory for the string table

This directory stores string tables used in ExpressCluster.

12. Directory for the WebManager

This directory stores the ExpressCluster X WebManager's modules and management files.

13. Directory for module tasks

This is a work directory for modules.

**14.** Directory for cluster drivers

This directory stores drivers for kernel mode LAN heartbeat and disk filter.

# **Communication ports**

ExpressCluster uses the following port numbers by default. You can change these port numbers by using the Builder. Make sure that the programs other than ExpressCluster do not access these port numbers.

To set up a firewall for the server, make sure that the following port numbers can be accessed.

Server - Ser	ver				
From			То		Remarks
Server	Auto-assignment <sup>1</sup>	$\rightarrow$	Server	29001/TCP	Internal communication
Server	Auto-assignment	$\rightarrow$	Server	29002/TCP	Data transfer
Server	Auto-assignment	$\rightarrow$	Server	29003/UDP	Alert synchronization
Server	Auto-assignment	$\rightarrow$	Server	29004/TCP	Communication between disk agents
Server	Auto-assignment	$\rightarrow$	Server	29005/TCP	Communication between mirror drivers
Server	29106/UDP	$\rightarrow$	Server	29106/UDP	Heartbeat (kernel mode)

Server - Clie	ent				
From			То		Remark
Server	Auto-assignment	$\rightarrow$	Server	29007/TCP 29007/UDP	Client-server communication

Server - Webl	<b>l</b> lanager				
From			То		Remarks
WebManager	Auto-assignment	$\rightarrow$	Server	29003/TCP	http communication

Integrated WebManager connected server-Server to be managed					
From			То		Remarks
Integrated WebManager connected server	Auto-assignment	$\rightarrow$	Server	29003/TCP	http communication

If mirror connect monitor resources are going to be used, you need to let icmp packets through because EXPRESSCLUSTER checks if ping reaches between servers. If mirror connect monitor resources are going to be used, modify firewall settings so that ping reaches between servers.

\_

<sup>&</sup>lt;sup>1</sup> An available port number at the time is automatically assigned.

# What causes ExpressCluster to shut down servers

When any one of the following errors occurs, ExpressCluster shuts down or resets servers to protect resources.

# Final action for an error in group resource activation or deactivation

When the final action for errors in resource activation/inactivation is specified as one of the following:

Final action	Result
The cluster service stops and the OS shuts down.	Causes normal shutdown after the group resources stop.
The cluster service stops and the OS reboots.	Causes normal reboot after the group resources stop.
An intentional stop error is generated	Causes a stop error (Panic) intentionally upon group resource activation/deactivation error.

#### Final action at detection of an error in monitor resource

When the final action for errors in monitor resource monitoring is specified as one of the following:

Final action	Result
Stop cluster service and shut down the OS	Causes normal shutdown after the group resources stop.
Stop cluster service and reboot the OS	Causes normal reboot after the group resources stop.
An intentional stop error is generated	Causes a stop error (Panic) intentionally upon monitor resource error detection.

## Forced stop action

When the setting is configured as "Use Forced Stop":

when the setting is configured as the configuration as the configured as the configuration as the configu				
Forced stop action	Result			
BMC reset	Causes reset in the failing server where the failover group existed.			
BMC power off	Causes power off in the failing server where the failover group existed.			
BMC power cycle	Causes power cycle in the failing server where the failover group existed.			
BMC NMI	Causes NMI in the failing server where the failover group existed.			

## **Emergency cluster shutdown**

When an abnormal termination is detected in the following process, ExpressCluster causes the normal shutdown after the group resources stopped.

• clprc

When an abnormal termination is detected in the following process, ExpressCluster causes the emergency shutdown after the group resources stopped

• clpnm

# Resource deactivation error in stopping the ExpressCluster Server service

When deactivating a resource by running clpcl –t, which stops the ExpressCluster Server service fails, ExpressCluster causes a shutdown.

#### Recovery from network partitioning

If all heartbeats are disrupted, network partitioning resolution takes place which results in one or all of the servers to shut down. When the server(s) is started after the shutdown, it is in the restarted status and is not clustered. When you resolve the problem that caused the disruption of heartbeats, recover the cluster.

For details of network partitioning, see Chapter 9, "Details on network partition resolution resources." For information on the suspended status (restart following the shutdown) and cluster recovery, see Chapter 1, "Functions of the WebManager."

#### **Emergency server restart**

When an abnormal termination is detected in the following process, ExpressCluster causes the OS restart after the group resources stopped.

clpdiskagent

# Configuring the settings to temporarily prevent execution of failover

Follow the steps below to temporarily prevent failover caused by a failed server or detection of an error during monitoring from occurring.

1. Temporarily adjust time-out

By temporarily adjusting time-out, you can prevent a failover caused by a failed server from occurring.

The clptoratio command is used to temporarily adjust time-out. Run the clptoratio command on one of the servers in the cluster.

(Example) To prevent a failover for an hour when the heartbeat time-out is set to 90 seconds:

clptoratio -r 40 -t 1h

2. Suspending monitoring operation of monitor resources

By suspending monitoring operations, a failover caused by monitoring can be prevented. The clpmonctrl command is used to suspend monitoring. Run the clpmonctrl command on all servers in the cluster.

(Example) To suspend all monitoring operations:

clpmonctrl -s

Follow the steps below to cancel the settings that prevent a failover when such settings are no longer necessary.

3. Cancel the temporarily adjusted time-out

Cancel temporary adjustment of time-out. Run the clptoratio command on one of the servers in the cluster.

clptoratio -i

4. Resume monitoring operation by monitor resources

Resume the monitoring operation. Run the clpmonctrl command on all servers in the cluster.

(Example) To resume all monitoring operations:

clpmonctrl -r

## How to replace a server with a new one

When you replace a server in a cluster environment, follow the instructions below:

- 1. Set up a new server in the same way as the failed server.
  - When using a shared disk, do not connect the new server to the shared disk yet.
  - Set the same computer name and IP address as the failed server.
  - Register the ExpressCluster license and apply updates as they have been registered and applied before.
  - If there were cluster partition and/or data partition of a mirror disk or hybrid disk on the local disk of the failing server, allocate these partitions and assign drive letters for them as they were configured in the failing server. When you use the disk of the failing server, configure drive letters for the partitions, though allocating partitions is not necessary.
  - When using a shared disk, set the SCSI controller or the HBA that is connected to the shared disk to be filtered in Filter Settings of Shared Disk upon installing the ExpressCluster Server.
  - After the setup, shut it down and power it off.

#### Important:

In **Filter Settings of Shared Disk**, set the SCSI controller or the HBA that is connected to the shared disk to be filtered. If the new server is connected to the shared disk when it has not been set to be filtered, data on the shared disk may be corrupted.

- 2. If the failed server is still running, shut it down and remove it from the shared disk and the LAN, and make sure other servers in the cluster are working properly. (Ignore errors caused by the failed server being stopped.)
- 3. Start the new server while it is connected to the LAN. When using a shared disk, start the server while it is also connected to the shared disk.
- 4. When using the shared disk, on the new server, use Disk Management (On the **Start** menu, point to **Settings**, and click **Control Panel**. Double-click **Administrative Tools** and then **Computer Management**, and click **Disk Management**.) to confirm that the shared disk is visible, and set the same drive letter as the failed server.
  - At this point, access to the shared disk is controlled, so the disk data cannot be referred.
- **5.** Connect to a server in normal operation in the cluster by using the Web browser to start the Builder. When using a shared disk, click **Properties, HBA** tab and **Connect** on the new server to check or modify the information on HBA and partitions.

#### Important:

On the **HBA** tab of **Properties** of the new server, set the SCSI controller or the HBA that is connected to the shared disk to be filtered. If the shared disk is connected when it has not been set to be filtered, data on the shared disk may be corrupted.

- **6.** When there is any mirror disk resource or hybrid disk resource in the resources used in the new server, stop the failover group containing these resources from the WebManager.
- 7. Run "clpcl --suspend --force" from the command prompt on the server in normal operation in the cluster and suspend the cluster.
  - A server is recognized to have stopped, so the cluster cannot be suspended from the WebManager.

- **8.** Upload the updated cluster configuration data from the Builder. When the message "There is difference between the disk information in the configuration information and the disk information in the server. Are you sure you want automatic moification?" appears, select **Yes**.
- 9. Resume the cluster from the WebManager. If you stopped any group in step 6, start it.

#### Note:

If you resume the cluster from the WebManager, the error message "Failed to resume the cluster. Click the Reload button, or try again later." is displayed, but ignore it. This is displayed because the new server has not been suspended.

- 10. Right-click the new server on the WebManager, and select Service and then Start.
- **11.** When **Off** is selected for **Auto Return** in **Cluster Properties**, right-click the server where ExpressCluster has been reinstalled by using the WebManager and select **Recover**.
- **12.** When a mirror disk resource or hybrid disk resource exists in the resources used in the new server and the **Auto mirror recovery** check box is not selected in **Properties** of the cluster, copy the mirror disk or hybrid disk fully from Mirror Disk Helper.
- **13.** Move group as necessary. When mirror disk or hybrid disk is being fully copied, complete copying before moving.

# Wait time for synchronized cluster startup

Even all servers in a cluster are powered on simultaneously, it does not always mean that ExpressCluster will start up simultaneously on all servers. ExpressCluster may not start up simultaneously after rebooting the cluster following shutdown. Because of this, one server waits for other servers in the cluster to start.

By default, 5 minutes is set to the startup synchronization time. To change the default value, click **Cluster Properties** in the Builder, click the **Timeout** tab, and select **Synchronize Wait Time**.

For more information, see the description for the "Timeout tab" in Chapter 3, "Function of Builder" of this guide.

# Changing the server configuration (add/delete)

## Adding a server

To add a server, follow the steps below:

- 1. Make sure that the cluster is working properly.
- 2. Start the server to add. For using the shared disk, make sure the server to add is not connected to the shared disk and then start the server to add.

#### Important:

To use the shared disk, do not connect the server to the shared disk before setting it up and powering it off. Data on the shared disk may be corrupted.

Configure the settings that should be done before setting up the ExpressCluster Server on the server to add. However, to use the shared disk, do not configure the settings for the disk in this step.

#### **Related Information:**

As for the settings to be configured before the setup, see "Settings after configuring hardware" of Chapter 1, "Determining a system configuration" in *Installation and Configuration Guide*.

4. Set up the ExpressCluster Server to the server to add. Enter the port numbers of the WebManager and the disk agent. Configure the same settings for the port number as the server that has been already set up. To use the shared disk, set the HBA that is connected to the shared disk to be filtered. Register the license as necessary. After the setup, shut down the server to add and power it off.

#### **Important:**

If the shared disk is not set to be filtered in **Filter Settings of Shared Disk** when setting up the ExpressCluster Server, do not connect to the shared disk even after the setup completes. Data on the shared disk may be corrupted. Reinstall ExpressCluster and set the shared disk to be filtered.

- 5. Start the server to add. To use the shared disk, connect the disk to the server to add at first, and then start the server.
- **6**. To use the shared disk, configure the settings for the disk on the server to add.
  - Use Disk Management (On the start menu, point to Settings, and click Control Panel. Double-click Administrative Tools and then Computer Management, and click Disk Management.) to confirm that the shared disk is visible.
  - Set the switchable partitions for disk resources and the partitions used as the cluster partition or data partition for hybrid disk resources so that they can be accessed from all the servers by using the same drive letters.
  - On all the servers, set the same drive letter to the disk heartbeat partitions to be used for the disk network partition resolution resources.
  - At this point, access to the shared disk is controlled, so the disk data cannot be referred.
- 7. Access to other server in the cluster via the Web browser and start the Builder. Right-click **Servers** on the tree in the left pane of the Builder, and select the server to add. Enter the required information and add the server. To use the shared disk, set the SCSI controller or the HBA that is connected to the shared disk to be filtered.

#### Important:

If the settings are not configured for the shared disk, data on the shared disk may be corrupted. Set the SCSI controller or the HBA that is connected to the shared disk to be filtered.

- **8.** When using a hybrid disk resource in the added server, right-click the server group on the tree in the left pane of the Builder, and select **Properties**. Add the server to **Servers that can run the Group** on the **Server Groups** tab. Do this for required servers only.
- **9.** Right-click the failover group on the tree in the left pane of the Builder, and select the properties. Add the server that can be started on the **Startup Server** tab. Add the server that can be started only to the required failover group.
- 10. By using the Builder, configure the following settings of the server to add.
  - Information on the HBA and the partition on the **HBA** tab of **Properties** of the server to add (when using the shared disk).
  - Information on the disk heartbeat partition on the **Disk I/F** tab of **Properties** of the server to add (when using the shared disk).
  - Information on the source IP address of the server to add on the **Details** tab of **Properties** of the virtual IP resource (when using the virtual IP resource).

- Information on the switchable partition of the server to add which is displayed on the **Details** tab of **Properties** of the disk resource.
- IP address of the server to add on the **Parameter** tab of **Properties** of the Nic Link Up/Down monitor resource (when using the Nic Link Up/Down monitor resource).

#### Important:

On the **HBA** tab of **Properties** of the server to add, set the SCSI controller and the HBA connected to the shared disk to be filtered. If the shared disk is connected when it has not been set to be filtered, data on the shared disk may be corrupted.

- 11. Connect to another server in the cluster via the Web browser to start the WebManager, and suspend the cluster. When the server group configuration has been changed, stop the cluster.
- **12.** Select **Upload the Configuration File** from the **File** menu of the Builder, and reflect the cluster configuration data to the cluster.
  - When the message "There is the disk information that is not configured. Are you sure you want automatic configuration?" appears, select **Yes**.
- 13. Resume the cluster after restarting the Manager with the WebManager. If the cluster has been stopped, start it.

#### Note:

If the cluster is resumed by using the WebManager, the message "Failed to resume the cluster. Click the Reload button, or try again later." is displayed, but ignore it. This message is displayed because the server to add is not suspended.

- **14**. Restart the service of the added server with the WebManager. When **Off** is selected for **Auto Return** in Cluster **Properties**, recover the cluster by using the WebManager manually.
- 15. Return the added server with the WebManager to the cluster.
- **16**. Move group as necessary.

## Deleting a server

To delete a server, follow the steps below:

 From the WebManager, stop the server to delete, close all the connections including LANs, SCSIs and COMs.

#### Important:

When the shared disk is used, take the following steps after closing all the connections to the shared disk completely. If a connection to the shared disk is kept after uninstalling ExpressCluster, data on the shared disk may be corrupted.

- **2.** Make sure that the cluster is working properly. (However, ignore errors in the server to be deleted.)
- 3. Run the "clpcl --suspend --force" command at the command prompt, and suspend only the server that has been started.
- **4.** When the server to be deleted is registered in a server group, right-click the server group in the tree in the left pane of the Builder, and then select **Properties**. Delete the target server from **Servers that can run the Group** in the **Server Groups** tab.
- Right-click the server to delete on the tree in the left pane of the Builder, and select Remove the server.

- **6.** Execute "clpcl --suspend --force" from command prompt on the server in normal operation in the cluster to suspend only the servers in operation. When the server group configuration has been changed, stop the cluster from the WebManager.
- 7. Select **Upload the Configuration File** from the **File** menu of the Builder, and reflect the cluster configuration data to the cluster.
- **8.** Resume the cluster by using the WebManager.
- **9.** Uninstall ExpressCluster from the server you have deleted.
- **10.** Shut down the deleted server.

# Changing the server IP address

To change the server IP address after you have started the cluster system operation, follow the instructions below.

## When changing the mirror connect IP address is not required

- 1. Make sure that the cluster is working properly.
- 2. Suspend the cluster by using the WebManager.
- 3. Change the OS network configuration in the **Properties** of **My Network Places**.
- **4.** Change the IP address on the **Interconnect LAN I/F** tab and the **Public LAN I/F** tab of the server properties by using the Builder.
- **5.** If the changed IP address is used for the NIC Link Up/Down monitor resource, change the IP address on the **Parameter** tab of the monitor resource properties.
- **6.** Select **Upload the Configuration File** from the **File** menu of the Builder, and reflect the cluster configuration data to the cluster.
- 7. Resume the cluster by using the WebManager.

### When changing the mirror connect IP address is required

- **1.** Make sure that the cluster is working properly.
- 2. Stop the cluster by using the WebManager.
- 3. Change the OS network configuration in the **Properties** of **My Network Places**.
- **4.** Change the IP address on the **Interconnect LAN I/F** tab, the **Public LAN I/F** tab and the **Mirror Connect I/F** tab of the server properties by using the Builder.
- **5.** If the changed IP address is used for the NIC Link Up/Down monitor resource, change the IP address on the **Parameter** tab of the monitor resource properties.
- **6.** Select **Upload the Configuration File** from the **File** menu of the Builder, and reflect the cluster configuration data to the cluster.
- **7.** Reboot the OS on all the servers.

## Changing the host name

Follow the steps below if you want to change the host name of a server after you have started the cluster system operation.

## Environment where the mirror disk / hybrid disk does not exist

- 1. Make sure that the cluster is working properly.
- 2. If the group is started on the server whose host name is to be changed, move the group.
- 3. Suspend the cluster by using the WebManager.
- 4. Change the host name in the properties of My Computer.

#### Note:

Do not restart the OS at this stage. The cluster configuration data will not be able to be reflected until the OS is completely restarted.

- 5. Right-click the server name on the tree in the left pane of the Builder, and select **Rename**Server
- **6.** Select **Upload the Configuration File** from the **File** menu of the Builder, reflect the cluster configuration data to the cluster.
- **7.** Restart the OS on the server you have changed the host name.
- **8.** Resume the cluster from the WebManager.

#### Note:

If the cluster is resumed from the WebManager, the error message "Failed to resume the cluster. Click the Reload button, or try again later." is displayed, but ignore it. This message is displayed because the server whose host name was changed is not suspended.

9. Right-click the server whose server name has been changed on the tree in the left pane of the WebManager, and select **Start** of **Service** to start the cluster. When **Off** is selected for **Auto Return** in **Cluster Properties**, recover the cluster by using the WebManager manually.

### Environment where the mirror disk / hybrid disk exists

- 1. Make sure that the cluster is working properly.
- 2. Stop the cluster by using the WebManager.
- 3. Change the host name in the properties of My Computer.

#### Note:

Do not restart the OS at this stage. The cluster configuration data will not be able to be reflected until the OS is completely restarted.

- Right-click the server name on the tree in the left pane of the Builder, and select Rename Server.
- 5. Select **Upload the Configuration File** from the **File** menu of the Builder, reflect the cluster configuration data to the cluster.
- **6.** Reboot the OS on all the servers.

# Replacing the network card

To replace the network card, follow the steps below. To replace the network card used for the mirror connect, follow the same steps as well.

- 1. Make sure that the cluster is working properly. (However, ignore errors in the network card to be replaced.)
- 2. If a group is running on the server whose network card is to be replaced, move the group. If the network card has been used for the mirror connect, no groups can be moved until the mirror disk recovers after the replacement. Because of this, stop the group by WebManager.
- 3. Open Services on the server whose network is to be changed (On the **start** menu, point to **Settings**, and click **Control Panel**. Double-click **Administrative Tools** and then **Services**.) set **Startup Type** to **Manual** from **Properties** of the ExpressCluster Server service and the ExpressCluster X Disk Agent service.
- **4.** Right-click the server whose network card is to be replaced on the tree in the left pane of the WebManager, and select **Shut Down**.
- **5.** After the shutdown completes, replace the network card.
- **6.** Start the server that the network card is replaced.
- 7. Configure the settings for the OS network in the **Properties** of **My Network Places**. Configure the same settings for the network as before replacing the network card.
- 8. Open Services on the server whose network card has been replaced (On the **Start** menu, point to **Settings**, and click **Control Panel**. Double-click **Administrative Tools** and then **Services**.), and set **Startup Type** to **Automatic** from **Properties** of the ExpressCluster Server service and the ExpressCluster X Disk Agent service.
- **9.** When **Off** is selected for **Auto Return** in **Cluster Properties**, recover the cluster by using the WebManager manually.
- **10.** Move group as necessary.

# Changing the disk configuration ~For a shared disk~

#### Replacing the disk

To replace the shared disk, see "Replacing the shared disk."

#### Adding a disk

The following shows the procedures to add a disk resource. When you add a hybrid disk, consider "disk resource" as "hybrid disk resource", and "partition used for disk resource" as "data partition". Note that it is necessary to add the disk to both of two server groups when you add a hybrid disk resource. As for cluster partition, an existing cluster partition can be used, but it is necessary to configure it so that the offset index of the cluster partition does not overlap the existing hybrid disk.

- 1. Make sure that the cluster is working properly.
- 2. Stop the cluster by using the WebManager.
- 3. Change **Startup Attribute** to manual on the **Attribute** tab of **Properties** of the group to which the disk resource is added.
- **4.** Select **Upload the Configuration File** from the **File** menu of the Builder, and reflect the cluster configuration data to the cluster.
- **5.** Shut down all the servers and power them off.
- **6.** Power off the shared disk and add a disk.
- 7. Power on the share disk and configure its settings.
  - If it is required to build a RAID again or to change the LUN configuration, use the setup tool provided with the shared disk. For details, see the manual attached to the shared disk.
- 8. Start only one server, and create a partition used for the disk resource using Disk Management (On the **Start** menu, point to **Settings**, and click **Control Panel**. Double-click **Administrative Tools** and then **Computer Management**, and click **Disk Management**.) and set its drive letter.

#### Note:

Controlling the access to the created partition is started upon its creation, so it cannot be formatted. Set only the drive letter.

- To create a disk heartbeat partition, create it in the same way as the disk resource, and set the drive letter. Do not format the partition.
- 10. Start other servers in the cluster, and by using Disk Management (On the Start menu, point to Settings, and click Control Panel. Double-click Administrative Tools and then Computer Management, and click Disk Management.), confirm that the partition created by the first server is visible.
- **11.** Set the drive letter of the partition used as the disk resource in the same way as the first server.
- **12.** If the disk heartbeat partition has been created, set its drive letter in the same way as the first server
- 13. Start the WebManager, and stop the cluster.

- 14. Start the Builder, and right-click the group to add a disk resource, and add a disk resource from Add Resource. Change Startup Attribute to manual on the Attribute tab of Properties of the group.
- **15.** If the disk heartbeat partition has been added, in all the servers in the cluster, add a disk network partition resolution resource on the **Disk I/F** tab of **Server Properties**.
- **16.** Select **Upload the Configuration File** from the **File** menu of the Builder, and reflect the cluster configuration data to the cluster.
- 17. Start the cluster by using the WebManager.
- **18.** Format the partition used by the disk resource by using the server whose disk resource has been started.

### **Deleting a disk**

- 1. Make sure that the cluster is working properly.
- **2.** Stop the cluster by using the WebManager.
- **3.** Start the Builder and select the group whose disk resource is to be deleted. Right-click the disk resource from **Resources**, and select **Remove**. When there is a hybrid disk resource using the partition of the disk to be deleted, delete it as well.
- **4.** Select **Upload the Configuration File** from the **File** menu of the Builder, and reflect the cluster configuration data to the cluster.
- **5.** Shut down all the servers, and power them off.
- **6.** Power off the shared disk and remove it.
- 7. Power on the shared disk, and configure its settings.
  - If it is required to build a RAID again or to change the LUN configuration, use the setup tool provided with the shared disk. For details, see the manual attached to the shared disk.
- **8.** Start all the servers.

# Changing the disk configuration ~For a mirror disk~

### Replacing the disk

To replace the mirror disk, see "Replacing the mirror disk."

### Adding a disk

To add a disk used for the mirror disk, follow the steps below:

- 1. Make sure that the cluster is working properly.
- **2.** If the group is running on the server to which a disk is added, move the group.
- 3. Shut down only one server by using the WebManager, and power it off.
- **4.** Expand the disk, and start the server.
- **5.** Return the server to the cluster, and rebuild the mirror again.
- **6.** Configure the settings for the disk by the server on which the disk is added.
  - Reserve a data partition and a cluster partition for mirror disk using Disk Management
    (On the Start menu, point to Settings, and click Control Panel. Double-click
    Administrative Tools and then Computer Management, and click Disk
    Management.). Set their drive letters so that they will be the same on both of the servers.
- **7.** Perform the steps 2 to 6 on other server.
- **8.** Suspend the cluster by using the WebManager.
- **9.** Start the Builder, and right-click the group to which the mirror disk resource is added, and add the mirror disk resource from **Add Resource**.
- **10.** Select **Upload the Configuration File** from the **File** menu of the Builder, and reflect the cluster configuration data to the cluster.
- 11. Resume the cluster by using the WebManager.
- 12. Start the added mirror disk resource or the group that added the mirror disk resource. If **Auto**Mirror Initial Construction is set to be performed in Cluster Properties, the initial mirror construction is started. If **Auto Mirror Initial Construction** is set not to be performed, perform the initial mirror construction manually.
- 13. Move group as necessary.


## Deleting a disk

Follow the steps below to delete the disk used for the mirror disk.

- 1. Make sure that the cluster is working properly.
- 2. Stop the group with the mirror disk resource to be deleted by using the WebManager.
- **3.** Suspend the cluster by using the WebManager.
- **4.** Start the Builder and select the group from which the mirror disk resource is deleted. Right-click the mirror disk from **Resources** and select **Remove**.
- **5.** Select **Upload the Configuration File** from the **File** menu of the Builder, and reflect the cluster configuration data to the cluster.
- **6.** Resume the cluster by using the WebManager.
- 7. Start the group with the WebManager.
- **8.** Shut down the server on which the group has not been started with the WebManager, and power it off.
- **9.** Remove the disk, and start the server.
- **10.** Move the group, and perform the steps 8 and 9 on other server.
- **11.** Move group as necessary.

# Backing up/restoring data

Data is backed up and restored, as shown in the following image. For details on how to back up data, see the manuals of the backup software.



# Performing a snapshot backup

When a mirror disk or a hybrid disk is used, it is possible to suspend mirroring to back up the stand-by data partition as a snapshot image. This is referred to as snapshot backup.

During executing snapshot backup, failover cannot be performed to the stand-by server or server group of the copying destination since mirroring is temporarily cancelled. While in this state, cancel the access restriction to the data partition of the standby server to collect the backup.

To return from the snapshot status, control the disk access and build the mirror again.

For details for how to collect the backup, see the manuals of the backup software.

### Performing a snapshot backup

To execute the snapshot backup for a mirror disk, follow the steps below:

 Stop the mirror disk monitor resource that monitors the mirror disk that will be backed up on the server to be backed up.

```
clpmonctrl -s -m <mdw(mirror_disk_monitor_resource_name)>
```

**2.** Disconnect the mirror disk.

```
clpmdctrl --break <md(mirror_disk_resource_name)>
```

**3.** Allow accesses to the mirror disk.

```
mdopen <md(mirror_disk_resource_name)>
```

- **4.** Back up necessary files.
- 5. Forbid accesses to the mirror disk.

```
mdclose <md(mirror_disk_resource_name)>
```

**6.** Recover the mirror disk.

```
clpmdctrl --recovery <md(mirror_disk_resource_name)>
```

7. Start the mirror disk monitor resource that monitors the mirror disk.

```
clpmonctrl -r -m <mdw(mirror_disk_resource_monitor_resource_name)>
```

To execute the snapshot backup for a hybrid disk, collect the backup by following the steps below in a server in the standby server group of the copying destination.

1. Run the following command in the server where the backup is collected.

```
Clphdsnapshot -open <hybrid_disk_resource_name>
```

- 2. When the access restriction in the data partition is cancelled, back up the required files.
- **3.** Run the following command in the server where the backup has been collected to restart mirroring.

```
Clphdsnapshot --close <hybrid disk resource name>
```

**4.** When the automatic mirror recovery is disabled, perform mirror recovery manually from Mirror Disk Helper.

For the commands, see Chapter 4, "ExpressCluster command reference" of this guide.

# **Linking to ESMPRO Agent**

By linking to ESMPRO Agent, ExpressCluster can fail over by the event logs indicating the system error. To monitor the event logs, it is required to set up ESMPRO Agent on the cluster server.

## **Environment settings**

In the report settings from ESMPRO Agent to the event log to be monitored, register the execution of the failover command to all the servers that configure the cluster.

For example, if an error is detected, register the ARMDOWN command.

For details on setting ESMPRO Agent, see the manual of ESMPRO Agent.

## Setting the UPS

To power on a server when the multifunction UPS is connected to, set the AUTO/LOCAL switch on the rear side of the UPS that is connected to the server to LOCAL, and return the AUTO/LOCAL switch to AUTO after it is powered on by the ON/OFF switch on the front side of the UPS.

In case of the shared disk system, it is not required to operate the Auto/Local switch of the UPS that is connected to the shared disk.

Also, power on all the servers within the delay time of startup synchronization (default value: 5 minutes) that is set by the ExpressCluster X Builder. If they are not powered on during this time, a failover occurs.

Also, the shared disk system performs the initialization process for a few minutes after it is turned on the power. During the initialization process, if a server (OS) has been started, the shared disk cannot be recognized. Make sure that the server will not be started during this time.

# Restoring the system disk

If an error occurs in the system disk of the server, change the disk following the steps below, and restore the backup data. If ExpressCluster has been updated or changes have been made on the configuration after the backup was created, make sure to uninstall ExpressCluster after restoration and set this server as a new server by following the steps for server replacement.

1. If any group is running on the server where a system disk is restored (hereafter referred to as target server), move the group. When a mirror disk resource or hybrid disk resource is used, make sure that these resources are running properly after the group is moved.

#### **Important:**

If the mirror disk resource or hybrid disk resource is not in the latest status, and if the system disk is restored on the server that is not to be restored, the data on the data partition may be corrupted.

- 2. If the mirror disk resource or hybrid disk resource is used, execute the following procedure.
  - **2-1.** Start up the Builder and right click on the cluster. In the **Properties**, select **Mirror Disk** tab and uncheck **Auto Mirror Recovery**.
  - **2-2.** In **File** menu of the Builder, select **Upload the Configuration File** and reflect the cluster configuration data to the cluster.
- If the target server is running, shut down the server by selecting Shut Down from Start menu.
- **4.** When the shared disk is connected to the target server, remove the cable connecting the target server and the shared disk. Remove the cable carefully by following the instructions shown below:
  - When a SCSI disk array is used, remove the cable from the base of the two-way cable.
  - When a Fibre Channel disk array device, remove the cable between the failing server and the Fibre Channel-HUB or the Fibre Channel-Switch.
- **5.** Change the system disk of the server to be restored. For details on how to change the system disk, see the user's guide provided with the device.
- **6.** Follow the normal installation procedure and install the OS.
  - To install the OS, see the user's guide provided with the server.

- Make sure to configure the network settings when installing the OS. Apply the same OS service pack as the removed disk.
- 7. Make sure that the OS is running normally, and install the backup software. (For details, see the manual of the backup software.)
- **8.** Use the backup software to restore the system disk from the backup.
  - There is no note cluster dependent note. Restore the system disk with the settings that allow the registry to be recovered and files with the same file names to be overwritten. For details, see the manual of the backup software.
- **9.** When the ExpressCluster Server service of the target server is configured as Auto Startup, change the settings to Manual Startup.
- **10.** Reset its drive letter if it has been changed. Make sure that the date and time are the same as those of other servers in the same cluster.
- 11. When the driver of SCSI controller or FC-HBA (Host Bus Adapter) cannot be restored, re-install the above driver. For details, refer to the instruction manual of backup software.
- **12.** Restart the target server. When the shared disk is not connected to the target server, the following steps up to 16 are not required.
- 13. Connect to the server that has not been restored via the Web browser to start the Builder. Open the **Properties** of the target server to configure the filter settings of the HBA connected to the shared disk.
  - Click the connect button of the HBA tab to acquire the disk configuration information of the target server, and select the checkbox of the HBA connected to the shared disk.
  - Do not change any settings other than above.
- **14.** Use Builder to save the cluster configuration information in which HBA filter settings have been configured in a disk area accessible from a cluster server.
  - When the Builder is used on a cluster server, save the information in the local disk. When the Builder is used in another PC, save the information in the shared disk that can be accessed from the cluster server or save it in a floppy disk or the like and then copy it to the local disk of a cluster server.
- **15.** Run the following command on one of the cluster servers to upload the saved cluster configuration information.
  - clpcfctrl --push -x <path\_of\_the\_cluster\_configuration\_information> --nocheck
- 16. Shut down the target server and connect the disk cable, and then reboot the server.
- 17. Start the target server and check the drive letter of the shared disk and the mirror disk (data partition and cluster partition) in **Disk Management** of the target server. If the drive letter has been changed, re-configure it as it was, restart the server and check that the drive letter is configured correctly.
- **18.** Connect to the server which has not been restored via the Web browser to start the Builder. When the shared disk is connected to the target server and the shared disk has a volume that is not for filtering, update the information on the partition that is not for filtering in the **HBA** tab of **Properties** in the target server.
- **19.** Perform the procedures in steps 14 and 15 above to save the cluster configuration information and then upload the information by using the clpcfctrl command from the server.
  - If the message "There is difference between the disk information in the configuration information and the disk information in the server. Are you sure you want automatic moification?" appears upon saving the configuration information, select **Yes**.
- **20.** Restore the setting of the ExpressCluster Server service to Auto Startup and reboot the target server.

- **21.** When the Auto Recovery is configured as **Off** in **Properties** of the cluster, right-click the target server and select **Recover** in the WebManager. If mirror disk resource or hybrid disk resource is not used on the target server, the following procedure is not required.
- **22.** Execute the mirror recovery (full copy) from the Mirror Disk Helper of WebManager to all the mirror disk resources and hybrid disk resources.
  - •A server where restoring is not performed must be the source of the copy.
  - •Recover the mirror by fully copying, not partially copying because the data difference may be invalid in the process of restoring.
- **23.** Start up the Builder and right click on the cluster. In the **Properties**, select **Mirror disk** tab and check **Auto Mirror Recovery.**
- **24.** In **File** menu of the Builder, select **Upload the Configuration File** to upload the cluster configuration data to the cluster.

# Replacing the shared disk

**Important:** Before step 14, it is not possible to access to the partitions under HBAs to be managed by cluster, even if the partition is not access restricted.

- **1.** Make sure that the cluster is working properly. (However, ignore errors in the disk to be replaced.)
- 2. Stop the cluster by using the WebManager. When the shared disk to be replaced is connected to some of the servers but not all, stop those servers only.
- **3.** On all servers connected to the shared disk to be replaced, set **Startup Type** to **Manual** from **Properties** of the **EXPRESSCLUSTER Server** service.
- 4. Shut down all the servers connected to the shared disk to be replaced, and power them off.
- **5.** Power off the shared disk, and change the disk.
- **6.** Power on the shared disk, and configure its settings.
  - If it is required to build a RAID again or to change the LAN configuration, use the setup tool provided with the shared disk. For details, see the manual provided with the shared disk.
- 7. Start only one server, create a partition by using Disk Management (On the Start menu, point to Settings, and click Control Panel. Double-click Administrative Tools and then Computer Management, and click Disk Management.), and set the drive letter as before replacing the disk.

#### Note:

Controlling the access to the created partition is started upon its creation, so it cannot be formatted. Set only the drive letter.

#### Note:

The size of the switchable partition used for disk resource can be changed in this occasion. The size of the data partitions of hybrid disk resource need to be the same in both server groups. Because of this, to change the size it is necessary to delete the resource, change the partition size in both server groups and then create the resource again.

- 8. Start other servers connected to the replaced shared disk in the cluster, by using Disk Management (On the **Start** menu, point to **Settings**, and click **Control Panel**. Double-click **Administrative Tools** and then **Computer Management**, and click **Disk Management**.), and check that the partition created by the first server is visible.
- Set the drive letter of the partition used for the disk resource in the same way as the first server.
- **10.** Start the Builder online.
- 11. When there are partitions with no access restriction on the replaced shared disk, add these partitions in **Partition excluded from cluster management** by selecting **Properties**, the **HBA** tab and **Connect** in each server connected to the shared disk.
- 12. When some servers are operating as cluster, stop the cluster from the WebManager.
- **13.** Select **Upload the Configuration File** from the **File** menu of the Builder, and reflect the cluster configuration data to the cluster.
  - When the message "There is difference between the disk information in the configuration information and the disk information in the server. Are you sure you want automatic modification?" appears, select **Yes**.
- **14.** On all servers connected to the replaced shared disk, re-configure **Startup Type** to **Automatic** from **Properties** of the **EXPRESSCLUSTER Server** service.
- **15.** Start the WebManager, and start the cluster.

- **16.** Format the partition used for the disk resource from the server on which the disk resource is running. In case the group with the disk resource is stopped, format the partition after starting the disk resource as necessary.
- 17. When there is a partition of the hybrid disk resource on the replaced shared disk, rebuilding of mirroring (full copy) is automatically performed if the **Auto mirror recovery** is configured in the **Mirror disk** tab of **Cluster Properties**. If the settings are configured not to perform **Auto mirror recovery**, reconfigure mirror manually.

# Replacing the mirror disk

If an error occurs in a disk that forms a mirror set, follow the steps below to replace the disk. When disks are arrayed, following procedure is required if the array is rebuilt.

You can replace a local disk mirrored by a hybrid disk resource by following the steps below. In that case, consider "mirror disk resource" in the description below as "hybrid disk resource".

- **1.** Make sure that the cluster is working properly. (However, ignore errors in the disk to be replaced.)
- 2. If the group is running on the server, which contains the disk to be replaced, move the group.
- 3. When the **Auto Mirror Recovery** checkbox is selected in **Properties** of the cluster, start the Builder on line, select **Properties** of the cluster and the **Mirror disk** tab, clear the **Auto Mirror Recovery** checkbox, select **Upload the Configuration File** in the **File** menu to reflect the cluster configuration data to the cluster.
- 4. Shutdown the server whose disk is to be replaced from the WebManager and power it off.
- **5.** Replace the disk and start the server.
- **6.** Configure the settings for the disk by the server with the replaced disk.
  - Reserve the data partition and the cluster partition for the mirror disk by using Disk
    Management (On the Start menu, point to Settings, and click Control Panel.
    Double-click Administrative Tools and then Computer Management, and click Disk
    Management.) Set the drive letters of the data partition and the cluster partition so that
    the drive letters of data partition and cluster partition and the size of data partitions are the
    same in both servers.
- 7. When the **Auto Mirror Recovery** is configured as **Off** in the **Auto Recovery** tab in **Cluster properties**, return the replaced server to the cluster from the WebManager.
- **8.** Stop group with mirror disk resource by using WebManager and suspend the cluster.
- 9. Start the Builder on line. If you have unchecked the **Auto Mirror Recovery** checkbox in procedure 3, check the **Auto Mirror Recovery** checkbox again.
- **10.** Select **Upload the Configuration File** from the **File** menu of the Builder to upload the cluster configuration data to the cluster.
- 11. Resume the cluster by using the WebManager.and start the group which has been stopped in step 8 with the server which has not been replaced disks.
- **12.** If the **Auto Mirror Recovery** checkbox is selected in cluster properties, full reconstruction of mirror will be performed. If not, it is required to perform the reconstruction manually.
- **13.** Move the group as necessary.

## Replacing FibreChannel HBA / SCSI controller

Follow the procedures below to replace HBA connecting the shared disk.

- 1. If the group is operating in the server where HBA is to be replaced (hereafter referred to as target server), move the group to another server.
- 2. Change the settings for the ExpressCluster Server service of the target server to manual start.
- 3. Shut down the target server to replace HBA.
- **4.** Start the target server with the disk cable disconnected.
- 5. Start the Builder online, open the properties of the target server and configure filter settings on the replaced HBA.
  - Click the **Connect** button in the HBA tab to acquire the disk configuration data of the target server and select the replaced HBA.
  - Do not change the settings other than above.
- **6.** Save the cluster configuration data in which HBA filter setting has been configured in Builder temporarily in the disk area accessible from the cluster server.
  - If the Builder is used on the cluster server, save the cluster configuration data in the local disk. Also, if the Builder is used on another PC, save it in the shared folder accessible from the cluster server, or save it temporarily in a floppy disk etc. and then copy it to the local disk of the cluster server.
- **7.** Execute the following command on one of the cluster servers to upload the saved cluster configuration data.
  - clpcfctrl --push -x < path\_of\_the\_cluster\_configuration\_information > --nocheck
- **8.** Shut down the target server and connect the disk cable.
- 9. Start the target server to check the drive letter in **Disk Management**. If the drive letter has been changed, set it as it was before. Restart the server to check that the drive letter is correctly configured.
- **10.** Start the Builder online and open the properties of the target server to check the settings for the **HBA** tab. If there is a partition which does not restrict access on the shared disk, check that the partition data is registered in **Partition excluded from cluster management**.
- 11. As with the steps 6 and 7 above, save the cluster configuration data temporarily and upload it from the cluster server with the following command:
  - clpcfctrl --push -x < path\_of\_the\_cluster\_configuration\_information > --nocheck
- **12.** Set the configuration for the ExpressCluster Server service of the target server back to automatic start, and reboot the target server.
- **13.** When **Auto Recovery** is configured as **Off** in **Properties** of the cluster, right-click the target server in WebManager to select **Recover**.
- 14. Migrate the group if necessary.

# Information required for inquiry

The following information is required for inquiring about the failure.

1. Failure

Describe the failure.

Example) Failover group (failover1) failed to fail over from server1 to server2.

- 2. Time that the failure occurred Example) 2006/01/01 00:00
- **3.** Name of the server with the failure Example) server2
- **4.** Version of ExpressCluster Example) ExpressCluster X 2.0
- 5. ExpressCluster log and event log of when the failure occurred Logs can be collected by using the WebManager or by running the log collection command. To use the WebManager, see Chapter 1, "Functions of the WebManager." To use the log collection command, see Chapter 4, "ExpressCluster command reference."

# **Chapter 12** Troubleshooting

This chapter provides instructions for troubleshooting problems with ExpressCluster. This chapter covers:

•	Troubleshooting	788
•	When the ExpressCluster system does not start or end	788
•	When activating or deactivating network partition resolution resource fails	789
•	When a network partition resolution resource error is detected	789
•	Network partition resolution resource becomes unavailable	789
•	When activating or deactivating group resources fails	790
•	When a monitor resource error occurs	790
•	When a heartbeat time-out occurs ·····	
•	Recovering from failure of one server	790
•	Recovering from failure of both servers	790
•	Recovering a suspended server (with unresolved network partition)	791
•	When network partitioning occurs ·····	792
•	Unavailable commands when interconnections are disconnected	795
•	Connecting mirror disks/hybrid disks manually	796
•	Normally connecting mirror disk when mirroring is available	796
•	Forcibly connecting mirror disk when mirroring is not available	796
•	Recovering from mirror breaks ·····	797
•	Automatically recovering from mirroring	797
•	Checking the mirror break status with a command	799
•	Checking the mirror recovery progress with a command	800
•	Recovering mirror with a command	800
•	Running the forcible mirror recovery with a command	802
•	Running the forcible mirror recovery with a command only on one server	803
•	Checking the mirror break status from the WebManager	804
•	Checking the mirror recovery progress from the WebManager	805
•	Recovering mirror using the WebManager	807
•	Running the forcible mirror recovery using the WebManager	
•	Running the forcible mirror recovery from the WebManager only on one server	809
•	Media sense function becomes invalid	809

## **Troubleshooting**

The following provides instructions for troubleshooting problems you experience in operating the ExpressCluster system.

### When the ExpressCluster system does not start or end

A cluster system starts working by restarting servers after installing ExpressCluster. If your cluster system does not behave properly, check the following:

1. Registration of cluster configuration data

The cluster configuration data should be registered with all servers (which will form a cluster system) when you cluster them. Make sure that the cluster configuration data is uploaded on all the servers.

For details, see Chapter 5, "Creating the cluster configuration data" in the *Installation and Configuration Guide* for registering the data.

2. Server names and IP addresses in the cluster configuration data

Check the server names and IP addresses are valid. (>hostname,>ipconfig...)

**3.** License registration

The license may not be registered yet. Run the license manager on all servers in the cluster to confirm that the license is registered:

If you are using the trial version license, confirm if it is not expired yet.

To run the license manager, select **ExpressCluster Server** from the **Start** menu, and then **License Manager**.

4. EXPRESSCLUSTER service

Start the service control manager of the OS, and make sure that the following ExpressCluster services have been started. If all of them have been started, ExpressCluster is running normally. To run the service control manager, from **Control Panel**, select **Administrative Tools** and select **Services**.

ExpressCluster

ExpressCluster Disk Agent

ExpressCluster Event

ExpressCluster Manager

ExpressCluster Old API Support

ExpressCluster Server

ExpressCluster Transaction

ExpressCluster Web Alert

**5.** Free disk space

Run [Disk Management] to check the size of the free disk space in the drive that contains <*ExpressCluster\_installation\_path>*. For details on the disk space to be used by ExpressCluster, see Chapter 3, "Installation requirements for ExpressCluster" in *Getting Started Guide*. To run Disk Management, select **Control Panel**, select **Administrative Tools**, and select **Computer Management**. Then from the icon tree, select **Services** under **Services and Applications**.

**6.** Usage of memory or OS resource

Run Task Manager of the OS to check the OS memory usage and CPU usage rate.

# When activating or deactivating network partition resolution resource fails

1. Majority method

Memory or OS resources may not be sufficient. Check them.

2. COM method

The cause may be one of the following:

- The specified device name (such as COM1 and COM2) may not exist in the system. Confirm that the device name specified by the Builder exists in the system.
- Other application may be using the device name specified by the Builder (such as COM1 and COM2). Check the device name.
- 3. PING method

Memory or OS resources may not be sufficient. Check them.

4. DISK method

The settings of the Builder are invalid. Check that the disk heartbeat partition is set to be filtered on the **HBA** tab of **Server Properties** of the server that failed to be activated or deactivated. Check that the disk heartbeat partition is not used by other resource (disk resource, mirror disk resource).

#### When a network partition resolution resource error is detected

1. Majority method

Memory or OS resources may not be sufficient. Check them.

COM method

Communication between the servers by the COM method cannot be performed. Confirm that the serial cable is connected to the device specified by the Builder properly.

3. PING method

There is no PING command response from the PING destination device. Check that there is no problem in the communication path from the cluster server to the PING destination device.

4. DISK method

Time-out occurred in accessing the disk heartbeat partition, or disconnection of the cable to the shared disk was detected.

If a time-out has occurred, select **Tuning** on the **Network Partition Resolution I/F** tab of **Tuning**. Select the disk network partition resolution resource with an error on the **Disk** tab of the **NP Resolution Tuning Properties** dialog, and adjust **IO Wait Time** from **Edit**.

If cable disconnection is detected, check the cable connection status.

## Network partition resolution resource becomes unavailable

A combination of network partition resolution resources is invalid. Refer to Chapter 9, "Details on network partition resolution resources" and change the settings by using the Builder.

#### When activating or deactivating group resources fails

If any error is detected in activation of a group resource, detailed error information is logged in the alert and event log. See "Detailed information in activating and deactivating group resources" and examine the logs to find the cause of the error and take appropriate action for it.

#### When a monitor resource error occurs

If a monitor resource detects any error, detailed information on error is logged in the alert and event logs. See "Detailed info of monitor resource errors" and examine the logs to find the cause of the error and take appropriate action for it.

#### When a heartbeat time-out occurs

Possible causes of heartbeat time-out between servers are listed below:

Cause	Solution
Disconnection of LAN cables	Check that you can send packets with the ping command.

### Recovering from failure of one server

If the automatic recovery mode is not set in **Cluster Properties**, the server that you have removed errors and restarted is in the **Suspension (Isolated)** status. To recover the server to the normally functioning cluster from this status, use the WebManager or the clpcl command.

If the Replicator is used, data between the disks that form a mirror set becomes inconsistent. However, by recovering the server, the mirror will be automatically rebuilt, and the data will become consistent.

To recover the server by the WebManager, see "Operating a cluster by using the WebManager" of Chapter 1, "Functions of the WebManager" of Section I of this guide.

To recover the server by the clpcl command, see "Operating the cluster" of Chapter 4, "ExpressCluster command reference" of Section I of this guide.

## Recovering from failure of both servers

When **Off** is selected for **Auto Return** on the **Auto Recovery** tab in **Cluster Properties**, when all the servers shut down by failures such as a hardware failure, after starting them up, they are removed from the cluster. Recover all the servers by using the WebManager or the clpcl command.

Right after recovering the servers, all the groups are stopped. Start all the groups. If the Replicator is used, the mirror will be automatically built again by starting the groups, and the data will become consistent.

# Recovering a suspended server (with unresolved network partition)

Since activating the same group is prevented on multiple servers, the group cannot be started. A server is suspended (with unresolved network partition) when all the conditions below are met.

- There are two or more network partition resolution resources of the DISK method.
- An error has occurred in the network partition resolution resource of the DISK method, and network partitioning cannot be resolved.
- Network partitioning or failure of a server occurred.

Perform the following steps to recover the suspended server.

- 1. If network partitioning occurred, recover all the heartbeat resources to the normal status. To check if the network partition has occurred, refer to "When network partitioning occurs."
- 2. Shut down the whole cluster by using the WebManager or the clpstdn command.
- 3. Start all the cluster servers.
- **4.** Recover the network partition resolution resource of the DISK method with an error. For how to recover, refer to "When a network partition resolution resource error is detected."
- 5. If a suspended server (rebooted after shutdown) exists, recover the server by using the WebManager and the clpcl command.

## When network partitioning occurs

Network partitioning indicates that all communication routes are blocked between servers. This section describes how you can check whether or not the network is partitioned and what you should do about it when the network partition resolution resource is not registered. The following examples assume that you have registered kernel mode LAN heartbeat resources for heartbeat resources in a 2-node cluster configuration.

When all heartbeat resources are normal (the network is not partitioned), the result of executing the clpstat command is:

## When you run the command on server1 # clpstat -n ========== HEARTBEAT RESOURCE STATUS ============= Cluster : cluster \*server0 : server1 server1 : server2 HB0 : lanhb1 HB1 : lanhb2 [on server0 : Online] HB server0 : o o server1 : o o [on server1 : Online] $_{ m HB}$ \_\_\_\_\_\_ server0 : o o server1 : o o When you run the command on server2 # clpstat -n ========= HEARTBEAT RESOURCE STATUS =========== Cluster : cluster server0 : server1 \*server1 : server2 HB0 : lanhb1 HB1 : lanhb2 [on server0 : Online] HB 0 1 \_\_\_\_\_\_ server0 : o o server1 : o o [on server1 : Online] server0 : o o server1 : o o

\_\_\_\_\_\_

When the network is partitioned, the result of executing the clostat command is what is described below. Both servers recognize each other that the counterpart is down.

#### When you run the command on server1 # clpstat -n ========== HEARTBEAT RESOURCE STATUS ============= Cluster : cluster \*server0 : server1 server1 : server2 HB0 : lanhb1 HB1: lanhb2 [on server0 : Online] $_{ m HB}$ 0 1 \_\_\_\_\_\_ server0 : o o server1 : x x [on server1 : Offline] HB 0 1 \_\_\_\_\_\_ server0 : - server1 : -\_\_\_\_\_\_ When you run the command on server2 # clpstat -n ======== HEARTBEAT RESOURCE STATUS =========== Cluster : cluster server0 : server1 \*server1 : server2 HB0 : lanhb1 HB1 : lanhb2 [on server0 : Offline] HB 0 1 \_\_\_\_\_\_ server0 : - server1 : -[on server1 : Online] HB 0 1 2

\_\_\_\_\_\_

\_\_\_\_\_\_

server0 : x x
server1 : o o

Shut down both servers immediately if the network is partitioned. Check the following for heartbeat resources.

- 1. Kernel mode LAN heartbeat resource
  - LAN cable status
  - Network interface status

If interconnection LAN is recovered from the network partitioning, ExpressCluster causes the servers to shut down.

If ExpressCluster detects that the same group is active on multiple servers, it causes the servers to shut down.

For the Replicator, depending on the server shutdown timing, the statuses of mirror disk resources may not be the same after rebooting the server.

Depending on the timing of server shutdown, the status of mirror disk resources may be the one requiring forced mirror recovery, mirror recovery, or normal.

## Unavailable commands when interconnections are disconnected

Commands for cluster construction											
Command	Description	Remarks									
clpcfctrl	Distributes the configuration information created by the Builder to the servers registered in the configuration information.	The configuration information cannot be distributed to other									
	Backs up the cluster configuration information to be used by the Builder.	servers.									
Commands for showing status											
Command	Description	Remarks									
clpstat	Displays the cluster status and settings information.	Statuses of other servers cannot be retrieved.									
Commands for cl											
Command	Description	Remarks									
clpcl	Starts, stops, suspends and resumes the ExpressCluster Server service.	Other servers cannot be operated, suspended or resumed.									
clpdown	Stops the ExpressCluster service and shuts down a server registered in the configuration information.	Other servers cannot be operated.									
clpstdn	Stops the ExpressCluster service in the entire cluster, and shuts down all servers.	Other servers cannot be operated.									
clpgrp	Starts, stops and moves groups.	Only groups on the local server can be stopped.									
clptoratio	Extends and displays time-out values of all servers in the cluster.	Time-out ratios of other servers cannot be set.									
Commands for lo											
Command	Description	Remarks									
clplogcc	Collects logs and OS information.	Logs of other servers cannot be collected.									
	irror (only for the Replicator / Replicator DR)										
Command	Description	Remarks									
clpmdstat	Displays the status and settings information of mirroring	The mirror status of the remote server cannot be retrieved.									
clpmdctrl	Activates/inactivates mirror disk resources and recovers mirroring.	Do not use this command since mirror disk resources of both servers may be activated.									
clphdsnapshot	Controls snapshot backup of hybrid disk resource.	This command cannot be used unless mirroring is successfully performed.									

## Connecting mirror disks/hybrid disks manually

This section describes how to cancel the access restriction for the data partition of mirror disk resource or hybrid disk resource when you cannot start ExpressCluster due to some sort of failure.

#### Normally connecting mirror disk when mirroring is available

When the ExpressCluster Server service can be activated while the ExpressCluster X Disk Agent service cannot be, access restriction can be cancelled by following the steps below.

1. Run the following command on the server where you want to connect disks.

For mirror disks:

```
clpmdctrl --active <mirror_disk_resource_name (Example: md1) >
For hybrid disks:
clphdctrl --active <hybrid disk resource name (Example: hd1) >
```


The mirror disk resource or hybrid disk resource becomes accessible. Written data is mirrored to the other server.


#### Forcibly connecting mirror disk when mirroring is not available

Follow the steps below to save data on mirror disks when both the ExpressCluster Server service and the ExpressCluster X Disk Agent service cannot be activated.

However, the mirroring status up to the moment just before both the ExpressCluster Server service and the ExpressCluster X Disk Agent service became unable to be activated must be normal, or you must know which server has the latest data.

1. Uninstall ExpressCluster from the server with the latest data, and restart the server.





2. Back up the data in the data partition on a DAT tape or other media.

As for hybrid disk resources, if the above is performed while another server in the same server group is using the shared disk, the data on the shared disk may be destroyed. Make sure to stop the other server or disconnect the disk cable of the other server when you perform the above.

#### Recovering from mirror breaks

When the auto-mirror recovery is enabled, no special operation is required. Mirroring is automatically recovered. However, if mirroring needs to be recovered forcibly, execution of a command or operations for forcible mirror recovery using the WebManager are required.

If the auto-mirror recovery is disabled, you have to recover mirroring by executing a command or using the WebManager.

The difference mirror recovery function is disabled and full copy is performed in the following cases:

- When the partition configuration for mirror disk resource or hybrid disk has been changed due to disk replacement etc.
- When both servers fail at the same time while mirror disk resource is normally activated
- When the current servers (servers updating and managing the disk in the server group) in the both server groups fail at the same time when the hybrid disk resource is normally activated
- When difference information could not be written successfully due to disk failure etc.

### **Automatically recovering from mirroring**

When the auto-mirror recovery is enabled, mirroring is automatically recovered under the following conditions:

- 1. Mirror disk resource or hybrid disk resource is active.
- **2.** The server where mirror disk resource or hybrid disk resource is activated contains the latest data.
- 3. Servers in the cluster are in the normal status, and you can verify their mirroring statuses.
- **4.** The data among the servers is not the same.
- **5.** In case of mirror disk, both the mirror disk monitor resource and the mirror disk connect monitor resource must operate normally on all the registered servers.

In case of hybrid disk, hybrid disk monitor resource must operate normally on a server that monitor target resource is activated.

- **6.** Resource is not activated on a server/server group that does not store the latest data.
- 7. **Auto Mirror Recovery Setting** in the cluster's properties must be checked. However, if the initial mirror configuration is yet to be set, the initial mirror configuration must be checked in accordance with the above indicated.
- **8.** Failures such as disk errors on the target disk of the mirror disk or hybrid disk are not occurring

The auto-mirror recovery is not performed if any of the following applies.

- One of the servers (for hybrid disk resource, all servers in one of the server groups) is not started.
- **2.** You cannot confirm the mirroring status of the other server.
- **3.** There is no server whose mirror status is normal.
- **4.** Mirror disk monitor resource or hybrid disk monitor resource is not registered.
- 5. Monitor resource is suspended or stopped in a server or server group that stores the latest data.
- **6.** Resource is forcibly activated in other server or server group, including when snap shot backup is being executed.

For information on how to verify the progress of recovering mirroring, see "Checking the mirror recovery progress with a command" on page 800 and "Checking the mirror recovery progress from the WebManager" on page 805.

#### Checking the mirror break status with a command

For mirror disk resources, run the following command to view the mirror break statuses.

clpmdstat --mirror <mirror\_disk\_resource\_name (Example: md1) >

You can view the mirror disk resource statuses by running the clpmdstat command.

#### 1. When normal:

Mirror Status: Normal

md1	server1	server2
Mirror Color	GREEN	GREEN

#### **2.** When the mirror recovery is required:

Mirror Status: Error

md1	server1	server2
Mirror Color	GREEN	RED
Lastupdate Time	2004/03/04 17:30:05	
Break Time	2004/03/04 17:30:05	
Disk Error	OK	OK
Difference Percent	1%	

#### **3.** When the forcible mirror recovery is required:

Mirror Status: Error

md1	server1	server2
Mirror Color	RED	RED
Lastupdate Time	2004/03/09 14:07:10	2004/03/09 13:41:34
Break Time	2004/03/09 14:06:21	2004/03/09 13:41:34
Disk Error	OK	OK
Difference Percent	1%	1%

#### **4.** While the mirroring is being recovered:

See "Checking the mirror recovery progress with a command" on page 800. For hybrid disk, execute the following command to check the mirror break status.

clphdstat --mirror <hybrid\_disk\_resource\_name (Example:hd1)>

For details, see "Hybrid disk status display command" in Chapter 4 ExpressCluster command reference.

Section III Maintenance information

#### Checking the mirror recovery progress with a command

For mirror disk resources, run the following command to view the progress of recovering mirroring.

clpmdstat --mirror <mirror disk resource name (Example: md1)>

You will see the following data while mirroring is being recovered.

Mirror Status: Recovering

md1 server1 server2

-----

Mirror Color YELLOW YELLOW

Recovery Status Value

-----

Status: Recovering

Direction: server1 -> server2

Percent: 7%

Used Time: 00:00:09
Remain Time: 00:01:59

You will see the following information when the mirror recovery is successfully completed.

Mirror Status: Normal

For hybrid disks, execute the following command to check the mirror break status.

clphdstat --mirror<hybrid\_disk\_resource\_name (Example: hd1) >

For details, see "Hybrid disk status display command" in Chapter 4 ExpressCluster command reference.

### Recovering mirror with a command

Run the following command to start the mirror recovery.

For mirror disk:

clpmdctrl --recovery <mirror\_disk\_resource\_name (Example: md1)>

When the mirror recovery can be performed, the difference data is used to recover the mirror.

This command immediately returns the control once the mirror recovery starts. For information on how to verify the mirror recovery progress, see "Checking the mirror recovery progress with a command" on page 800 and "Checking the mirror recovery progress from the WebManager" on page 805.

#### Running the forcible mirror recovery with a command

If ExpressCluster cannot determine which server contains the latest data, you have to run the forcible mirror recovery.

In this case, you have to manually identify the server that holds the latest data, and perform the forcible mirror recovery.

The difference mirror recovery function is disabled in the forcible mirror recover, and the data may be fully copied.

Identify the server that holds the latest data by any of the following means:

- Using Mirror Disk Helper of the WebManager
  - 1. Right-click the mirror disk resource or hybrid disk resource you want to check and select **Detail information** in the WebManager tree to start Mirror Disk Helper.
    - 2. Click Details.
    - 3. See the last update time stamp (Last Data Updated Time) to identify the server which has the latest data. However, this Last Data Updated Time depends on the operating system's clock.
- Using the clpmdstat / clphdstat command

Confirmation method is the same as Mirror Disk Helper of the WebManager except that you use a command.

1. Run the following command.

For mirror disks:

```
clpmdstat --mirror <mirror_disk_resource_name (Example: md1)>
```

For hybrid disks:

```
clphdstat --mirror <hybrid disk resource name(Example:hd1) >
```

- 2. See the last update time stamp (Last Data Updated Time) to identify the server which has the latest data. However, this Last Data Updated Time depends on the operating system's clock.
- Using data on disks

This method is not recommended because the data may be corrupted if anything goes wrong in the procedure. Perform the following steps on both servers to identify which has the latest data.

For mirror disks:

- 1. Confirm all groups are stopped.
  - **2.** Run the following command to connect the mirror disk resource.

```
clpmdopen <mirror disk resource name (Example: md1) >
```

- 3. Logically examine the data on the connection destination.
- **4.** Run the following command to disconnect the mirror disk resource.

```
clpmdclose <mirror disk resource name (Example: md1) >
```

For hybrid disks:

- 1. Confirm all groups are stopped.
- 2. Run the following command to connect the hybrid disk resource.

```
clphdctrl -active <hybrid_disk_resource_name (Example:hd1) > -f
```

- **3.** Logically examine the data on the connection destination.
- **4.** Run the following command to disconnect the hybrid disk resource.

```
clphdctrl -deactive <hybrid_disk_resource_name (Example:hd1) >
```

When you have identified the server holding the latest data, run the following command to start the forcible mirror recovery.

For mirror disks:

```
clpmdctrl --force <server_containing_the_latest_data>
<mirror_disk_resource_name (Example: md1)>
For hybrid disks (conducted on the server having the latest data):
clphdctrl --force <hybrid disk resource name (Example:hd1)>
```

The clpmdctrl / clphdctrl command immediately returns the control once the forcible mirror recovery starts. For information on how to check the forcible mirror recovery progress, see "Checking the mirror recovery progress with a command" on page 800 and "Checking the mirror recovery progress from the WebManager" on page 805.

When the forcible mirror recovery is successfully completed, activate the groups. The mirror disks become available.

# Running the forcible mirror recovery with a command only on one server

In some cases, you cannot start one of the servers due to a hardware or OS failure, and the server that can be started may not have the latest data. If you want to start applications at least on the server that can be started, you can perform the forcible mirror recovery on that server.

However, remember that if you do this, the data on the server where you run this command becomes the latest data no matter which server actually has it. Therefore, even if you are able to start the other server later, you cannot handle the data in that server as the latest one. Make sure you understand the consequence before running the following command.

For mirror disk resources, run the following command to start the forcible mirror recovery:

```
clpmdctrl --force <server_name> <mirror_disk_resource_name (Example:
md1)>
```

After running the command, you can activate the groups and use the mirror disks.

For hybrid disk resources, execute the following command on the target server to start forcible mirror recovery.

```
clphdctrl --force <hybrid disk resource name (Example:hd1) >
```

After executing the command, it becomes possible to start the group to use the hybrid disk.

#### Checking the mirror break status from the WebManager

You can see the mirror break status by starting Mirror Disk Helper from the WebManager.

• When normal:



• When mirror recovery is required:



• When forcible mirror recovery is required:





ExpressCluster X 2.1 for Windows Reference Guide

While mirror recovery is in progress:
 See "Checking the mirror recovery progress from the WebManager" on page 804.

#### Checking the mirror recovery progress from the WebManager

Start Mirror Disk Helper from the WebManager to view the mirror recovery progress. You will see the following screen during the mirror recovery.






You will see the following screen when the mirror recovery is successfully completed.

#### Recovering mirror using the WebManager

Start Mirror Disk Helper from the WebManager to start mirror recovery. Click the icon of the server that needs to be recovered. The icon will be changed as in the window below. Click **Execute** to start the mirror recovery processing.



When the difference mirror recovery can be performed, the recovery is done using the difference data. The difference mirror recovery takes less time than the forcible mirror recovery.

For information on how to check the mirror recovery progress, see "Checking the mirror recovery progress with a command" on page 800 and "Checking the mirror recovery progress from the WebManager" on page 805.

## Running the forcible mirror recovery using the WebManager

When ExpressCluster cannot determine which server has the latest data, you have to perform the forcible mirror recovery. In this case, you have to manually identify the server which holds the latest data, and perform the forcible mirror recovery.


The difference mirror recovery function is disabled in the forcible mirror recovery and the data may be fully copied.

Identify the server that has the latest data by any of the following methods:

- Using Mirror Disk Helper of the WebManager
  - 1. Right-click **Servers** in the WebManager tree to start the Mirror Disk Helper.
  - **2.** On the main screen of Mirror Disk Helper, display the detailed data of the mirror disk resources you want to see.
  - 3. Click the **Details** button.

**4.** See the last update time stamp (Last Data Updated Time) to identify the server which has the latest data. However, this Last Data Updated Time depends on the operating system's clock.

Select the icon of server containing the latest data. The icon will be changed as in the window below. Click **Execute** to start the mirror recovery processing.



For information on how to check the forcible mirror recovery progress, see "Checking the mirror recovery progress with a command" on page 800 and "Checking the mirror recovery progress from the WebManager" on page 805.


When the forcible mirror recovery is successfully completed, you can activate the groups and use the mirror disks.

# Running the forcible mirror recovery from the WebManager only on one server

In some cases, you cannot start one of the servers due to a hardware or OS failure, and the server that can be started may not have the latest data. If you want to start applications at least on the server that can be started, you can perform the forcible mirror recovery on that server.

However, remember that if you do this, the data on the server where you run this command becomes the latest data no matter which server actually has it. Therefore, even if the other server becomes available later, you cannot handle the data in that server as the latest one. Make sure you understand the consequence before running the following command.

Start the Mirror Disk Helper from the WebManager to start the forcible mirror recovery. Select the icon of the server, which you want to perform the forcible mirror recovery. The icon will be changed as follows. Click **Execute** to perform the forcible mirror recovery processing.



When the forcible mirror recovery is successfully completed, you can activate the groups and use the mirror disks.

## Media sense function becomes invalid

Media sense function is the OS function that detects disconnection of network cable. When disconnection is detected, TCP/IP receives a notification from the media sense function and renders the information such as an IP address assigned to the disconnected network card unavailable while it is disconnected. ExpressCluster cannot be operated properly if the information such as IP address becomes invalid during its operation, so the media sense function is rendered invalid when installing ExpressCluster.

# **Chapter 13** Error messages

This chapter provides information on error messages you might encounter in operating ExpressCluster. This chapter covers:

•	Messages ·····	812
•	Messages during setup	812
•	Messages reported by event log and alert	813
•	Driver event log messages-	835
•	Detailed information in activating and deactivating group resources	838
•	Detailed info of monitor resource errors	

# **Messages**

# **Messages during setup**

Module Type	Error Message	Solution
setup	Previous version of ExpressCluster is installed. Upgrading from this version is not supported. Install after uninstalling the previous version of ExpressCluster.	Uninstall the previous version of ExpressCluster, and then try installing again.
setup	The SNMP service is running. You need to stop the SNMP service before you perform uninstallation. Do you want to stop the SNMP service now?	Select <b>Yes</b> to stop the SNMP service automatically and continue the installation. Or, select <b>No</b> to cancel the installation, manually stop the SNMP service and then perform installation again.
setup	Setup has failed. Error code : xxx	- Check the system requirements, setup procedures and notes described in the manual, and make sure they are followed If other application is running, terminate it Install again after restarting the OS.
setup	Setup has failed(xxx). Error code : xxx Please reboot the system and try again.	<ul> <li>Check the system requirements, setup procedures and notes described in the manual, and make sure these requirements are followed.</li> <li>If other application is running, terminate it.</li> <li>Install again after starting the OS again.</li> </ul>
setup	Unsupported environment.	Install in the environment where the system requirements are met.
setup	Cannot perform uninstallation because there is one or more ExpressCluster services still running. Stop all ExpressCluster services before you restart uninstallation.	Stop all ExpressCluster services, and then perform uninstallation.
setup	Failed to start the installer. (errcode: xxx)	<ul> <li>Check the system requirements, setup procedures and notes described in the manual, and make sure they are followed.</li> <li>If other application is running, terminate it.</li> <li>The installer file may be corrupted or missing. Check it.</li> </ul>
setup	Internal error. (xxx)	- Check the system requirements, setup procedures and notes described in the manual, and make sure they are followed If other application is running, terminate it.

# Messages reported by event log and alert

These are the messages reported by applications, event logs, and alert viewer of the WebManager. Messages with • in the columns of Alert, Eventlog and Userlog are recorded in each log. The following shows how to refer the logs:

Log Name	How to refer	File Name
Alert	Output to the Alert Viewer of the WebManager. Logs can be collected by using the log collection tool.	alertlog.alt
Event log	Output to the Event Viewer (application log) of the OS. Collect logs by using the log collection tool. The source of the event is "ExpressCluster X." Logs can be collected by using the log collection tool. Note because they are collected in the binary format with the file names in the right column, it is necessary to open the files using Event Viewer in the environment where ExpressCluster is set up to refer to the information.	AppEvent.Evt SysEvent.Evt
User log	These are the logs with text format, in which detail information is recorded. They are output in the "userlog.00.log" file in the log folder of the logs collected by using the log collection tool.	userlog.00.log

Messages with ● in the Mailr Report column are reported when mail reporting of the alert service is configured.

"Report Settings" are settings of when linking to the ESMPRO Agent. In "Alive," the ESMPRO Agent performs the Alert report. In "Manager," alerts are output to the ESMPRO Agent. For details, see the manual of the ESMPRO Agent.

Module Type	Event Type	Event ID	Messages	Description	Solution	Alert	Event log	User log	Mail report	setting Alive	Report Manager
nm	Information	1	The server %1 has been started.	Server up	-	•	•				
nm	Information	2	The server %1 has been stopped.	Server down	Server down was detected. Remove the failures of the server and then return the server to the cluster.	•	•			•	•
nm	Information	3	The resource %2 of the server %1 has been started.	Resource up	-			•			
nm	Error	4	The resource %2 of the server %1 has an error.	Resource abnormally	An error of the resource was detected. Refer to the event logs of the appropriate resource.			•			
nm	Information	5	The resource %2 of the server %1 has been recovered to the normal status.	Resource recover	-			•			

Module	Event	Event				Ą	Eve	USI	Mail	setting	Report
Туре	Туре	ID	Messages	Description	Solution	Alert	Event log	User log	Mail report	Alive	Manager
nm	Error	6	The resource %2 of the server %1 is unknown.	Resource unknown	Check the cluster configuration data.	•	•				•
nm	Error	7	Network partition was detected. Shut down the server %1 to protect data.	Network partition	All heartbeat resources cannot be used. Check if an error has occurred in network adapter and the network is properly connected.	•	•			•	•
nm	Error	8	An error occurred while confirming the network partition. Shut down the server %1.	Can not network partition resolution	Refer to the event logs and check if an error has occurred in resource.	•	•			•	•
nm	Error	9	An error occurred in confirming the network partition. To avoid failover on multiple servers, the server %1 suspended failover.	Failover hold	Refer to the event logs and check if an error has occurred in resource.	•	•			•	•
nm	Information	10	The server %1 cancelled the pending failover.	Failover hold cancel	-	•	•				
nm	Error	11	Shut down the server %1. (reason:%2)	Server shutdown	All heartbeat resources cannot be used. Check if an error has occurred in network adapter and the network is properly connected.	•	•			•	•
nm	Error	12	Cluster service will be stopped. (reason:%1)	Cluster service stopping	Check the cause following the message.	•	•				•
nm	Warning	13	The combination of the network partition resources is invalid. (server name:%1)	NP resource combination error	Check the cluster configuration data.	•	•				•
nm	Error	14	The status of heartbeat %1 is abnormal.	Heartbeat abnormally	Check if an error has occurred in network adapter and the network is properly connected.	•	•			•	•
nm	Information	15	The heartbeat %1 has been recovered to the normal status.	Heartbeat recovered	-	•	•				
nm	Error	16	The network partition %2 of the server %1 has an error.	Network partition abnormally	Refer to the event logs and check if an error has occurred in resource.	•	•			•	•
nm	Information	17	been recovered to the normal status.	Network partition recovered	-	•	•				
nm	Error	18	Failed to start the resource %1. Server name:%2	Resource start failed	Refer to the event logs and check if an error has occurred in resource.	•	•			•	•
pm	Information	501	Cluster service has been started properly.	Cluster service started	-	•	•	•			
pm	Information	502	Cluster service is shutting down.	Cluster service shutting down	-	•	•	•			
pm	Information	503	Shutdown stall monitor has been started.	Shutting down stall monitor	-	•	•	•			
pm	Error	510	Cluster service has already been started.	Cluster service already started	Check the status of cluster service.	•	•	•			•
pm	Error	511	Fatal error has occurred in the cluster service.	Critical error in cluster service	The service is not run by a user with required privilege or the system may not be able to operate properly.	•	•	•	•		•

Module	Event	Event				Þ	Eve	User	Mail	setting	Report
Туре	Туре	ID	Messages	Description	Solution	Alert	Event log	er log	Mail report	Alive	Manager
pm	Error	512	An error is detected in xml library.	problem detected in xml library	The system may not be able to operate properly.	•	•	•			•
pm	Error	513	An error is detected in configuration file.	problem detected in configuration file	Check the cluster configuration data.	•	•	•	•		•
pm	Error	514	Configuration file does not exist.	Configuration file not exists	Upload the cluster configuration data.	•	•	•			•
pm	Error	515	My host name is not found in configuration file.	my name not found in configuration file	Check the cluster configuration data.	•	•	•			•
pm	Error	520	%1 process terminated abnormally.	process exit abnormally	The system may not be able to operate properly.	•	•	•	•		•
pm	Error	521	The cluster service process returned an error. (halting system)	Rc process exit with error	Deactivation of group resources may be failed. Troubleshoot by following the group resource message.	•	•	•			•
pm	Error	522	An error has occurred while initializing %1 process. (return code:%2)	process init error	Check the cause of an initialization error and troubleshoot it.	•	•	•	•		•
pm	Information	523	The system will be shut down.	system halting	-	•	•	•			
pm	Information	524	Cluster service will be stopped.	Cluster service stopping	-	•	•	•			
pm	Information	525	System will be rebooted.	System rebooting	-	•	•	•			
pm	Information	526	%1 process will be restarted.	Process restarting	-	•	•	•			
pm	Information	527	Emergency shutdown is in progress.	Emergency shutdown	-	•	•	•			
pm	Information	528	Generating STOP error.	Stop Error	-	•	•	•			
pm	Information	529	Generating hardware reset.	HW reset	-	•	•	•			
pm	Information	530	There was a request to shut down the system from the %1.	request of system halt	-	•	•	•			
pm	Information	531	There was a request to stop cluster service from the %1.	request of cluster service stop	-	•	•	•			
pm	Information	532	There was a request to reboot system from the %1.	request of system reboot	-	•	•	•			
pm	Information	533	There was a request to restart cluster service from the %1.	request of cluster service restart	-	•	•	•			
pm	Information	534	There was a request to resume cluster service from the %1.	request of cluster service resume	-	•	•	•			
pm	Information	535	There was a request to suspend cluster service from the %1.	request of cluster service suspend	-	•	•	•			
pm	Information	536	There was a request of emergency shutdown from the %1.	request of emergency shutdown	-	•	•	•			
pm	Information	537	There was a request to generate STOP error from the %1.	request of STOP error	-	•	•	•			
pm	Information	538	There was a request to generate hardware reset from ther %1.	request of HW reset	-	•	•	•			

Module Type	Event Type	Event ID	Messages	Description	Solution	Alert	Event log	User log	Mail report	setting Alive	Report Manager
			Poguacting shutdown to	chutdown request to the							백
pm	Information	540	Requesting shutdown to the automatic running control software.	shutdown request to the automatic running control software start	-	•	•	•			
pm	Information	541	Requesting shutdown (reboot) to the automatic running control software.	shutdown (reboot) request to the automatic running control software	-	•	•	•			
pm	Information	542	Shutdown request to the automatic running control software is completed.	shutdown request to the automatic running control software complete	-	•	•	•			
pm	Error	543	The automatic running control software returned an error to the shutdown request.	shutdown by ESMPRO/AC fail	The automatic operating settings may be incorrect. Check the settings.	•	•	•			•
pm	Error	544	Communications with the automatic running control software failed.	Communications with ESMPRO/AC fail	The system may not be able to operate properly.	•	•	•			•
rc	Information	1010	The group %1 is starting.	group-start started	-	•	•	•			
rc	Information	1011	The group %1 has been started.	group-start ended	-	•	•	•			
rc	Error	1012	Failed to start the group %1.	group-start failed	Troubleshoot according to the group resource message.	•	•	•			•
rc	Error	1019	Server %1 is not in a condition to start group %2.	cannot-start-group	Perform server recovery if the target server is suspended (Isolated). If it is suspended (Network Partition Unsolved), recover network partition resources to normal status.	•					
rc	Information	1020	The group %1 is stopping.	group-stop started	-	•	•	•			
rc	Information	1021	The group %1 has been stopped.	group-stop ended	-	•	•	•			
rc	Error	1022	Failed to stop the group %1.	group-stop failed	Troubleshoot according to the group resource message.	•	•	•			•
rc	Information	1030	The resource %1 is starting.	resource-start started	-		•	•			
rc	Information	1031	The resource %1 has been started.	resource-start ended	-		•	•			
rc	Error	1032	Failed to start the resource %1. (%2 : %3)	resource-start failed	Check the cause for failing to start the resource.	•	•	•	•		•
rc	Error	1033	Failed to start the recovery script of resource %1. (%2: %3)	recoverscript-start failed	Check the cause for failing to start the recovery script.	•	•	•			•
rc	Information	1040	The resource %1 is stopping.	resource-stop started	-		•	•			
rc	Information	1041	The resource %1 has been stopped.	resource-stop ended	-		•	•			
rc	Error	1042	Failed to stop the resource %1. (%2 : %3)	resource-stop failed	Check the cause for failing to stop the resource.	•	•	•	•		•
rc	Information	1050	Moving the group %1.	group-move started	-	•	•	•			
rc	Information	1051	The group %1 has been moved.	group-move ended	-	•	•	•			
rc	Error	1052	Failed to move the group %1.	group-move failed	Troubleshoot according to the group resource message.	•	•	•			•

Module	Event	Event		Possibility	Quinting.	Þ	Eve	User	Mail	setting	Report
Туре	Туре	ID	Messages	Description	Solution	Alert	Event log	er log	Mail report	Alive	Manager
rc	Error	1059	Server %1 is not in a condition to move group %2.	cannot-move-group	Perform server recovery if the target server is suspended (Isolated). If it is suspended (Network Partition Unsolved), recover network partition resources to normal status.	•					
rc	Information	1060	Failing over the group %1.	group-failover started	-	•	•	•			
rc	Information	1061	The group %1 has been failed over.	group-failover ended	-	•	•	•			
rc	Error	1062	Failed to fail over the group %1.	group-failover failed	Troubleshoot according to the group resource message.	•	•	•			•
rc	Information	1070	Restarting the group %1.	group-restart started	-	•	•	•			
rc	Information	1071	The group %1 has been restarted.	group-restart ended	-	•	•	•			
rc	Error	1072	Failed to restart the group %1.	group-restart failed	Troubleshoot according to the group resource message.	•	•	•			•
rc	Information	1080	Restarting the resource %1.	resource-restart started	-	•	•	•			
rc	Information	1081	The resource %1 has been restarted.	resource-restart ended	-	•	•	•			
rc	Error	1082	Failed to restart the resource %1.	resource-restart failed	Troubleshoot according to the group resource message.	•	•	•			•
rc	Information	1090	Shutting down the cluster.	cluster shutdown	-	•	•	•			
rc	Information	1091	Shutting down the server.	server shutdown	-	•	•	•			
rc	Error	1092	Group %1 is started on more than one server.	group double start	Server will automatically be shut down. Check the cause for the group to be started in more than one server.	•	•	•	•		•
rc	Error	1093	The system shutdown was performed by other than the cluster service.	system shutdown by other than cluster service	It is considered as an error if the system shuts down by other than cluster service. Follow the appropriate steps to shut down the system.	•	•	•			•
rc	Warning	1100	Shutdown count is reached the maximum number (%1). Final action of resource %2 was ignored.	shutdown count reached the limit	-	•	•	•	•		•
rc	Information	1110	Server %1 is returned to the cluster.	server returned	-	•	•	•			
rc	Information	1111	Server %1 is isolated from the cluster.	server isolated	-	•	•	•			
rc	Information	1112	Server %1 started to return to the cluster.	server return start	-	•	•	•			
rc	Error	1113	Server %1 failed to return to the cluster.	server return fail	The system may not be able to operate properly.	•	•	•			•
rc	Information	1120	Server %1 will notify the automatic running control software of shutdown start.	shutdown notification start	-	•	•	•			
rc	Error	1121	The automatic running control software returned an error to the shutdown start notification in server %1.	shutdown notification fail	The automatic operating settings may be incorrect. Check the settings.	•	•	•			•

Module Type	Event Type	Event ID	Messages	Description	Solution	Alert	Event log	User log	Mail report	setting Alive	Report Manager
rc	Information	1122	Server %1 notified the automatic running control software of shutdown start.	shutdown notification finish	-	•	•	•			
rc	Information	1123	The automatic running control software is checking the power status of shared disks. A server will be restarted after the power status is checked.	waiting for disk power-on	-	•	•	•			
rc	Error	1124	An error was returned from the automatic running control software. Failed to check the power status of shared disks.	disk power-on confirmation failed	The automatic operating settings may be incorrect. Check the settings. An error may have occurred in the automatic power control unit. Check the automatic power control unit.	•	•	•			•
rc	Error	1125	Server %1 failed to communicate with the automatic running control software.	communications with the automatic running control software failed	The system may not be able to operate properly.	•	•	•			•
rc	Information	1130	Starting a single resource %1.	single-resource-start started	-	•	•	•			
rc	Information	1131	A single resource %1 has been started.	single-resource-start ended	-	•	•	•			
rc	Error	1132	Failed to start a single resource %1.	single-resource-start failed	Troubleshoot according to the group resource message.	•	•	•			•
rc	Error	1139	Server %1 is not in a condition to start a single resource %2.	cannot-start-single-resou rce	Perform server recovery if the target server is suspended (Isolated). If it is suspended (Network Partition Unsolved), recover network partition resources to normal status.	•					
rc	Information	1140	Stopping a single resource %1.	single-resource-stop started	-	•	•	•			
rc	Information	1141	A single resource %1 has been stopped.	single-resource-stop ended	-	•	•	•			
rc	Error	1142	Failed to stop a single resource %1.	single-resource-stop failed	Troubleshoot according to the group resource message.	•	•	•			•
rc	Information	1200	The resource %1 will be restarted since starting the resource %2 failed.	resource-restart by resource-acterr	-	•	•	•			
rc	Information	1201	The group %1 will be failed over to server %2 since starting the resource %3 failed.	group-failover by resource-acterr	-	•	•	•			
rc	Information	1202	The group %1 will be stopped since starting the resource %2 failed.	group-stop by resource-acterr	-	•	•	•			
rc	Information	1203	The cluster service will be stopped since starting the resource %1 failed.	service-stop by resource-acterr	-	•	•	•			
rc	Information	1204	The system will be shut down since starting the resource %1 failed.	shutdown-system by resource-acterr	-	•	•	•			

Module Type	Event Type	Event ID	Messages	Description	Solution	Alert	Event log	User log	Mail report	setting Alive	Report Manager
rc	Information	1205	The system will be rebooted since starting the resource %1 failed.	reboot-system by resource-acterr	-	•	•	•			
rc	Information	1220	The resource %1 will be stopped again since stopping the resource %2 failed.	resource-stop retry by resource-deacterr	-	•	•	•			
rc	Information	1223	The cluster service will be stopped since stopping the resource %1 failed.	service-stop by resource-deacterr	-	•	•	•			
rc	Information	1224	The system will be shut down since stopping the resource %1 failed.	shutdown-system by resource-deacterr	-	•	•	•			
rc	Information	1225	The system will be rebooted since stopping the resource %1 failed.	reboot-system by resource-deacterr	-	•	•	•			
rc	Information	1241	Hardware reset will be generated since starting the resource %1 failed.	hw-reset by resource-acterr	-	•	•	•			
rc	Information	1242	STOP error will be generated since starting the resource %1 failed.	stop-error by resource-acterr	-	•	•	•			
rc	Information	1281	Hardware reset will be generated since stopping the resource %1 failed.	hw-reset by resource-deacterr	-	•	•	•			
rc	Information	1282	STOP error will be generated since stopping the resource %1 failed.	stop-error by resource-deacterr	-	•	•	•			
rc	Information	1300	Script before final action upon activation failure in resource %1 started.	Script before final action upon resource activation failure started.	-	•	•	•			
rc	Information	1301	upon activation failure in	Script before final action upon resource activation failure completed.	-	•	•	•			
rc	Information	1302	Script before final action upon deactivation failure in resource %1 started.	Script before final action upon resource deactivation failure started.	-	•	•	•			
rc	Information	1303	Script before final action upon deactivation failure in resource %1 completed.	Script before final action upon resource deactivation failure completed.	-	•	•	•			
rc	Information	1304	Script before activation in resource %1 started.	Script before resource activation started.	-	•	•	•			
rc	Information	1305	Script before activation in resource %1 completed.	Script before resource activation completed.	-	•	•	•			
rc	Information	1306	Script after activation in resource %1 started.	Script after resource activation started.	-	•	•	•			
rc	Information	1307	Script after activation in resource %1 completed.	Script after resource activation completed.	-	•	•	•			
rc	Information	1308	Script before deactivation in resource %1 started.	Script before resource deactivation started.	-	•	•	•			

Module	Event	Event		B	O.L.C.	Þ	Eve	User	Mail	setting	Report
Туре	Туре	ID	Messages	Description	Solution	Alert	Event log	er log	Mail report	Alive	Manager
rc	Information	1309	Script before deactivation in resource %1 completed.	Script before resource deactivation completed.	-	•	•	•			
rc	Information	1310	Script after deactivation in resource %1 started.	Script after resource deactivation started.	-	•	•	•			
rc	Information	1311	Script after deactivation in resource %1 completed.	Script after resource deactivation completed.	-	•	•	•			
rc	Error	1340	Script before final action upon activation failure in resource %1 failed.	Check the cause of the script failure and take measures.	Check the cause of the script failure and take measures.	•	•	•			•
rc	Error	1341	Script before final action upon deactivation failure in resource %1 failed.	Check the cause of the script failure and take measures.	Check the cause of the script failure and take measures.	•	•	•			•
rc	Error	1342	Failed to execute script before activation in resource %1.	Check the cause of the script failure and take measures.	Check the cause of the script failure and take measures.	•	•	•			•
rc	Error	1343	Failed to execute script after activation in resource %1.	Check the cause of the script failure and take measures.	Check the cause of the script failure and take measures.	•	•	•			•
rc	Error	1344	Failed to execute script before deactivation in resource %1.	Check the cause of the script failure and take measures.	Check the cause of the script failure and take measures.	•	•	•			•
rc	Error	1345	Failed to execute script after deactivation in resource %1.	Check the cause of the script failure and take measures.	Check the cause of the script failure and take measures.	•	•	•			•
rc	Information	1400	Forced stop (BMC Power Off) of server %1 has been requested.	forced-stop (bmc-poweroff) requested	-			•			
rc	Information	1401	Forced stop (BMC Power Cycle) of server %1 has been requested.	forced-stop (bmc-powercycle) requested	-			•			
rc	Information	1402	Forced stop (BMC Reset) of server %1 has been requested.	forced-stop (bmc-reset) requested	-			•			
rc	Information	1403	Forced stop (BMC NMI) of server %1 has been requested.	forced-stop (bmc-nmi) requested	-			•			
rc	Error	1420	Forced stop (BMC Power Off) of server %1 failed.	forced-stop (bmc-poweroff) failed	The system may not be able to operate properly.	•	•	•			•
rc	Error	1421	Forced stop (BMC Power Cycle) of server %1 failed.	forced-stop (bmc-powercycle) failed	The system may not be able to operate properly.	•	•	•			•
rc	Error	1422	Forced stop (BMC Reset) of server %1 failed.	forced-stop (bmc-reset) failed	The system may not be able to operate properly.	•	•	•			•
rc	Error	1423	Forced stop (BMC NMI) of server %1 failed.	forced-stop (bmc-nmi) failed	The system may not be able to operate properly.	•	•	•			•
rc	Information	1440	The CPU frequency has been set to high.	The CPU frequency has been set to high.	-	•	•	•			
rc	Information	1441	The CPU frequency has been set to low.	The CPU frequency has been set to low.	-	•	•	•			
rc	Information	1442	The CPU frequency has been set to %1.	The CPU frequency has been set.		•	•	•		_	
rc	Information	1443	CPU frequency setting has been switched to automatic control by cluster.	CPU frequency setting has been switched to automatic control by cluster.	-	•	•	•			

Module	Event	Event	Messages	Description	Solution	Alert	Event log	User	Mail report	setting	Report
Туре	Туре	ID		·		ert	ıt log	· log	eport	Alive	Manager
rc	Error	1460	CPU frequency control cannot be used.	CPU frequency control cannot be used.	Check BIOS settings and kernel settings.	•	•	•			•
rc	Error	1461	Failed to set the CPU frequency to high.	Setting the CPU frequency to high has failed.	Check BIOS settings and kernel settings. Check if the cluster service is started. Check if the configuration is set so that CPU frequency control is used.	•	•	•			•
rc	Error	1462	Failed to set the CPU frequency to low.	Setting the CPU frequency to low has failed.	Check BIOS settings and kernel settings. Check if the cluster service is started. Check if the configuration is set so that CPU frequency control is used.	•	•	•			•
rc	Error	1463	Failed to set the CPU frequency to %1.	Setting the CPU frequency has failed.	Check BIOS settings and kernel settings. Check if the cluster service is started. Check if the configuration is set so that CPU frequency control is used.	•	•	•			•
rc	Error	1464	Failed to switch the CPU frequency setting to automatic control by cluster.	Switching the CPU frequency setting to automatic control by cluster has failed.	Check if the cluster service is started. Check if the configuration is set so that CPU frequency control is used.	•	•	•			•
rm	Information	1501	Monitor %1 has been started.	Monitor start	-	•	•	•			
rm	Information	1502	Monitor %1 has been stopped.	Monitor stop	-	•	•	•			
rm	Information	1503	Monitor %1 does not monitor in this server.	Not target server	-	•	•	•			
rm	Warning	1504	Monitor %1 is in the warning status. (%2 : %3)	Monitor warn	Check the cause of Warning.	•	•	•			•
rm	Warning	1505	The number of monitor resources reached the maximum number. (registered resource: %1)	invalid number of monitor resource	Check the cluster configuration data.	•	•	•			•
rm	Warning	1506	Configuration of %1 is invalid. (%2 : %3)	invalid monitor resource	Check the cluster configuration data.	•	•	•			•
rm	Error	1507	Failed to start monitor %1.	monitor starting failed	The system may not be able to operate properly.	•	•	•	•		•
rm	Error	1508	Failed to stop monitor %1.	monitor stopping failed	The system may not be able to operate properly.	•	•	•			•
rm	Error	1509	Monitor %1 detected an error. (%2 : %3)	monitor failed	Check the cause for monitor error.	•	•	•	•		•
rm	Information	1510	Monitor %1 is not monitored.	not monitored	-	•	•	•			
rm	Information	1511	Monitor resource has not been registered.	unregistered monitor resource	-	•	•	•			
rm	Information	1512	%1 was stopped for failure in monitor %2.	relation stop	-	•	•	•			
rm	Information	1513	%1 was restarted for failure in monitor %2.	relation restart	-	•	•	•			
rm	Information	1514	%1 was failed over for failure in monitor %2.	relation group failover	-	•	•	•			
rm	Information	1515	There was a request to stop cluster for failure in monitor %1.	cluster stop	-	•	•	•			

Module	Event	Event		2		A	Eve	User	Mail	setting	Report
Туре	Туре	ID	Messages	Description	Solution	Alert	Event log	er log	Mail report	Alive	Manager
rm	Information	1516	There was a request to shut down the system for failure in monitor %1.	system shutdown	-	•	•	•			
rm	Information	1517	There was a request to restart the system for failure in monitor %1.	system reboot	-	•	•	•			
rm	Error	1518	Failed to stop %1 due to error detection of %2.	relation stop failure	Check the status of resources.	•	•	•			•
rm	Error	1519	Failed to restart %1 due to error detection of %2.	relation restart failure	Check the status of resources.	•	•	•			•
rm	Error	1520	Failed to fail over %1 due to error detection of %2.	relation group failover failure	Check the status of resources.	•	•	•			•
rm	Error	1521	Failed to stop the cluster due to error detection of %1.	cluster stop failure	The system may not be able to operate properly.	•	•	•			•
rm	Error	1522	Failed to shut down the system due to error detection of %1.	os shutdown failure	The system may not be able to operate properly.	•	•	•			•
rm	Error	1523	Failed to restart the system due to error detection of %1.	os reboot failure	The system may not be able to operate properly.	•	•	•			•
rm	Error	1524	The group of monitor %1 is unknown.	unknown group	Check the cluster configuration data.	•	•	•			•
rm	Warning	1525	No action is taken because %1 is not online.	not perform failure action	-	•	•	•			•
rm	Information	1526	Status of monitor %1 was returned to normal.	status changed into normal	-	•	•	•			
rm	Information	1527	Status of monitor %1 was changed into unknown.	status changed into unknown	The system may not be able to operate properly.	•	•	•			
rm	Error	1528	Initialization error has occurred (%1 : %2)	process initialize error	The system may not be able to operate properly.	•	•	•			•
rm	Information	1529	Monitor %1 was suspended.	suspend (single monitor)	-	•	•	•			
rm	Information	1530	Monitor %1 was resumed.	resume (single monitor)	-	•	•	•			
rm	Information	1531	All monitors were suspended.	suspend (all monitors)	-	•	•	•			
rm	Information	1532	All monitors were resumed.	resume (all monitors)	-	•	•	•			
rm	Information	1533	The polling interval of monitor %1 was changed into %2*%3.	change polling interval (single monitor)	-	•	•	•			
rm	Information	1534	The polling interval ratio of all monitors were changed into %1.	change polling interval (all monitors)	-	•	•	•			
rm	Information	1535	Causing intentional stop error was required because an error is detected by %1.	intentional panic	-	•	•	•			
rm	Error	1536	Causing intentional stop error has failed because an error is detected by %1.	intentional panic failure	The system may not be able to operate properly.	•	•	•			•

Module Type	Event Type	Event ID	Messages	Description	Solution	Alert	Event log	User log	Mail report	setting Alive	Report Manager
rm	Warning	1537	Recovery will not be executed since server is suspending.	not recovery(server suspending)	Monitor resource is not recovered if the server is suspended (Network Partition Unsolved). Check the cause for being suspended (Network Partition Unsolved) and recover network partition resources to normal status.	•	•	•			•
rm	Warning	1571	Monitor %1 was delayed. (timeout=%2, response time=%3, rate=%4)	monitor delayed	Check the load on the server where monitoring delay was detected and reduce the load. Set longer time-out if the monitoring time-out is detected.	•	•	•			•
rm	Warning	1600	Shutdown count reached the maximum number (%1). Final action of monitor %2 was ignored.	reached OS shutdown limit	-	•	•	•	•		•
rm	Information	1700	Script before final action upon failure in %1 monitor resource started.	Script before final action upon monitor resource failure started.	-	•	•	•			
rm	Information	1701	Script before final action upon failure in %1 monitor resource completed.	Script before final action upon monitor resource failure completed.	-	•	•	•			
rm	Information	1720	Script before final action upon failure in %1 monitor resource failed.	Script before final action upon monitor resource failure has failed.	-	•	•	•			
diskagent	Information	2001	%1 service was started.	Start service	-		•	•			
diskagent	Information	2002	%1 service was stopped.	Stop service	-		•	•			
diskagent	Warning	2030	%1 service was not stopped successfully due to stop time-out or other errors of the internal threads.	Fail to stop service	The system may not be able to operate properly.	•	•	•			•
diskagent	Error	2050	%1 service was not started successfully because the specified parameter was invalid. Confirm the cluster configuration data.	Fail to start service	Check the cluster configuration data.	•	•	•			•
diskagent	Error	2051	%1 service was not started because obtaining the policy data failed. Check the data.	Fail to start service	Check the policy file.	•	•	•			•
diskagent	Error	2052	%1 service was not started successfully because dispatching to service manager failed. System may be unable to operate correctly.	Fail to start service	The system may not be able to operate properly.	•	•	•			•
diskagent	Error	2053	%1 service was not started successfully because creating and loading internal resources failed. System may be unable to operate correctly.	Fail to start service	System may be unable to operate correctly.	•	•	•			•

Module Type	Event Type	Event ID	Messages	Description	Solution	Alert	Event log	User log	Mail report	setting	
							g	ğ	ort	Alive	Manager
diskagent	Error	2054	%1 service was not started successfully because initialization of shared disk or mirror disk library failed at termination code %2. System may be unable to operate correctly.	Fail to start service	The system may not be able to operate properly.	•	•	•			•
diskagent	Error	2055	%1 service was not started successfully because creating communication socket failed. System may be unable to operate correctly.	Fail to start service	The system may not be able to operate properly.	•	•	•			•
diskagent	Error	2056	%1 service was not started successfully because creating internal threads failed. System may be unable to operate successfully.	Fail to start service	The system may not be able to operate properly.	•	•	•			•
diskagent	Error	2057	%1 service was not started because it may be stopped or forcibly stopped last time when it was started. Reboot the server.	Fail to start service	Reboot the server.	•	•	•			•
diskagent	Error	2090	%1 service failed to reload cluster configuration data. System may be unable to operate correctly. The own server will be shut down.	Server shutdown	The system may not be able to operate properly.	•	•	•			•
diskagent	Error	2099	%1 service was not started successfully because the other internal error occurred. System may be unable to operate correctly.	Fail to start service	The system may not be able to operate properly.	•	•	•			•
event	Information	2101	%1 service has been started.	Start service	-		•				
event	Information	2102	%1 service has been stopped.	Stop service	-		•				
event	Warning	2130	Time-out or other error has occurred while waiting for internal threads to stop. Detected internal error %1.	Threads were timeout	The system may not be able to operate properly.	•	•				•
event	Error	2150	The specified parameters are invalid. Check the cluster configuration data.	Invalid configuration	Check the cluster configuration data.	•	•				•
event	Error	2151	Failed to obtain the policy data. Check the data.	Invalid configuration	Check the policy file.	•	•				•

event Error 2152 Failed to obtain the registry data. System may be unable to operate correctly.  Error 2153 Failed to obtain the registry data. System may be unable to operate correctly.  Failed to dispatch to the service manager. System may be unable to operate correctly.  Failed to create an internal resource.  Failed to resource The system may not be able to operate to create an internal resource.  The system may not be able to operate properly.	Alert • •	Event log • •	User log	Mail report	Alive	Manager •
event Error 2152 registry data. System may be unable to operate correctly.  Failed to read registry operate properly.  Failed to read registry operate properly.  Failed to read registry operate properly.  The system may not be able to operate properly.  The system may not be able to operate properly.  The system may not be able to operate properly.  Failed to create an internal resource.  Failed to resource The system may not be able to	•	•				•
event Error 2153 service manager. System may be unable to operate correctly.  Failed to create an internal resource.  Service manager. Dispatch failed operate properly.  The system may not be able to operate properly.  The system may not be able to operate properly.	•	•				
event Error 2154 internal resource. failed to resource The system may not be able to	•	•				•
to operate correctly.						•
event Error 2155 Failed to create communication sockets. System may be unable to operate correctly.  Failed to create communication sockets. System may be unable to operate correctly.  The system may not be able to operate properly.	•	•				•
event Error 2156 Failed to control the shared memory. System may be unable to operate correctly. The system may not be able to operate properly.	•	•				•
may be unable to operate properly. operate correctly.	•	•				•
event Error 2199 Other internal error has occurred. System may be unable to operate correctly.  Other internal error has occurred. System may be unable to operate correctly.  The system may not be able to operate properly.	•	•				•
mdadmn Information 2401 Full Recovery of mirror disk %1 started. Full Recovery of mirror disk started	•	•	•			
successfully.	•	•	•			
mdadmn Information 2403 Full Recovery of mirror disk %1 was canceled. Full Recovery of mirror disk was canceled.	•	•	•			
mdadmn Error 2404 Full Recovery of mirror disk %1 failed. Full Recovery of mirror disk failed. Check that there is no error in the disk and network adapter and the network is correctly connected.	•	•	•		•	•
mdadmn Information 2405 Fast Recovery of mirror disk %1 started. Fast Recovery of mirror disk started	•	•	•			
mdadmn Information 2406 Fast Recovery of mirror disk %1 finished successfully. Fast Recovery of mirror disk succeeded	•	•	•			
mdadmn Information 2407 Fast Recovery of mirror disk %1 was canceled. Fast Recovery of mirror disk was canceled.	•	•	•			
Check that there is no error in Fast Recovery of mirror Fast Recovery of mirror the disk and network adapter	•	•	•		•	•
disk %1. Check if the disk is being retried. being used.	•	•	•			•
mdadmn Information 2412 Mirror disk %1 was mirror disk was forcibly disconnected.	•	•	•			

Module	Event	Event	Messages	Description	Solution	Ą	Event log	User	Mail	setting	Report
Type	Туре	ID	incooliges	Beschiphen	Condition	Alert	it log	r log	Mail report	Alive	Manager
mdadmn	Error	2421	The mirror connect of the mirror disk %1 has been disconnected.	Mirror connect error.	Check that there is no error in the network adapter and the network is correctly connected.	•	•	•			•
mdadmn	Error	2422	A data partition error occurred in the mirror disk %1.	mirror disk abnormal	Replace the server disk.	•	•	•		•	•
mdadmn	Error	2423	A cluster partition error occurred in the mirror disk %1.	Disk error	Replace the server disk.	•	•	•		•	•
mdadmn	Error	2431	Failed to initialize the mirror connect.	Mirror connection initialization failed.	Check that there is no error in the network adapter and the network is correctly connected.	•	•	•		•	•
mdadmn	Error	2432	Failed to initialize the mirror disk %1.	Mirror disk initialization failed.	Check the partition exists and the disk is recognized by the operating system.	•	•	•		•	•
mdadmn	Error	2433	Failed to initialize the mirror disk %1. The cluster partition and the data partition must be different partitions.	Mirror disk initialization failed.	Check the cluster configuration data.	•	•	•			•
mdadmn	Error	2434	Failed to initialize the mirror disk %1. The area in the cluster partition has been used by another mirror disk.	Mirror disk initialization failed.	Check the cluster configuration data.	•	•	•			•
mdadmn	Error	2435	Failed to initialize the mirror disk %1. The partition specified for the cluster partition has been used as the data partition of another mirror disk.	Mirror disk initialization failed.	Check the cluster configuration data.	•	•	•			•
mdadmn	Error	2436	Failed to initialize the mirror disk %1. The partition specified for the data partition has been used by another mirror disk.	Mirror disk initialization failed.	Check the cluster configuration data.	•	•	•			•
mdadmn	Error	2440	Connecting mirror disk %1 has failed.	Connecting mirror disk failed.	Check the partition exists and the disk is recognized by the operating system.		•			•	•
mdadmn	Error	2441	Disconnecting mirror disk %1 has failed.	Disconnecting mirror disk failed.	Check if the mirror disk is being used.		•				•
lankhb	Error	2851	Keep-alive timeout was detected on the server %1.	Keep-alive timeout	There is a server where keep-alive timeout is detected. Check the server error.	•	•				•
fip	Error	2901	IP address already exists. (IP=%1)	address duplication	-	•	•	•			
fip	Information	2902	IP address will be activated forcibly. (IP=%1)	address force activation	-	•	•	•			
vip	Error	3051	IP address already exists. (IP=%1)	address duplication	-	•	•	•			
vip	Information	3052	IP address will be activated forcibly. (IP=%1)	address force activation	-	•	•	•			

Module Type	Event Type	Event ID	Messages	Description	Solution	Alert	Event log	User log	Mail report	setting Alive	Report Manager
sdfunc	Warning	3201	Trying again to disconnect disk %1. Check if the disk is being used.	Retry disk disconnection	Check if the disk is being used.	•	•	•			•
sdfunc	Information	3202	Disk %1 was forcibly disconnected.	Disconnect disk forcibly	-	•	•	•			
sdfunc	Warning	3203	Updated configuration data was not reflected properly. Update the configuration data again after modifying the configuration settings.	Fail to update configuration	Check the cluster configuration data.	•	•	•			•
sdfunc	Warning	3204	The server %1 is not found in the configuration data. Check the server name of the configuration data.	Fail to detect server name	Check the cluster configuration data.	•	•	•			•
sdfunc	Information	3205	Detected disk resources that have not been identified. Disk reidentification will be executed.	Execute disk reconfirmation	-	•	•	•			
sdfunc	Information	3206	Reidentification of the disk has finished.	Finish disk reconfirmation	-	•	•	•			
sdfunc	Error	3207	Connecting disk %1 has failed.	Fail to connect disk	Check if the partition is allocated and the disk is being recognized by operating system.		•			•	•
sdfunc	Error	3208	Disconnecting disk %1 has failed.	Fail to disconnect disk	Check if the disk is being used.		•				•
disknp	Warning	3251	Timeout has occurred in read/write to the partition for disk heartbeat. Check the connection status of partition for disk heartbeat.	Disk heart beat timeout	Check if an error has occurred in the disk and it is properly connected.	•	•	•		•	•
disknp	Information	3252	Recovered from the timeout occurred in read/write to the partition for disk heartbeat.	Recover from disk heartbeat timeout	-	•	•	•			
disknp	Error	3257	Disconnection monitoring(%1) among the shared disk and the servers could not be started. The system may not be able to operate properly.	Fail to start monitoring	The system may not be able to operate properly.	•	•	•			•
ptun	Warning	3301	The parameter (%1) exceeded the threshold (%2 p.c.). Timeout value=%3(sec) Data=%4(sec)	Delay warning	The parameter exceeded the threshold. Set an appropriate value to the parameter.	•	•	•			•

Module Type	Event Type	Event ID	Messages	Description	Solution	Alert	Event log	User log	Mail report	setting Alive	Report Manager
armcmd	Error	3501	ARMLOAD detected that the application (watchID=%2) of the group %1 has stopped. The number of failovers has reached the maximum count. Check what has caused the application to stop.	Application stopped	Check the cause for application to be stopped.	•	•				•
armcmd	Error	3502	ARMLOAD detected that the application (watchID=%2) of the group %1 has stopped. Script will be restarted. Check what has caused the application to stop.	Application stopped	Check the cause for application to be stopped.	•	•				•
armcmd	Error	3503	ARMLOAD detected that the application (watchID=%2) of the group %1 has stopped. The application will be restarted. Check what has caused the application to stop.	Application stopped	Check the cause for application to be stopped.	•	•				•
armcmd	Error	3504	ARMLOAD detected that the application (watchID=%2) of the group %1 has stopped. Group will be failed over. Check what has caused the application to stop.	Application stopped	Check the cause for application to be stopped.	•	•				•
armcmd	Error	3505	ARMLOAD detected that the application (watchID=%2) of the group %1has stopped. The server will shut down. Check what has caused the application to stop.	Application stopped	Check the cause for application to be stopped.	•	•				•
armcmd	Error	3506	ARMLOAD detected that the service (watchID=%2) of the group %1 has stopped. The number of failovers has reached the maximum count. Check what has caused the application to stop.	Service stopped	Check the cause for service to be stopped.	•	•				•
armcmd	Error	3507	ARMLOAD detected that the service (watchID=%2) of the group %1 has stopped. Script will be restarted. Check what has caused the application to stop.	Service stopped	Check the cause for service to be stopped.	•	•				•

Module Type	Event Type	Event ID	Messages	Description	Solution	Alert	Event log	User log	Mail report	setting Alive	Report Manager
										е	ger
armcmd	Error	3508	ARMLOAD detected that the service (watchID=%2) of the group %1 has stopped. The service will be restarted. Check what has caused the application to stop.	Service stopped	Check the cause for service to be stopped.	•	•				•
armcmd	Error	3509	ARMLOAD detected that the service (watchID=%2) of the group %1 has stopped. The group will be failed over. Check what has caused the application to stop.	Service stopped	Check the cause for service to be stopped.	•	•				•
armcmd	Error	3510	ARMLOAD detected that the service (watchID=%2) of the group %1 has stopped. The server will shut down. Check what has caused the application to stop.	Service stopped	Check the cause for service to be stopped.	•	•				•
armcmd	Error	3513	An error occurred in command %1. Shut down the server.	Command error	The system may not be able to operate properly.	•	•				•
armcmd	Warning	3514	An abnormal connection to the shared name (%1) has been detected.	Share-name abnormally	The shared name cannot be used. Recover the devices that correspond to the shared name. (1) OS is unstable. Check the OS status. (2) Check if the power is supplied to the appropriate devices. (3) Check if the appropriate devices and the servers are connected properly.	•	•				•
armcmd	Information	3515	Connection to the shared name (%1) has been recovered.	Share-name recovered	-	•	•				
armcmd	Warning	3516	Failed to start the application (WID=%2) of the group %1.	Application failed	Check the cause for failing to start the application.	•	•				•
armcmd	Information	3517	The application (WID=%2) of the group %1 has restarted.	Application restarted	-	•	•				
armcmd	Warning	3518	group %1.	Service failed	Check the cause for failing to start the service.	•	•				•
armcmd	Information	3519	The service (WID=%2) of the group %1 has restarted.	Service restarted	-	•	•				
armcmd	Error	3520	Failed to fail over the group %1. Check whether the server where the group can fail over exists.	Fail over failed	There may not be a server where the group can fail over.	•	•				•

Module Type	Event Type	Event ID	Messages	Description	Solution	Alert	Event log	User log	Mail report	setting Alive	Report Manager
Icns	Information	3551	The trial version is valid till %1/%2/%3. Product name:%4	trial version(normal)	-	•	•				
Icns	Error	3552	The trial version has expired(%1/%2/%3). Product name:%4	trial version(expired)	Register the license.	•	•	•			•
lcns	Warning	3553	Licenses are insufficient. The number of registered licenses is %1. The number of insufficient licenses is %2. Product name:%3	insufficient	Register the license.	•	•				•
Icns	Error	3554	The license is not registered. Product name:%1	not registered	Register the license.	•	•	•			•
Icns	Error	3555	The same license is registered with other servers. Product name:%1	repetition registered	Delete the overlapping license.	•	•	•			•
lcns	Error	3556	Manufacturer or model of this server is invalid.	Invalid manufacturer or model	Confirm the manufacturer or model.	•	•	•			•
logcmd	Information	3601		log command	-						
sdw	Warning	3651	Monitor %1 was delayed. (timeout=%2 response time=%3 rate=%4)	Monitoring is delayed		•	•	•			•
sdw	Error	3652	Cannot access the disk (%1).	Disconnection is detected.	Check that there is no error in the disk and the shared disk is correctly connected.		•			•	•
sdw	Information	3653	Recovered the status where access to the disk (%1) is possible.	Recovery from disconnection has been done.	-		•				
diskw	Warning	3701	Monitor %1 was delayed. (timeout=%2 response time=%3 rate=%4)	monitor delayed	-	•	•	•			•
vcom	Error	3751	Failed to register the virtual computer name (%1) to the DNS server.	Failed to register the virtual computer name	Check if an error has occurred on the DNS server, or a trouble occurred in communicating with the DNS server.	•	•				
vcom	Error	3752	Failed to delete the virtual computer name (%1) from the DNS server.	Failed to delete the virtual computer name	Check if an error has occurred on the DNS server, or a trouble occurred in communicating with the DNS server.	•	•				
hdadmn	Information	3851	Full Recovery of hybrid disk %1 started.	Full Recovery of hybrid disk started	-	•	•	•			
hdadmn	Information	3852	Full Recovery of hybrid disk %1 finished successfully.	Full Recovery of hybrid disk succeeded	-	•	•	•			
hdadmn	Information	3853	Full Recovery of hybrid disk %1 was canceled.	Full Recovery of hybrid disk was canceled	-	•	•	•			
hdadmn	Error	3854	Full Recovery of hybrid disk %1 failed.	Full Recovery of hybrid disk failed	Check that there is no error in the disk and network adapter and the network is correctly connected.	•	•	•		•	•

Module	Event	Event	Messages	Description	Solution	AI	Ever	User	Mail	setting	Report
Туре	Туре	ID			Solution	Alert	Event log	r log	Mail report	Alive	Manager
hdadmn	Information	3855	Fast Recovery of hybrid disk %1 started.	Fast Recovery of hybrid disk started	-	•	•	•			
hdadmn	Information	3856	Fast Recovery of hybrid disk %1 finished successfully.	Fast Recovery of hybrid disk succeeded	-	•	•	•			
hdadmn	Information	3857	Fast Recovery of hybrid disk %1 was canceled.	Fast Recovery of hybrid disk was canceled	-	•	•	•			
hdadmn	Error	3858	Fast Recovery of hybrid disk %1 failed.	Fast Recovery of hybrid disk failed	Check that there is no error in the disk and network adapter and the network is correctly connected.	•	•	•		•	•
hdadmn	Warning	3859	Trying again to disconnect hybrid disk %1. Check if the hybrid disk is being used.	Disconnection of hybrid disk is being retried	Check if the hybrid disk is being used.	•	•	•			•
hdadmn	Information	3860	Hybrid disk %1 was forcibly disconnected.	Hybrid disk was forcibly disconnected.	-	•	•	•			
hdadmn	Error	3861	The mirror connect of the hybrid disk %1 has been disconnected.	mirror connect error	Check that there is no error in the network adapter and the network is correctly connected.	•	•	•			•
hdadmn	Error	3862	A data partition error occurred in the hybrid disk %1.	disk error	Replace the server disk.	•	•	•		•	•
hdadmn	Error	3863	A cluster partition error occurred in the hybrid disk %1.	disk error	Replace the server disk.	•	•	•		•	•
hdadmn	Error	3864	Failed to initialize the mirror connect.	Mirror connection initialization failed	Check that there is no error in the network adapter and the network is correctly connected.	•	•	•		•	•
hdadmn	Error	3865	Failed to initialize the hybrid disk %1.	Hybrid disk initialization failed	Check the partition exists and the disk is recognized by the operating system.	•	•	•		•	•
hdadmn	Error	3866	Failed to initialize the hybrid disk %1. The cluster partition and the data partition must be different partitions.	Hybrid disk initialization failed	Check the cluster configuration data.	•	•	•			•
hdadmn	Error	3867	Failed to initialize the hybrid disk %1. The area in the cluster partition has been used by another hybrid disk.	Hybrid disk initialization failed	Check the cluster configuration data.	•	•	•			•
hdadmn	Error	3868	Failed to initialize the hybrid disk %1. The partition specified for the cluster partition has been used as the data partition of another hybrid disk.	Hybrid disk initialization failed	Check the cluster configuration data.	•	•	•			•
hdadmn	Error	3869	Failed to initialize the hybrid disk %1. The partition specified for the data partition has been used by another hybrid disk.	Hybrid disk initialization failed	Check the cluster configuration data.	•	•	•			•

Module	Event	Event		B	O.L.diss	A	Eve	User	Mail	setting	Report
Туре	Туре	ID	Messages	Description	Solution	Alert	Event log	r log	Mail report	Alive	Manager
hdadmn	Error	3870	Connecting hybrid disk %1 has failed.	Connecting hybrid disk failed	Check the partition exists and the disk is recognized by the operating system.		•			•	•
hdadmn	Error	3871	Disconnecting hybrid disk %1 has failed.  Detected a disk resource	Disconnecting hybrid disk failed	Check if the hybrid disk is being used.		•				•
hdadmn	Information	3872	that has not been identified. Disk reidentification will be executed.	Disk reidentification starts	-	•	•	•			
hdadmn	Information	3873	Reidentification of the disk has finished.	Disk reidentifcaiton finished.	-	•	•	•			
hdadmn	Error	3874	A fatal error has occurred during control hybrid disk %1. Shutdown the server. Monitor %1 was	Fatal error has occurred	Check that there is no error in disk and network adapter and the network is correctly connected.	•	•	•		•	•
hdtw	Warning	4001	delayed. (timeout=%2 response time=%3 rate=%4)	Monitoring is delayed	-	•	•	•			•
hdtw	Error	4002	Cannot access the disk (%1).	Disconnection is detected.	Check that there is no error in the disk and the shared disk is correctly connected.		•			•	•
hdtw	Information	4003	Recovered the status where access to the disk (%1) is possible.	Recovery from disconnection has been done.	-		•				
mail	Error	4101	mail failed(%1).(SMTP server: %2)	Mail failed	Check if an error has occurred on the SMTP server, or a trouble occurred in communicating with the SMTP server.	•	•	•			•
mail	Information	4102	mail succeed.(SMTP server: %1)	Mail succeeded	-		•	•			
dn1000s	Information	4151	Notice by the network warming light succeeded.	Network warning light succeeded	-	•	•	•			
dn1000s	Error	4152	Error in network warning light notice command.(%1)	Network warning light failed	Troubleshoot according to the error code.	•	•	•			•
dn1000s	Error	4153	Failed to execute warning light command.(%1)	Network warning light failed	The system may not be able to operate properly.	•	•	•			•
cifs	Information	4201	Created new shared configuration file.	Created new shared configuration file.	_	•	•	•			
cifs	Information	4202	Failed to read in shared configuration file. File may be corrupted.	Reading shared configuration file failed.	Check if the shared configuration file is corrupted.	•	•	•			
cifs	Information	4203	Recovered shared configuration file from backup file.	Shared configuration file is restored.	_	•	•	•			
cifs	Information	4204	Recreated shared configuration file since it cannot be found.	Shared configuration file is created again.	This is an normal action at first activation. In other cases, check if the shared configuration file is not deleted.	•	•	•			

Module Type	Event Type	Event ID	Messages	Description	Solution	Alert	Event log	User log	Mail report		Report Manager
cifs	Information	4205	There are differences between share settings stored in shared configuration file and the current configuration settings.	Sharing target folder is lost.	Check if the shared folder is not deleted while CIFS resource is deactivated.	•	•	•		Ф	yer
db2 ftp http imap4 odbc oracle oracleas oss otx pop3 psql smtp sqlserver tux was wls	Warning	10001	%1	Error message for each monitored application.	Troubleshoot the application failure according to the error message.	•					
db2w ftpw httpw imap4w odbcw oracleasw ossw otxw pop3w psqlw smtpw sqlserverw tuxw wasw db2 ftp http imap4 odbc oracleas oss otx pop3 psql smtpw sqlserverw tuxw wasw wlsw db2 ftp	Warning	10002	The API Error of Windows occurred.%1	API error of Windows has occurred. %1 is API error code.	Troubleshoot the OS failure according to the error code.	•					

#### Chapter 13 Error messages

Module Type	Event Type	Event ID	Messages	Description	Solution	Alert	Event log	User log	Mail report	setting Alive	Report Manager
tuxw	Warning	10004	Application occurred %1		Troubleshoot the application failure according to the error code.	•					

# **Driver event log messages**

#### Disk filter driver

The following events are recorded in system event log as the source "clpdiskfltr".

Module Type	Event Type	Event ID	Message	Description	Solution
diskfltr	Info	1001	Mirror disk resource activated without mirroring achieved.(%1)	Mirror disk resource has been activated without connecting to the mirror connect. %1: mirror disk number	Mirror disk resource has been activated while the other server is not in normal state such as in failover or access restriction release. Check that there is no error in the other server.
				Disconnected: Disconnection has been detected in the mirror connect.	Check that there is no error in the network.
				Timeout - HealthCheck: There was no response from the other server.	Same as above.
diskfltr	Error	2001	Mirror disk connect error.(%1)	Timeout - 1stAck: There was no response from the other server.	Check that there is no error in the network or the other server.
				Timeout - 2ndAck: There was no response from the other server.	Same as above.
				Mirror DP Not Found: The data partition of the other server cannot be found.	Check that there is no error in the data partition of the other server.
diskfltr	Error	2002	Asynchronized transfer error.(%1)	Timeout - Get KernelQueue: Timeout occurred in ansynchronized transfer.	An error occurred in the user process of asynchronized transfer. Check that the Clpdiskageent process is running normally, and that there is no error in I/O to the local disk.
				History Overflow: The number of the items to be recorded as history was exceeded, so mirroring was interrupted.	Consider to decrease the process to write asynchronized transfer or improve the speed of circuit.
diskfltr	Error	2003	Mirror disk access error(DP).(%1)	Accessing the mirror disk failed. %1: mirror disk number	Check that there is no error in the data partition of the mirror disk. In case of an error, exchange the disk for the one without an error.

Module Type	Event Type	Event ID	Message	Description	Solution
diskfltr	Error	2004	Mirror disk access error(CP).(%1)	Failed to record the difference information on the cluster partition. %1: mirror disk number	Check that there is no error in the cluster partition of the mirror disk. In case of an error, exchange the disk for the one without an error.
diskfltr	Error	2005	Cluster partition access error.	Accessing the cluster portion failed.	Check that there is no error in the cluster partition of the mirror disk. In case of an error, exchange the disk for the one without an error.
				Standby: Mirror disk is already being operated as the standby system.	An error in operation is considered to have caused this error. Check the cause of this error.
diskfltr	Error	2006	Mirror disk activation error.(%1)	Already opened: Mirror disk is already being operated as the active system.	Same as above.
				Refused by other: The status of the other server is wrong. (It is being activated now.)	Same as above.
diskfltr	Error	2099	Internal error.	An internal error occurred.	Insufficient kernel memory or OS resource is considered to have caused this error. Check this error with the performance monitor.
diskfltr	Error	5001	Connection error on mirror disk connect.(%1)	Connecting to the mirror connect failed.	Check that there is no error in the network or the mirror connect settings.
diskfltr	Error	5002	Communication error on mirror disk connect.(%1)	Since the network has an error or is highly loaded, the mirror connect is disconnected.	Check that there is no error in the network.
diskfltr	Error	5003	History file access error.(%1)	Failed to write or read the history file.	Check that there is no error in the hard disk. In case of an error, exchange the disk for the one without an error.
diskfltr	Error	5004	Mirror disk virtual device access error.(%1)	Failed to obtain the data from the mirror disk virtual driver.	The mirror disk virtual driver is not running normally or has an error. Check that ExpressCluster has been set up correctly.
diskfltr	Error	5005	Mirror disk connect timeout.(%1)	The network has an error or is highly loaded, the mirror connect is disconnected.	Check that there is no error in the network or the other server.
diskfltr	Error	5006	History file disk overflow.(%1)	Failed to output the history file because of insufficient disk capacity.	The folder to store the history file does not have enough. Set the folder with enough capacity.

Module Type	Event Type	Event ID	Message	Description	Solution
diskfltr	Error	5007	Queue buffer allocation error.(%1)	Failed to allocate the buffer for ansynchronized transfer.	Insufficient memory or OS resource is considered to have caused this error. Check the cause.
diskfltr	Error	5099	Internal error.(%1)	An internal error occurred.	Insufficient memory or OS resource is considered to have caused this error. Check the cause.

### Kernel mode LAN heartbeat driver

The following events are recorded in system event log as the source "clphb".

Module Type	Event Type	Event ID	Message	Description	Solution
clphb	Error	3001	Fatal error occurred in the driver.	Fatal error occurred in the driver.	Kernel memory or OS resource may not be sufficient. Check with performance monitor.
clphb	Info	1001	Signal has been set to the shutdown event due to the keep alive timeout.	User mode is stalled.	Kernel memory or OS resource may not be sufficient. Check with performance monitor.
clphb	Info	1002	Signal has been set to the shutdown event due to the FILTER closing action.	Received FILTER closing action.	Kernel memory or OS resource may not be sufficient. Check with performance monitor.

# Detailed information in activating and deactivating group resources

The following information is displayed in the messages recorded in event logs or alert viewer as detail information when the resource activation / deactivation fails.

#### **Application resource**

Module Type	Туре	Return Value	Message	Description	Solution
appli	Error	5	The application path is invalid.	The application path is invalid.	Check if the application path is correct.
appli	Error	7	Failed to start application.	Failed to start application.	Memory or OS resources may not be sufficient. Check them.
appli	Error	8	Failed to stop application.	Failed to stop application.	Memory or OS resources may not be sufficient. Check them.
appli	Error	10	Timeout occurred.	Timeout occurred.	Check if the application terminates within the time-out period.
appli	Error	11	Failed to log on as a user.	Failed to log on as a user.	Check if a domain, an account and a password of the logon user are set properly.
appli	Error	Others	Internal error occurred.	Internal error occurred.	Memory or OS resources may not be sufficient. Check them.

#### **CIFS** Resource

Module Type	Туре	Return Value	Message	Description	Solution
cifs	Error	2	The specified path is invalid.	The specified path is invalid.	Correct the setting of target folder.
cifs	Error	3	Access denied.	Access denied.	Check if local system account has the appropriate access right to the target folder.
cifs	Error	4	The share name is already in use on this server.	The specified name of the shared folder is already in use on this server.	Correct the setting of shared name.
cifs	Error	5	The specified path does not exist.	The specified path does not exist.	Correct the setting of target folder.
cifs	Error	6	Insufficient memory is available.	Insufficient memory is available.	Memory or OS resources may not be sufficient. Check them.
cifs	Error	7	The specified folder can not be found.	The specified folder can not be found.	Correct the setting of target folder.

Module Type	Туре	Return Value	Message	Description	Solution
cifs	Error	10	Failed to set the caching.	Failed to set the caching.	Check if local system account has the appropriate access right to the target folder.
cifs	Error	11	Failed to set security information.	Failed to set security information.	Check if local system account has the appropriate access right to the target folder.
cifs	Error	15	The shared configuration file path is wrong.	Specified path does not exist, or invalid character strings are used in the absolute path.	Correct the configuration value.
cifs	Error	17	Failed to write the shared configuration file.	Failed to save the shared configuration in the file.	Check if the writing to the shared configuration file is available with the local system account.
cifs	Error	18	Failed to read the shared configuration file.	Failed to read the shared configuration form the file.	Check if the reading from the shared configuration file is available with the local system account.
cifs	Error	20	Failed to start up CIFS control process.	Failed to start up the process (clpcifsp.exe) that monitors the change of shared configuration	There may be corruption of the execution file, lack of memory capacity or lack of OS resource. Check these issues.
cifs	Error	Others	Internal error occurred.	Internal error occurred.	Memory or OS resources may not be sufficient. Check them.

# Floating IP resource

Module Type	Туре	Return Value	Message	Description	Solution
fip	Error	5	IP address already exists.	IP address already exists.	Check if the IP address is already used on the network. Set the IP address that is not used.
fip	Error	8	Available adapter does not exist.	Available adapter does not exist.	Check if the FIP address network is the same as the server's real IP address.
fip	Error	9	Failed to add IP address.	Failed to add IP address.	Check the result of the ipconfig command. If 0.0.0.0 address exists, restart NIC.
fip	Error	10	Failed to delete IP address.	Failed to delete IP address.	Memory or OS resources may not be sufficient. Check them.
fip	Error	99	Internal error occurred.	Internal error occurred.	Memory or OS resources may not be sufficient. Check them.

# Mirror disk resource / hybrid disk resource

Module Type	Туре	Return Value	Message	Description	Solution
md/hd	Error	2	An internal error occurred.	An internal error occurred.	Memory or OS resources may not be sufficient. Check them.
md/hd	Error	2	The resource is busy.	The resource is busy.	Wait for a while, and retry the operation.
md/hd	Error	2	A network error occurred.	A network error occurred.	Check the status of the interconnect connection.
md/hd	Error	2	Cannot establish the mirror disk connection.	Cannot establish the mirror disk connection.	Check if the cluster configuration data is correct.
md/hd	Error	2	The resource name is invalid.	The resource name is invalid.	Check if the cluster configuration data is correct.
md/hd	Error	2	The status is invalid.	The status is invalid.	You need to perform the mirror recovery.
md/hd	Error	2	The resource is not initialized.	The resource is not initialized.	Check if the partition is allocated and OS recognizes the disk. Check if the cluster configuration data is correct.
md/hd	Error	2	The resource is not performed first mirror construction.	The resource is not performed first mirror construction.	You need to perform the initial mirror construction.
md/hd	Error	2	Cannot lock the mirror disk.	Cannot lock the mirror disk.	Memory or OS resources may not be sufficient. Check them.
md/hd	Error	2	The license is not registered.	The license is not registered.	Register the license.
md/hd	Error	2	The trial version has expired.	The trial version has expired.	Register the license.
md/hd	Error	2	The license authentication failed.	The license authentication failed.	Register the license.
md/hd	Error	2	Cannot find the history folder.	Cannot find the history folder.	Check if the cluster configuration data is correct.
md/hd	Error	2	The mirror connect is not initialized.	The mirror connect is not initialized.	Check the status of the mirror connect. Check if the cluster configuration data is correct.
md/hd	Error	2	Cannot find the partition specified for the cluster partition.	Cannot find the partition specified for the cluster partition.	Check if the partition is allocated and the OS recognizes the disk.
md/hd	Error	2	Cannot find the partition specified for the data partition.	Cannot find the partition specified for the data partition.	Check if the partition is allocated and the OS recognizes the disk.

Module Type	Туре	Return Value	Message	Description	Solution
md/hd	Error	2	Cannot change the drive letter for the cluster partition.	Cannot change the drive letter for the cluster partition.	Check if the drive letter for the cluster configuration data is specified. Check if the drive letter is not used for another partition.
md/hd	Error	2	Cannot change the drive letter for the data partition.	Cannot change the drive letter for the data partition.	Check if the drive letter for the cluster configuration data is specified. Check if the drive letter is not used for another partition.
md/hd	Error	2	The server name is invalid.	The server name is invalid.	Check if the cluster configuration data is correct.

# Registry synchronization resource

Module Type	Туре	Return Value	Message	Description	Solution
regsync	Error	2	Timeout has occurred while waiting for completion of synchronization processing at startup.	The resource cannot be activated since synchronization of registry files between servers has not been completed.	Activate the resource again after a while. If the error persists, OS may have errors. Check the status of the system.
regsync	Error	2	Timeout occurred when waiting for completing initialization of resource thread.	Activating the resource failed since initialization process of the thread has not been completed.	OS may have errors. Check the status of the system.
regsync	Error	2	Timeout occurred when waiting for completing termination of resource thread.	Deactivating the resource failed since termination process of the thread has not been completed.	OS may have errors. Check the status of the system.
regsync	Error	4	Specified resource does not exist in cluster configuration data.	Activating or deactivating the resource failed since it does not exist on the cluster configuration data.	Check if the resource name is consistent with the information in the cluster configuration data.
regsync	Error	5	Failed to allocate memory.	Activating the resource failed since the memory cannot be allocated.	Memory or OS resources may not be sufficient. Check the status of the system.
regsync	Error	6	Failed to get OS resource.	Activating the resource failed since OS resource cannot be obtained.	Memory or OS resources may not be sufficient. Check the status of the system.
regsync	Error	6	Failed to create thread.	Activating the resource failed since the thread cannot be created.	Memory or OS resources may not be sufficient. Check the status of the system.
regsync	Error	7	Failed to open registry.	Opening the registry failed since invalid	Check the value set on the Builder ( <b>Details</b> on

Module Type	Туре	Return Value	Message	Description	Solution
				registry key is registered to the resource.	Resource Properties), and change to a correct registry key.
regsync	Error	7	Failed to restore registry.	Restoring the registry failed since invalid registry key is registered to the resource.	Check the value set on the Builder ( <b>Details</b> on <b>Resource Properties</b> ), and change to a correct registry key.
regsync	Error	8	Failed to open registry.	Opening the registry failed since the registry key registered to the resource does not exist on the registry, or Win32 API error occurred.	Check if the registry key exists on the registry. If it does not exist, create it. If it exists, OS may have errors. Check the status of the system.
regsync	Error	8	Failed to restore registry.	Opening the registry failed since the registry key registered to the resource does not exist on the registry, other process opens the registry key, or the system call for registry operation returned an error.	Check if the registry key exists on the registry. If it does not exist, create it. If it exists, check if a process other than ExpressCluster opens the registry key. If the registry key exists and no other process opens it, OS may have errors. Check the status of the system.
regsync	Error	9	Failed to lock file.	Locking a file failed when operating the registry storage file.	Check if the process other than ExpressCluster opens the registry storage file.
regsync	Error	9	Failed to input/output the file.	The input/output process of the file failed when operating the registry storage file.	Check if the process other than ExpressCluster opens the registry storage file.  OS may have errors. Check the status of the system.
regsync	Error	12	Synchronization processing at startup has failed.	The resource cannot be activated since synchronization process of the registry storage file between servers failed.	OS may have errors. Check the status of the system.

# **Script resource**

Module Type	Туре	Return Value	Message	Description	Solution
script	Error	6	Failed to execute start script.	Failed to execute start script.	Memory or OS resources may not be sufficient. Check them.
script	Error	7	Failed to execute stop script.	Failed to execute stop script.	Memory or OS resources may not be sufficient. Check them.
script	Error	9	Timeout occurred.	Timeout occurred.	Check if the script terminates within the time-out period.
script	Error	Others	Internal error occurred.	Internal error occurred.	Memory or OS resources may not be sufficient. Check them.

### Disk resource

Module Type	Туре	Return Value	Message	Description	Solution
sd	Error	-1	Internal error occurred.	Internal error occurred.	Memory or OS resources may not be sufficient. Check them.
sd	Error	-1	Failed to load cluster configuration data.	Failed to load cluster configuration data.	Check if the cluster configuration data is stored on a proper location.
sd	Error	-1	Failed to unload cluster configuration data.	Failed to unload cluster configuration data.	Check if the cluster configuration data is stored on a proper location.
sd	Error	-1	Failed to get cluster configuration data.	Failed to get cluster configuration data.	Check if the cluster configuration data is correct.
sd	Error	-1	Failed to allocate memory.	Failed to allocate memory.	Memory or OS resources may not be sufficient. Check them.
sd	Error	-1	Failed to activate resource.	Failed to activate resource.	Check if the HBA settings are correct.
sd	Error	-1	Failed to create thread.	Failed to create thread.	Memory or OS resources may not be sufficient. Check them.
sd	Error	-1	Timeout occurred on thread.	Timeout occurred on thread.	Memory or OS resources may not be sufficient. Check them.
sd	Error	-1	Failed to dismount the partition specified by the resource.	Failed to dismount the partition specified by the resource.	The partition may be in use. Check it.
sd	Error	-1	Failed to lock the partition specified by the resource.	Failed to lock the partition specified by the resource.	The partition may be in use. Check it.

Module Type	Туре	Return Value	Message	Description	Solution
sd	Error	-1	Failed to deactivate resource.	Failed to deactivate resource.	Check if the HBA settings are correct.
sd	Error	-1	Server does not exist in cluster configuration data.	Server does not exist in cluster configuration data.	Check if the server exists in the cluster configuration data.
sd	Error	-1	Resource does not exist in cluster configuration data.	Resource does not exist in cluster configuration data.	Check if the resource exists in the cluster configuration data.
sd	Error	-1	Cannot find the specified partition.	Cannot find the specified partition.	Check if OS recognizes the specified partition.
sd	Error	-1	Cannot change the drive letter.	Cannot change the drive letter.	Check if the specified drive letter is used for another partition.

### Service resource

Module Type	Туре	Return Value	Message	Description	Solution
service	Error	5	Failed to get service control right.	Failed to get service control right.	Check if the service name is correct.
service	Error	6	Failed to start service.	Failed to start service.	Check the status of the service.
service	Error	7	Failed to stop service.	Failed to stop service.	Check the status of the service.
service	Error	8	Service has already been running.	Service has already been running.	Check the status of the service. It is possible to configure settings not to make it an error when the service is already running.
service	Error	10	Timeout occurred.	Timeout occurred.	Check if the service starts or stops within the time-out period.
service	Error	13	Computer name related to service that is running is different from virtual computer name of target VCOM resource.	Computer name related to service that is running is different from virtual computer name of target VCOM resource.	When you set the same service to more than one service, do not set the target VCOM resource name.
service	Error	Others	Internal error occurred.	Internal error occurred.	Memory or OS resources may not be sufficient. Check them.

# **Print spooler resource**

Module Type	Туре	Return Value	Message	Description	Solution
spool	Error	5	Failed to stop service.	Failed to stop service.	Stopping the spooler service failed. Check if the printer setting is correct.
spool	Error	4	Failed to start service.	Failed to start service.	Starting the spooler service failed. Check if the printer setting is correct.
spool	Error	Other	Internal error occurred.(status:%1!d!)	Internal error occurred.(status:%1!d!)	The disk capacity or the memory of the server where ExpressCluster is installed may not be sufficient. Check them.
angol	Error	, Failed to create a	Failed to create a	Check if activating the disk resource or the mirror disk resource fails.	
spool	LIIOI	1	specified spool directory.	specified spool directory.	Check if characters that cannot be used in a directory name are included.
anaal	Freez		Failed to change a spool	Failed to change a spool	Check if activating the disk resource or the mirror disk resource fails.
spool	Error	1	directory.	directory.	Check if characters that cannot be used in a directory name are included.
spool	Error	2	Config value(printer name) is invalid. resource:%1!s! value:%2!s!	Config value(printer name) is invalid. resource:%1!s! value:%2!s!	Check if the printer name exists on the server.
spool	Error	2	Config value(partition) is invalid. resource:%1!s! value:%2!s!	Config value(partition) is invalid. resource:%1!s! value:%2!s!	Check if the drive letter is the one on the disk resource or the mirror disk resource.
spool	Error	2	Config value(directory) is invalid. resource:%1!s! value:%2!s!	Config value(directory) is invalid. resource:%1!s! value:%2!s!	Check if characters that cannot be used in a directory name are included.

# Virtual computer name resource

Module Type	Туре	Return Value	Message	Description	Solution
vcom	Error	5	VCOM control process has already been started.	VCOM control process has already been started.	Memory or OS resources may not be sufficient. Check them.
			Started.	Started.	Restart the OS.
vcom	Error	6	VCOM control process has not been started.	VCOM control process has not been started.	Memory or OS resources may not be sufficient. Check them.
				nas not been statted.	Restart the OS.
vcom	Error	8	VCOM control process does not exist.	VCOM control process does not exist.	Memory or OS resources may not be sufficient. Check them.
					Restart the OS.
vcom	Error	9	Failed to get IP address table.	Failed to get IP address table.	Memory or OS resources may not be sufficient. Check them.
vcom	Error	10	Target FIP address does not exist.	Target FIP address does not exist.	Check if the IP address of the target FIP resource exists.
vcom	Error	11	Virtual computer name is the same as local hostname.	Virtual computer name is the same as local hostname.	Do not set existing host names for a virtual computer name.
vcom	Error	12	Failed to start VCOM control process.	Failed to start VCOM control process.	Check if all conditions for using a virtual computer are met.
vcom	Error	13	Failed to stop VCOM control process.	Failed to stop VCOM control process.	An error occurred when stopping the virtual computer.
					Restart the OS.
vcom	Error	Others	Internal error occurred.	Internal error occurred.	Memory or OS resources may not be sufficient. Check them.

### **Virtual IP resource**

Module Type	Туре	Return Value	Message	Description	Solution
vip	Error	5	IP address already	IP address already exists.	Check if the IP address is already used on the network.
			exists.	exists.	Set the IP address that is not used.
vip	Error	8	Available adapter does not exist.	Available adapter does not exist.	Check if the IP address set on the interconnect exists on the server. Set a proper IP address.
vip	Error	9	Failed to add IP address.	Failed to add IP address.	Check the result of the ipconfig command. If 0.0.0.0 address exists, restart NIC.
vip	Error	10	Failed to delete IP address.	Failed to delete IP address.	Memory or OS resources may not be sufficient. Check them.
vip	Error	Others	Internal error occurred.	Internal error occurred.	Memory or OS resources may not be sufficient. Check them.

### **NAS** Resource

Module Type	Туре	Return Value	Message	Description	Solution
nas	Error	1	The drive has already been used.	The specified drive letter has already been used for another network drive.	Change the drive letter.
nas	Error	3	Invalid nas drive.	The specified drive letter has already been used for another drive.	Change the drive letter.
nas	Error	4	Failed to redirect the network resource .	Failed to mount the network drive.	Check if the specified network resource is accessible with the specified account and password.
nas	Error	Others	Internal error occurred.	Internal error occurred.	Memory or OS resources may not be sufficient. Check them.

### Detailed info of monitor resource errors

The following information is displayed in the message recorded in event log or alert viewer as detail information when monitor resource detects an error.

#### **Application monitor resource**

Module Type	Туре	Return Value	Message	Description	Solution
appliw	Error	9	Process did not exist.	Process did not exist.	Process of the monitoring target application resource was cleared due to some error. Check it.
appliw	Error	11	Failed to log on as a user.	Failed to log on as a user.	Check if a domain, an account and a password of the logon user are set properly.
appliw	Error	Others	Internal error occurred.	Internal error occurred.	Memory or OS resources may not be sufficient. Check them.

#### **CIFS** monitor resource

Modul e Type	Туре	Return Value	Message	Description	Solution
cifsw	Error	3	Access denied.	Local system account doesn't have the appropriate access right to the shared folder.	Correct the access right setting of target folder.
cifsw	Error	6	Insufficient memory is available.	Insufficient memory is available.	Memory or OS resources may not be sufficient. Check them.
cifsw	Error	8	The specified share name can not be found.	The specified share name can not be found.	Check if the setting of file sharing has been canceled.
cifsw	Error	13	Error occurred while doing file check.	Error occurred while doing file check.	Check if local system account has the appropriate access right for executing specified method of monitoring.
cifsw	Error	14	Error occurred while doing folder check.	Error occurred while doing folder check.	Check if local system account has the appropriate access right for executing specified method of monitoring.
cifsw	Error	19	Failed to check the shared configuration file.	Failed to execute checking the configuration data saved in the shared configuration file.	Check if the shared configuration file is corrupted.
cifsw	Error	21	CIFS control process does not exist.	Failed to start up the process (clpcifsp.exe) that monitors the change of shared configuration.	Activate CIFS resource again.

Modul e Type	Туре	Return Value	Message	Description	Solution
cifsw	Error	99	Internal error occurred.	Internal error occurred.	Memory or OS resources may not be sufficient. Check them.
cifsw	Warning	101	Setting has been changed.	Setting of file sharing has been changed.	Check if the user limit setting or the target folder of file sharing has been changed.

### **DB2** monitor resource

Module Type	Туре	Return Value	Message	Description	Solution
db2w	Error	1	Initialization has failed[%1!s!].	Initialization process has failed. It may be due to memory allocation failure.  Information on the initialization may be displayed on %1.	OS itself may have errors.  Restart the server or take other actions.
db2w	Error	2	The configured value is not correct.	The configured value of the monitoring is not correct.	Check the configured value on the Builder since they may not be correct.
db2w	Error	10	A function error was detected.	A function error occurred.	Monitor applications or OS may have errors. Check the status of the system.
db2w	Error	11	An error was detected in accessing the monitor target.	Accessing the database failed.	Check configured values on the Builder (such as a database name). If there is no error, check the database has errors.
db2w	Error	12	An error was detected in user authentication.	Accessing the database failed.	Check configured values on the Builder (such as a user name or a password). If there is no error, check the database has errors.
db2w	Error	13	An application error was detected.	A database error was detected.	Refer to error messages for database described separately to fix errors.
db2w	Error	14	An error was detected in executing SQL statement [%1].	Executing SQL statement failed.  The executed SQL statement is displayed on %1.	Refer to error messages for database described separately to fix errors.
db2w	Error	15	A data error was detected.	A value on the table of database has an error.	Database may be corrupt. Stop the database operation and investigate it. This error may occur when more than one monitoring is performed with the same monitor table name concurrently. Check if the values set in

Section III Maintenance information

Module Type	Туре	Return Value	Message	Description	Solution
					the multi-directional environment are appropriate.
db2w	Error	40	No license is registered.	The license has not been registered.	Register the license.
db2w	Error	60	Failed to obtain the configuration data.	The configured value could not be obtained.	OS may have errors. Restart the server or take other actions.

### **Disk RW monitor resource**

Module Type	Туре	Return Value	Message	Description	Solution
diskw	Error	1	Initialization error has occurred in internal resource.	Initialization error has occurred in internal resource.	Memory or OS resources may not be sufficient. Check them.
diskw	Error	2	Failed to add keep alive drive when initializing keep alive driver.	Failed to add keep alive drive when initializing keep alive driver.	Memory or OS resources may not be sufficient. Check them.
diskw	Error	3	Initialization has not been done.	Initialization has not been done.	Memory or OS resources may not be sufficient. Check them.
diskw	Error	4	Failed to obtain the cluster configuration data.	Failed to obtain the cluster configuration data.	The cluster configuration data is invalid. Check the disk RW monitor resource on the Builder.
diskw	Error	5	Failed to open the file.	Failed to open the file.	Check if the disk driver of the monitoring target disk is loaded, the disk is connected properly, the disk is powered on, or no other errors are occurred on the disk. Memory or OS resources may not be sufficient. Check them.
diskw	Error	6	Failed to write in the file.	Failed to write in the file.	Check if the monitoring target disk is connected properly, the disk is powered on, or no other errors are occurred on the disk. Memory or OS resources may not be sufficient. Check them.
diskw	Error	7	Failed to synchronize the disk of the file.	Failed to synchronize the disk of the file.	Check if the monitoring target disk is connected properly, the disk is powered on, or no other errors are occurred on the disk. Memory or OS resources may not be

Module Type	Туре	Return Value	Message	Description	Solution
Туре		Value			sufficient. Check them.
diskw	Error	8	Failed to close the file.	Failed to close the file.	Check if the monitoring target disk is connected properly, the disk is powered on, or no other errors are occurred on the disk. Memory or OS resources may not be sufficient. Check them.
diskw	Error	9	Timeout has occurred when initializing internal resources.	Timeout has occurred when initializing internal resources.	Check if an error is occurred on the monitoring target disk. If there is no error, memory or OS resources may not be sufficient. Check them.
diskw	Error	10	Failed to allocate memory.	Failed to allocate memory.	Memory or OS resources may not be sufficient. Check them.
diskw	Error	70	Timeout has occurred when initializing internal resources.	Timeout has occurred when initializing internal resources.	Memory or OS resources may not be sufficient. Check them.
diskw	Error	71	Timeout has occurred when opening the file.	Timeout has occurred when opening the file.	Check if the monitoring target disk is connected properly, the disk is powered on, or no other errors are occurred on the disk. The system may be under high load, or memory or OS resources may not be sufficient. Check them.
diskw	Error	72	Timeout has occurred when writing in the file.	Timeout has occurred when writing in the file.	Check if the monitoring target disk is connected properly, the disk is powered on, or no other errors are occurred on the disk. The system may be under high load, or memory or OS resources may not be sufficient. Check them.
diskw	Error	73	Timeout has occurred when synchronizing the disk of the file.	Timeout has occurred when synchronizing the disk of the file.	Check if the monitoring target disk is connected properly, the disk is powered on, or no other errors are occurred on the disk. The system may be under high load, or memory or OS resources may not be sufficient. Check them.
diskw	Error	74	Timeout has occurred when closing the file.	Timeout has occurred when closing the file.	Check if the monitoring target disk is connected properly, the disk is powered on, or no other

Module Type	Туре	Return Value	Message	Description	Solution
					errors are occurred on the disk. The system may be under high load, or memory or OS resources may not be sufficient. Check them.
diskw	Error	90	Internal error occurred.	Internal error occurred.	Check if the monitoring target disk is connected properly, the disk is powered on, or no other errors are occurred on the disk. The system may be under high load, or memory or OS resources may not be sufficient. Check them.
diskw	Error	99	Internal error occurred.	Internal error occurred.	Memory or OS resources may not be sufficient. Check them.

# Floating IP monitor resource

Module Type	Туре	Return Value	Message	Description	Solution
fipw	Error	6	IP address does not exist.	IP address does not exist.	NIC may have been disabled. Check if the FIP address exists by the ipconfig command.
fipw	Error	11	Adapter Index is different.	Adapter Index is different.	NIC may have been disabled. Check if the FIP address exists by the ipconfig command.
fipw	Error	12	Failed to obtain IP address table.	Failed to obtain IP address table.	Memory or OS resources may not be sufficient. Check them.
fipw	Error	13	Failed to get NIC interface name.	Failed to get NIC interface name.	Memory or OS resources may not be sufficient. Check them.
fipw	Error	14	Failed to get NIC status.	Failed to get NIC status.	Check if the NIC device is supported by the device I/O controller.
fipw	Error	15	Detected NIC Link Down.	Detected NIC Link Down.	Check if the LAN cable is connected properly.
fipw	Error	Others	Internal error occurred.	Internal error occurred.	Memory or OS resources may not be sufficient. Check them.

### **FTP** monitor resource

Module Type	Туре	Return Value	Message	Description	Solution
ftpw	Error	1	Initialization has failed[%1!s!].	Initialization process has failed. It may be due to memory allocation	OS itself may have errors. Restart the server or take other

Module Type	Туре	Return Value	Message	Description	Solution
				failure.	actions
				Information on the initialization may be displayed on %1.	
ftpw	Error	2	The configured value is not correct.	The configured value of the monitoring is not correct.	Check the configured value on the Builder since it may not be correct.
ftpw	Error	10	A function error was detected.	A function error occurred.	Monitor applications or OS may have errors. Check the status of the system.
ftpw	Error	11	An error was detected in accessing the monitor target.	The access to the monitor application failed.	Check configured values on the Builder (such as an IP address). If there is no error, check if the monitor application has errors.
ftpw	Error	12	An error was detected in user authentication.	The user authentication failed.	Check configured values on the Builder (such as a user name or a password). If there is no error, check if the monitor application has errors
ftpw	Error	13	An application error was detected.	A monitor application error was detected.	Refer to error messages for monitor applications described separately to fix errors.
ftpw	Error	15	A data error was detected.	A value of the response data has an error.	Refer to error messages for monitor applications described separately to fix errors.
ftpw	Error	40	No license is registered.	The license has not been registered.	Register the license.
ftpw	Error	60	Failed to obtain the configuration data.	The configured value could not be obtained.	OS may have errors. Restart the server or take other actions

### **Custom monitor resource**

Module Type	Туре	Return Value	Message	Description	Solution
genw	Error	1	Parameter is invalid.	The configured value of the monitoring is not correct.	Check the configured value on the Builder.
genw	Error	2	Resource does not exist in cluster configuration data.	The cluster configuration data is not correct.	Check the cluster configuration data on the Builder.
genw	Error	3	Failed to get the value from cluster configuration data.	The cluster configuration data is not correct.	Check the cluster configuration data on the Builder.

Module Type	Туре	Return Value	Message	Description	Solution
genw	Error	4	Script path is invalid.	The configured value of the script path is not correct.	Check the configured value on the Builder.
genw	Error	5	Failed to start script.	Failed to start script.	Check if the script can be executed.
genw	Error	6	Script did not exist.	The asynchronous type script terminated abnormally.	Check the cause of the termination of the script.
genw	Error	7	Timeout occurred.	The synchronous type script did not terminate within the time-out period.	Check the cause of the delay of the script.
genw	Error	8	Returned termination code %1.	The synchronous type script returned abnormal error code.	Check the cause for the abnormal error code.
genw	Error	99	Internal error occurred.	Internal error occurred.	Memory or OS resources may not be sufficient. Check them.

# Hybrid disk TUR monitor resource

Module Type	Туре	Return Value	Message	Description	Solution
hdtw	Error	1	Initialization has failed. Check the cluster configuration data or system resources.	Initialization has failed. Check the cluster configuration data or system resources.	Memory or OS resources may not be sufficient. Check them.
hdtw	Error	2	Initialization has not been done.	Initialization has not been done.	Memory or OS resources may not be sufficient. Check them.
hdtw	Error	3	The cluster configuration data is invalid.	The cluster configuration data is invalid.	The cluster configuration data is invalid. Check the disk TUR monitor resource on the Builder
hdtw	Error	4	Failed to open device. Check the disk status of monitor destination volume.	Failed to open device. Check the disk status of monitor destination volume.	Check if the disk driver of the monitoring target disk is loaded, the device exists, the disk is connected properly, the disk is powered on, or no other errors are occurred on the disk. Memory or OS resources may not be sufficient. Check them.
hdtw	Error	5	Failed to control device. Check the disk status of monitor destination volume.	Failed to control device. Check the disk status of monitor destination volume.	Check if the monitoring target disk is connected properly, the disk is powered on, or no other errors are occurred on the disk.
hdtw	Error	6	Internal resources are busy.	Internal resources are busy.	Memory or OS resources may not be sufficient. Check them.

Module Type	Туре	Return Value	Message	Description	Solution
hdtw	Error	7	Failed to allocate memory. Check the system resource.	Failed to allocate memory. Check the system resource.	Memory or OS resources may not be sufficient. Check them.
hdtw	Error	90	Polling timeout. Check the disk load of the monitor target and extend the monitor timeout time.	Polling timeout. Check the disk load of the monitor target and extend the monitor timeout time.	Check if the monitoring target disk is connected properly, the disk is powered on, or no other errors are occurred on the disk. The system may be under high load, or memory or OS resources may not be sufficient. Check them.
hdtw	Error	99	Other internal error has occurred. Check the system resource.	Other internal error has occurred. Check the system resource.	Memory or OS resources may not be sufficient. Check them.

### Hybrid disk monitor resource

Module Type	Туре	Return Value	Message	Description	Solution
hdw	Error	2	Internal error.	An internal error has occurred.	Memory or OS resources may not be sufficient. Check them.
hdw	Error	3	HDR %1 has old data.	The information in the activated hybrid disk %1 is not updated.	Check the status of the hybrid disk with Mirror Disk Helper.
hdw	Error	4	A disk error is detected in HDR %1.	A disk error has been detected in hybrid disk %1.	Check that there is no HW failure in the disk or disk path where cluster partition or data partition exists.
hdw	Error	5	The status of HDR %1 is invalid.	The status of the hybrid disk %1 is invalid.	Restart the cluster.
hdw	Warning	101	HDR %1 recovery is in progress.	Hybrid disk %1 is being copied.	Wait for a while until mirror recovery completes.
hdw	Warning	102	HDR %1 is not being mirrored.	Hybrid disk %1 has not been mirrored.	Check the status of the hybrid disk with Mirror Disk Helper.
hdw	Warning	103	HDR %1 is activated on more than one server.	Hybrid disk %1 is activated on both server groups.	Deactivate the hybrid disk on one of the server groups.
hdw	Warning	104	The status of HDR %1 is unknown.	Hybrid disk to be monitored is stopped.	Stop the monitor resource or start the hybrid disk to be monitored.
hdw	Warning	105	Whether HDR %1 data is old/new is not determined.	Whether the data in hybrid disk %1 is old or new has not been determined.	Activate the hybrid disk on one of the servers.

#### **HTTP** monitor resource

Module Type	Туре	Return Value	Message	Description	Solution
httpw	Error	1	Initialization has failed[%1!s!].	Initialization process has failed. It may be due to memory allocation failure.  Information on the initialization may be displayed on %1.	OS itself may have errors. Restart the server or take other actions.
httpw	Error	2	The configured value is not correct.	The configured value of the monitoring is not correct.	Check the configured value on the Builder since it may not be correct.
httpw	Error	10	A function error was detected.	A function error occurred.	Monitor applications or OS may have errors. Check the status of the system.
httpw	Error	11	An error was detected in accessing the monitor target.	The access to the monitor application failed.	Check configured values on the Builder (such as an IP address). If there is no error, check if the monitor application has errors.
httpw	Error	13	An application error was detected.	A monitor application error was detected.	Refer to error messages for monitor applications described separately to fix errors.
httpw	Error	15	A data error was detected.	A value of the response data has an error.	Refer to error messages for monitor applications described separately to fix errors.
httpw	Error	40	No license is registered.	The license has not been registered.	Register the license.
httpw	Error	60	Failed to obtain the configuration data.	The configured value could not be obtained.	OS may have errors. Restart the server or take other actions.

### **IMAP4** monitor resource

Module Type	Туре	Return Value	Message	Description	Solution
imap4w	Error	1	Initialization has failed[%1!s!].	Initialization process has failed. It may be due to memory allocation failure.  Information on the initialization may be displayed on %1.	OS itself may have errors. Restart the server or take other actions
imap4w	Error	2	The configured value is not correct.	The configured value of the monitoring is not correct.	Check the configured value on the Builder since it may not be correct.
imap4w	Error	10	A function error was detected.	A function error occurred.	Monitor applications or OS may have errors. Check the status of the system.
imap4w	Error	11	An error was detected in accessing the monitor target.	The access to the monitor application failed.	Check configured values on the Builder (such as an IP address). If there is no error, check if the monitor application has errors.
imap4w	Error	12	An error was detected in user authentication.	The access to the monitor application failed.	Check configured values on the Builder (such as a user name or a password). If there is no error, check if the monitor application has errors.
imap4w	Error	13	An application error was detected.	A monitor application error was detected.	Refer to error messages for monitor applications described separately to fix errors.
imap4w	Error	15	A data error was detected.	A value of the response data has an error.	Refer to error messages for monitor applications described separately to fix errors.
imap4w	Error	40	No license is registered.	The license has not been registered.	Register the license.
imap4w	Error	60	Failed to obtain the configuration data.	The configured value could not be obtained.	OS may have errors. Restart the server or take other actions.

### **IP** monitor resource

Module Type	Туре	Return Value	Message	Description	Solution
ipw	Error	4	Ping could not reach.	Ping could not reach.	Check if the ping command to the corresponding IP address succeeds. When the command fails, check the status of the device that has the IP address and the network interface.
ipw	Error	5	Timeout occurred.	Timeout occurred.	Memory or OS resources may not be sufficient. Check them.
ipw	Error	Others	Internal error occurred.	Internal error occurred.	Memory or OS resources may not be sufficient. Check them.

### Mirror disk monitor resource

Module Type	Туре	Return Value	Message	Description	Solution
mdw	Error	2	Internal error.	Internal error.	Memory or OS resources may not be sufficient. Check them.
mdw	Error	3	Mirror disk %1 is abnormal.	Mirror disk %1 is abnormal.	The mirror disk of the local server has errors. Check it on the mirror disk helper.
mdw	Warning	101	Mirror disk %1 recovery is in progress.	Mirror disk %1 recovery is in progress.	Wait for a while until the mirror recovery completes.
mdw	Warning	102	Mirror disk %1 is not being mirrored.	Mirror disk %1 is not being mirrored.	Check the mirror disk on the mirror disk helper.
mdw	Warning	103	Mirror disk %1 is uncertain status.	Mirror disk %1 is uncertain status.	Check the mirror disk on the mirror disk helper.
mdw	Warning	104	Mirror disk %1 is activated on more than one server.	Mirror disk %1 is activated on more than one server.	When activation of the mirror disk resources on both servers is detected, the server is automatically shut down. Restart the server.
mdw	Warning	105	Mirror disk %1 is unknown status.	Mirror disk %1 is unknown status.	Memory or OS resources may not be sufficient. Check them.

### Mirror connect monitor resource

Module Type	Туре	Retur n Value	Message	Description	Solution
mdnw	Error	2	An internal error has occurred.	An internal error has occurred.	Memory or OS resources may not be sufficient. Check them.
mdnw	Warning	100	Network was interrupted.	Network was interrupted.	Check the connection status of the mirror connect.

### Multi target monitor resource

Module Type	Туре	Return Value	Message	Description	Solution
mtw	Error	Other	Internal error occurred.(status:%1!d!)	Internal error occurred.(status:%1!d!)	Memory or OS resources may not be sufficient. Check them.
mtw	Error	5	Status of resources is abnormal.	Status of resources is abnormal.	Check the status of the monitor resources listed on the monitor resources list.
mtw	Error	1	This option is invalid.	This option is invalid.	Memory or OS resources may not be sufficient. Check them.

### **NAS** monitor resource

Module Type	Туре	Return Value	Message	Description	Solution
nasw	Error	3	Invalid nas drive. drv:%1	The target drive is not the network drive.	Check if the drive letters have been changed
nasw	Error	4	Failed to get the network resource mapped by the specified drive. drv:%1 errcode:%2	The target drive is not being mounted.	Check if the network drive has been unmounted.
nasw	Error	4	The network resource is not connected. path:%1	The target drive is not being mounted.	Check if the network drive has been unmounted.
nasw	Error	4	The network resource is different from that of the configuration value. drv:%1	The network resource is different from that of the configuration value.	Check if the setting of the network drive has been changed.
nasw	Error	99	An internal error has occurred.	An internal error has occurred.	Memory or OS resources may not be sufficient. Check them.

# NIC Link Up/Down monitor resource

Module Type	Туре	Return Value	Message	Description	Solution
miiw	Error	4	IP address does not exist.	IP address does not exist.	NIC may have been disabled. Check if the IP address of the specified NIC exists by the ipconfig command.
miiw	Error	5	Failed to get IP address table.	Failed to get IP address table.	Memory or OS resources may not be sufficient. Check them.
miiw	Error	6	Failed to get NIC interface name.	Failed to get NIC interface name.	Memory or OS resources may not be sufficient. Check them.
miiw	Error	7	Failed to get NIC status.	Failed to get NIC status.	Check if the NIC device is supported by the device I/O controller.
miiw	Error	8	Detected NIC Link Down.	Detected NIC Link Down.	Check if the LAN cable is connected properly.
miiw	Error	Others	An internal error has occurred.	An internal error has occurred.	Memory or OS resources may not be sufficient. Check them.

### **ODBC** monitor resource

Module Type	Туре	Return Value	Message	Description	Solution
odbcw	Error	1	Initialization has failed[%1!s!].	Initialization process has failed. It may be due to memory allocation failure.  Information on the initialization may be displayed on %1.	OS itself may have errors. Restart the server or take other actions.
odbcw	Error	2	The configured value is not correct.	The configured value of the monitoring is not correct.	Check the configured value on the Builder since it may not be correct.
odbcw	Error	10	A function error was detected.	A function error occurred.	Monitor applications or OS may have errors. Check the status of the system.
odbcw	Error	11	An error was detected in accessing the monitor target.	The access to the database failed.	Check configured values on the Builder (such as a database name). If there is no error, check the database has errors.
odbcw	Error	12	An error was detected in user authentication.	The access to the database failed.	Check configured values on the Builder (such as a user name or a password). If there is no error, check if the

Module Type	Туре	Return Value	Message	Description	Solution
					database has errors.
odbcw	Error	13	An application error was detected.	The database error was detected.	Refer to error messages for database described separately to fix errors.
			An error was detected in	Executing SQL statement failed.	Refer to error messages
odbcw	Error	14	executing SQL statement [%1!s!].	The executed SQL statement is displayed on %1.	for database described separately to fix errors.
odbcw	Error	15	A data error was detected.	A value on the table of database has an error.	Database may be corrupt. Stop the database operation and investigate it. This error may occur when more than one monitoring is performed with the same monitor table name concurrently. Check if the values set in the multi-directional environment are appropriate.
odbcw	Error	40	No license is registered.	The license has not been registered.	Register the license.
odbcw	Error	60	Failed to obtain the configuration data.	The configured value could not be obtained.	OS may have errors. Restart the server or take other actions

### **Oracle monitor resource**

Module Type	Туре	Return Value	Message	Description	Solution
oraclew	Error	1	Initialization has failed[%1!s!].	Initialization process has failed. It may be due to memory allocation failure.  Information on the initialization may be displayed on %1.	OS itself may have errors. Restart the server or take other actions
oraclew	Error	2	The configured value is not correct.	The configured value of the monitoring is not correct.	Check the configured value on the Builder since it may not be correct.
oraclew	Error	10	A function error was detected.	A function error occurred.	Monitor applications or OS may have errors. Check the status of the system.

Module Type	Туре	Return Value	Message	Description	Solution
oraclew	Error	11	An error was detected in accessing the monitor target.	The access to the database failed.	Check configured values on the Builder (such as a database name). If there is no error, check the database has errors.
oraclew	Error	12	An error was detected in user authentication.	The access to the database failed.	Check configured values on the Builder (such as a user name or a password). If there is no error, check if the database has errors.
oraclew	Error	13	An application error was detected.	The database error was detected.	Refer to error messages for database described separately to fix errors.
oraclew	Error	14	An error was detected in executing SQL statement [%1!s!].	Executing SQL statement failed.  The executed SQL statement is displayed on %1.	Refer to error messages for database described separately to fix errors.
oraclew	Error	15	A data error was detected.	A value on the table of database has an error.	Database may be corrupt. Stop the database operation and investigate it. This error may occur when more than one monitoring is performed with the same monitor table name concurrently. Check if the values set in the multi-directional environment are appropriate.
oraclew	Error	40	No license is registered.	The license has not been registered.	Register the license.
oraclew	Error	60	Failed to obtain the configuration data.	The configured value could not be obtained.	OS may have errors. Restart the server or take other actions.

### **OracleAS monitor resource**

Module Type	Туре	Return Value	Message	Description	Solution
oracleas w	Error	1	Initialization has failed[%1!s!].	Initialization process has failed. It may be due to memory allocation failure.  Information on the initialization may be displayed on %1.	OS itself may have errors. Restart the server or take other actions.
oracleas w	Error	2	The configured value is not correct.	The configured value of the monitoring is not correct.	Check the configured value on the Builder since it may not be correct.

Module Type	Туре	Return Value	Message	Description	Solution
oracleas w	Error	10	A function error was detected.	A function error occurred.	Monitor applications or OS may have errors. Check the status of the system.
oracleas w	Error	11	An error was detected in accessing the monitor target.	The access to the monitor application failed.	Check if the monitor application has errors.
oracleas w	Error	12	An error was detected in user authentication.	The access to the monitor application failed.	Check configured values on the Builder (such as a user name or a password). If there is no error, check if the monitor application has errors.
oracleas w	Error	13	An application error was detected.	The monitor application error was detected.	Check configured values on the Builder (such as an instance name). If there is no error, refer to error messages for monitor applications described separately to fix errors.
oracleas w	Error	40	No license is registered.	The license has not been registered.	Register the license.
oracleas w	Error	60	Failed to obtain the configuration data.	The configured value could not be obtained.	OS may have errors. Restart the server or take other actions.
oracleas w	Error	98	Internal error.	Internal error occurred.	Memory or OS resources may not be sufficient. Check them.

### OfficeScan CL monitor resource

Module Type	Туре	Return Value	Message	Description	Solution
oscw	Error	2	Failed to get the value from cluster configuration data.	Failed to get the value from cluster configuration data.	Cluster configuration file (clp.conf) or policy file (oscw.pol) may be corrupted.
oscw	Error	10	Failed to get service control right.	Failed to get service control right.	Check if OfficeScan Client is installed correctly.
oscw	Error	11	Service status is abnormal.	Service status is abnormal.	Check the statu of OfficeScan NT Listener with Service Control Manager.
oscw	Error	12	Failed to start service.	Failed to start service.	Check the statu of OfficeScan NT Listener with Service Control Manager.
oscw	Error	13	Failed to stop service.	Failed to stop service.	Check the statu of OfficeScan NT Listener with Service Control Manager.

Section III Maintenance information

Module Type	Туре	Return Value	Message	Description	Solution
oscw	Error	50	License is invalid or not regisered.	License is invalid or not regisered.	Check the Anti-Virus Agent license is registered and valid.

#### OfficeScan SV monitor resource

Module Type	Туре	Return Value	Message	Description	Solution
ossw	Error	1	Initialization has failed[%1!s!].	Initialization process has failed. It may be due to memory allocation failure.  Information on the initialization may be displayed on %1.	OS itself may have errors. Restart the server or take other actions.
ossw	Error	2	The configured value is not correct.	The configured value of the monitoring is not correct.	Check if OfficeScan Server is installed correctly.
ossw	Error	10	A function error was detected.	A function error occurred.	Monitor applications or OS may have errors. Check the status of the system.
ossw	Error	11	An error was detected in accessing the monitor target.	The access to the monitor application failed.	Check if OfficeScan Server has errors.
ossw	Error	13	An application error was detected.	The access to the monitor application failed.	Refer to error messages for monitor applications described separately to fix errors.
ossw	Error	15	A data error was detected.	A value of the response data has an error.	Refer to error messages for monitor applications described separately to fix errors.
ossw	Error	40	No license is registered.	The license has not been registered.	Register Anti-Virus Agent license.
ossw	Error	60	Failed to obtain the configuration data.	The configured value could not be obtained.	OS may have errors.Restart the server or take other actions.
ossw	Error	98	Internal error.	Internal error occurred.	Memory or OS resources may not be sufficient. Check them.

### **POP3** monitor resource

Module	Туре	Return Value	Message	Description	Solution
Type		value			'

Module Type	Туре	Return Value	Message	Description	Solution
pop3w	Error	1	Initialization has failed[%1!s!].	Initialization process has failed. It may be due to memory allocation failure.  Information on the initialization may be displayed on %1.	OS itself may have errors. Restart the server or take other actions.
pop3w	Error	2	The configured value is not correct.	The configured value of the monitoring is not correct.	Check the configured value on the Builder since it may not be correct.
pop3w	Error	10	A function error was detected.	A function error occurred.	Monitor applications or OS may have errors. Check the status of the system.
pop3w	Error	11	An error was detected in accessing the monitor target.	The access to the monitor application failed.	Check configured values on the Builder (such as an IP address). If there is no error, check if the monitor application has errors.
pop3w	Error	12	An error was detected in user authentication.	The access to the monitor application failed.	Check configured values on the Builder (such as a user name or a password). If there is no error, check if the monitor application has errors.
pop3w	Error	13	An application error was detected.	The monitor application error was detected.	Refer to error messages for monitor applications described separately to fix errors.
pop3w	Error	15	A data error was detected.	A value of the response data has an error.	Refer to error messages for monitor applications described separately to fix errors.
pop3w	Error	40	No license is registered.	The license has not been registered.	Register the license.
pop3w	Error	60	Failed to obtain the configuration data	The configured value could not be obtained.	OS may have errors. Restart the server or take other actions.

# PostgreSQL monitor resource

Module Type	Туре	Return Value	Message	Description	Solution
psqlw	Error	1	Initialization has failed[%1!s!].	Initialization process has failed. It may be due to memory allocation failure.  Information on the initialization may be displayed on %1.	OS itself may have errors. Restart the server or take other actions.

Module Type	Туре	Return Value	Message	Description	Solution
psqlw	Error	2	The configured value is not correct.	The configured value of the monitoring is not correct.	Check the configured value on the Builder since it may not be correct.
psqlw	Error	10	A function error was detected.	A function error occurred.	Monitor applications or OS may have errors. Check the status of the system.
psqlw	Error	11	An error was detected in accessing the monitor target.	The access to the database failed.	Check configured values on the Builder (such as a database name). If there is no error, check the database has errors.
psqlw	Error	12	An error was detected in user authentication.	The access to the database failed.	Check configured values on the Builder (such as a user name or a password). If there is no error, check if the database has errors.
psqlw	Error	13	An application error was detected.	The database error was detected.	Refer to error messages for database described separately to fix errors.
psqlw	Error	14	An error was detected in executing SQL statement [%1!s!].	Executing SQL statement failed.  The executed SQL statement is displayed on %1.	Refer to error messages for database described separately to fix errors.
psqlw	Error	15	A data error was detected.	A value on the table of database has an error.	Database may be corrupt. Stop the database operation and investigate it. This error may occur when more than one monitoring is performed with the same monitor table name concurrently. Check if the values set in the multi-directional environment are appropriate.
psqlw	Error	40	No license is registered.	The license has not been registered.	Register the license.
psqlw	Error	60	Failed to obtain the configuration data.	The configured value could not be obtained.	OS may have errors. Restart the server or take other actions.

# Registry synchronization monitor resource

Module Type	ype Return Value	Message	Description	Solution
----------------	---------------------	---------	-------------	----------

Module Type	Туре	Return Value	Message	Description	Solution
regsyncw	Error	50	Failed to save registry.	The process of storing to a file at detection of registry update failed.	Check if the process other than ExpressCluster opens the registry storage file. Memory or OS resources may not be sufficient. Check the status of the system.
regsyncw	Warning	101	Setting of registry keys is invalid.	An invalid registry key is registered to the resource.	Check the value set on the Builder ( <b>Details</b> on <b>Resource Properties</b> ), and change to a correct registry key.
regsyncw	Warning 100	Delivery processing to other nodes has failed.	Registry storage files cannot be delivered to other nodes.	There may be an error on the connection to the other node. Check the status of the network.  OS of the local or other	
					server may have an error. Check the status of the system.

### **Disk TUR monitor resource**

Module Type	Туре	Return Value	Message	Description	Solution
sdw	Error	1	Initialization has failed. Check the cluster configuration data or system resources.	Initialization has failed. Check the cluster configuration data or system resources.	Memory or OS resources may not be sufficient. Check them.
sdw	Error	2	Initialization has not been done.	Initialization has not been done.	Memory or OS resources may not be sufficient. Check them.
sdw	Error	3	The cluster configuration data is invalid.	The cluster configuration data is invalid.	The cluster configuration data is invalid. Check the disk TUR monitor resource on the Builder
sdw	Error	4	Failed to open device. Check the disk status of monitor destination volume.	Failed to open device. Check the disk status of monitor destination volume.	Check if the disk driver of the monitoring target disk is loaded, the device exists, the disk is connected properly, the disk is powered on, or no other errors are occurred on the disk. Memory or OS resources may not be sufficient. Check them.
sdw	Error	5	Failed to control device. Check the disk status of monitor destination volume.	Failed to control device. Check the disk status of monitor destination volume.	Check if the monitoring target disk is connected properly, the disk is powered on, or no other errors are occurred on the disk.

Module Type	Туре	Return Value	Message	Description	Solution
sdw	Error	6	Internal resources are busy.	Internal resources are busy.	Memory or OS resources may not be sufficient. Check them.
sdw	Error	7	Failed to allocate memory. Check the system resource.	Failed to allocate memory. Check the system resource.	Memory or OS resources may not be sufficient. Check them.
sdw	Error	90	Polling timeout. Check the disk load of the monitor target and extend the monitor timeout time.	Polling timeout. Check the disk load of the monitor target and extend the monitor timeout time.	Check if the monitoring target disk is connected properly, the disk is powered on, or no other errors are occurred on the disk. The system may be under high load, or memory or OS resources may not be sufficient. Check them.
sdw	Error	99	Other internal error has occurred. Check the system resource.	Other internal error has occurred. Check the system resource.	Memory or OS resources may not be sufficient. Check them.

### **Service monitor resource**

Module Type	Туре	Return Value	Message	Description	Solution
service w	Error	5	Failed to obtain the service control right.	Failed to obtain the service control right.	Check if the service name is correct.
service w	Error	9	Service has been stopped.	Service has been stopped.	Check the status of the service.
service w	Error	Others	An internal error has occurred.	An internal error has occurred.	Memory or OS resources may not be sufficient. Check them.

# Print spooler monitor resource

Module Type	Туре	Return Value	Message	Description	Solution
spoolw	Error	3	Print spooler service has not been started.(%1!d!)	Print spooler service has not been started.(%1!d!)	Start the print spooler service.
spoolw	Error	4	Failed to get status of print spooler service.(errcode:%1!d!)	Failed to get status of print spooler service.(errcode:%1!d!)	Check the status of the print spooler service.
spoolw	Warnin g	100	Print spooler service is being started.	Print spooler service is being started.	Check the status of the print spooler service.

## **SMTP** monitor resource

Module Type	Туре	Return Value	Message	Description	Solution
smtpw	Error	1	Initialization has failed[%1!s!].	Initialization process has failed. It may be due to memory allocation failure.  Information on the initialization may be displayed on %1.	OS itself may have errors. Restart the server or take other actions.
smtpw	Error	2	The configured value is not correct.	The configured value of the monitoring is not correct.	Check the configured value on the Builder since it may not be correct.
smtpw	Error	10	A function error was detected.	A function error occurred.	Monitor applications or OS may have errors. Check the status of the system.
smtpw	Error	11	An error was detected in accessing the monitor target.	The access to the monitor application failed.	Check configured values on the Builder (such as an IP address). If there is no error, check if the monitor application has errors.
smtpw	Error	12	An error was detected in user authentication.	The access to the monitor application failed.	Check configured values on the Builder (such as a user name or a password). If there is no error, check if the monitor application has errors.
smtpw	Error	13	An application error was detected.	The monitor application error was detected.	Refer to error messages for monitor applications described separately to fix errors.
smtpw	Error	15	A data error was detected.	A value of the response data has an error.	Refer to error messages for monitor applications described separately to fix errors.
smtpw	Error	40	No license is registered.	The license has not been registered.	Register the license.
smtpw	Error	60	Failed to obtain the configuration data.	The configured value could not be obtained.	OS may have errors. Restart the server or take other actions.

### **SQL** Server monitor resource

Module Type	Туре	Return Value	Message	Description	Solution
sqlserve rw	Error	1	Initialization has failed[%1!s!].	Initialization process has failed. It may be due to memory allocation failure.  Information on the initialization may be displayed on %1.	OS itself may have errors. Restart the server or take other actions.
sqlserve rw	Error	2	The configured value is not correct.	The configured value of the monitoring is not correct.	Check the configured value on the Builder since it may not be correct.
sqlserve rw	Error	10	A function error was detected.	A function error occurred.	Monitor applications or OS may have errors. Check the status of the system.
sqlserve rw	Error	11	An error was detected in accessing the monitor target.	The access to the database failed.	Check configured values on the Builder (such as a database name). If there is no error, check the database has errors.
sqlserve rw	Error	12	An error was detected in user authentication.	The access to the database failed.	Check configured values on the Builder (such as a user name or a password). If there is no error, check if the database has errors.
sqlserve rw	Error	13	An application error was detected.	The database error was detected.	Refer to error messages for database described separately to fix errors.
sqlserve rw	Error	14	An error was detected in executing SQL statement [%1!s!].	Executing SQL statement failed.  The executed SQL statement is displayed on %1.	Refer to error messages for database described separately to fix errors.
sqlserve rw	Error	15	A data error was detected.	A value on the table of database has an error.	Database may be corrupt. Stop the database operation and investigate it. This error may occur when more than one monitoring is performed with the same monitor table name concurrently. Check if the values set in the multi-directional environment are appropriate.
sqlserve rw	Error	40	No license is registered.	The license has not been registered.	Register the license.

Module Type	Туре	Return Value	Message	Description	Solution
sqlserve rw	Error	60	Failed to obtain the configuration data.	The configured value could not be obtained.	OS may have errors. Restart the server or take other actions.

### **Tuxedo monitor resource**

Module Type	Туре	Return Value	Message	Description	Solution
tuxw	Error	1	Initialization has failed[%1!s!].	Initialization process has failed. It may be due to memory allocation failure.  Information on the initialization may be displayed on %1.	OS itself may have errors. Restart the server or take other actions.
tuxw	Error	2	The configured value is not correct.	The configured value of the monitoring is not correct.	Check the configured value on the Builder since it may not be correct.
tuxw	Error	10	A function error was detected.	A function error occurred.	Monitor applications or OS may have errors. Check the status of the system.
tuxw	Error	11	An error was detected in accessing the monitor target.	The access to the monitor application failed.	Check configured values on the Builder (such as an application config file). If there is no error, check if the monitor application has errors.
tuxw	Error	13	An application error was detected.	The monitor application error was detected.	Refer to error messages for monitor applications described separately to fix errors.
tuxw	Error	40	No license is registered.	The license has not been registered.	Register the license.
tuxw	Error	60	Failed to obtain the configuration data.	The configured value could not be obtained.	OS may have errors. Restart the server or take other actions.
tuxw	Error	98	Internal error.	Internal error occurred.	Memory or OS resources may not be sufficient. Check them.

# Virtual computer name monitor resource

Module Type	Туре	Return Value	Message	Description	Solution
vcomw	Error	5	VCOM control process has already been started.	VCOM control process has already been started.	Memory or OS resources may not be sufficient. Check them. Restart the OS.

Module Type	Туре	Return Value	Message	Description	Solution
vcomw	Error	6	VCOM control process has not been started.	VCOM control process has not been started.	Memory or OS resources may not be sufficient. Check them. Restart the OS.
vcomw	Error	8	VCOM control process does not exist.	VCOM control process does not exist.	The VCOM control process ID does not exist. Restart the OS.
vcomw	Error	Others	An internal error has occurred.	An internal error has occurred.	Memory or OS resources may not be sufficient. Check them.

### **Virtual IP monitor resource**

Module Type	Туре	Return Value	Message	Description	Solution
vipw	Error	6	IP address does not exist.	IP address does not exist.	NIC may have been disabled. Check if the VIP address exists by the ipconfig command.
vipw	Error	11	Adapter Index is different.	Adapter Index is different.	NIC may have been disabled. Check if the VIP address exists by the ipconfig command.
vipw	Error	Others	An internal error has occurred.	An internal error has occurred.	Memory or OS resources may not be sufficient. Check them.

# Websphere monitor resource

Module Type	Туре	Return Value	Message	Description	Solution
wasw	Error	1	Initialization has failed[%1!s!].	Initialization process has failed. It may be due to memory allocation failure.  Information on the initialization may be displayed on %1.	OS itself may have errors. Restart the server or take other actions.
wasw	Error	2	The configured value is not correct.	The configured value of the monitoring is not correct.	Check the configured value on the Builder since it may not be correct.
wasw	Error	10	A function error was detected.	A function error occurred.	Monitor applications or OS may have errors. Check the status of the system.

Module Type	Туре	Return Value	Message	Description	Solution
wasw	Error	12	An error was detected in user authentication.	The access to the monitor application failed.	Check configured values on the Builder (such as a user name or a password). If there is no error, check if the monitor application has errors.
wasw	Error	13	An application error was detected.	The monitor application error was detected.	Refer to error messages for monitor applications described separately to fix errors.
wasw	Error	40	No license is registered.	The license has not been registered.	Register the license.
wasw	Error	60	Failed to obtain the configuration data.	The configured value could not be obtained.	OS may have errors. Restart the server or take other actions.
wasw	Error	98	Internal error.	Internal error occurred.	Memory or OS resources may not be sufficient. Check them.

# Weblogic monitor resource

Module Type	Туре	Return Value	Message	Description	Solution
wlsw	Error	1	Initialization has failed[%1!s!].	Initialization process has failed. It may be due to memory allocation failure.  Information on the initialization may be displayed on %1.	OS itself may have errors. Restart the server or take other actions.
wlsw	Error	2	The configured value is not correct.	The configured value of the monitoring is not correct.	Check the configured value on the Builder since it may not be correct.
wlsw	Error	10	A function error was detected.	A function error occurred.	Monitor applications or OS may have errors. Check the status of the system.
wlsw	Error	11	An error was detected in accessing the monitor target.	The access to the monitor application failed.	Check configured values on the Builder (such as an IP address). If there is no error, check if the monitor application has errors.
wlsw	Error	12	An error was detected in user authentication.	The access to the monitor application failed.	Check configured values on the Builder (such as a user name or a password). If there is no error, check if the monitor application has errors.

Module Type	Туре	Return Value	Message	Description	Solution
wlsw	Error	13	An application error was detected.	The monitor application error was detected.	Refer to error messages for monitor applications described separately to fix errors.
wlsw	Error	40	No license is registered.	The license has not been registered.	Register the license.
wlsw	Error	60	Failed to obtain the configuration data.	amou to transmit and	
wlsw	Error	98	Internal error.	Internal error occurred.	Memory or OS resources may not be sufficient. Check them.

## **WebOTX** monitor resource

Module Type	Туре	Return Value	Message	Description	Solution
otxw	Error	1	Initialization has failed[%1!s!].	Initialization process has failed. It may be due to memory allocation failure.  Information on the initialization may be displayed on %1.	OS itself may have errors. Restart the server or take other actions.
otxw	Error	2	The configured value is not correct.	The configured value of the monitoring is not correct.	Check the configured value on the Builder since it may not be correct.
otxw	Error	10	A function error was detected.	A function error occurred.	Monitor applications or OS may have errors. Check the status of the system.
otxw	Error	11	An error was detected in accessing the monitor target.	The access to the monitor application failed.	Check configured values on the Builder (such as an IP address or an application server name). If there is no error, check if the monitor application has errors.
otxw	Error	12	An error was detected in user authentication.	The access to the monitor application failed.	Check configured values on the Builder (such as a user name or a password). If there is no error, check if the monitor application has errors.
otxw	Error	13	An application error was detected.	The monitor application error was detected.	Refer to error messages for monitor applications described separately to fix errors.
otxw	Error	40	No license is registered.	The license has not been registered.	Register the license.

Module Type	Туре	Return Value	Message	Description	Solution
otxw	Error	60	Failed to obtain the configuration data.	The configured value could not be obtained.	OS may have errors. Restart the server or take other actions.
otxw	Error	98	Internal error.	Internal error occurred.	Memory or OS resources may not be sufficient. Check them.

# **Appendix**

#### This section covers:

Appendix A GlossaryAppendix B Index

# **Appendix A Glossary**

**Cluster partition** 

**Active server** A server that is running for an application set.

(Related term: Standby server)

A partition on a mirror disk. Used for managing mirror

disks.

(Related term: Disk heartbeat partition)

**Cluster shutdown** To shut down an entire cluster system (all servers that

configure a cluster system).

Cluster system Multiple computers are connected via a LAN (or other

network) and behave as if it were a single system.

**Data partition** A local disk that can be used as a shared disk for

switchable partition. Data partition for mirror disks.

(Related term: Cluster partition)

**Disk heartbeat partition** A partition used for heartbeat communication in a shared

disk type cluster.

**Failover** The process of a standby server taking over the group of

resources that the active server previously was handling

due to error detection.

Failback A process of returning an application back to an active

server after an application fails over to another server.

Failover group A group of cluster resources and attributes required to

execute an application.

**Failover policy** A priority list of servers that a group can fail over to.

Floating IP address Clients can transparently switch one server from another

when a failover occurs.

Any unassigned IP address that has the same network address that a cluster server belongs to can be used as a

floating address.

**Heartbeat** Signals that servers in a cluster send to each other to detect

a failure in a cluster.

(Related terms: Interconnect, Network partition)

Interconnect A dedicated communication path for server-to-server

communication in a cluster.

(Related terms: Private LAN, Public LAN)

Management client Any machine that uses the WebManager to access and

manage a cluster system.

Master server The server displayed on top of the Master Server in

Cluster Properties in the Builder.

**Mirror connect** LAN used for data mirroring in a data mirror type cluster.

Mirror connect can be used with primary interconnect.

Mirror disk type cluster A cluster system that does not use a shared disk. Local

disks of the servers are mirrored.

Moving failover group Moving an application from an active server to a standby

server by a user.

**Network partition** All heartbeat is lost and the network between servers is

partitioned.

(Related terms: Interconnect, Heartbeat)

Node A server that is part of a cluster in a cluster system. In

networking terminology, it refers to devices, including computers and routers, that can transmit, receive, or

process signals.

Private LAN in which only servers configured in a clustered

system are connected.

(Related terms: Interconnect, Public LAN)

**Primary (server)** A server that is the main server for a failover group.

(Related term: Secondary server)

Public LAN A communication channel between clients and servers.

(Related terms: Interconnect, Private LAN)

Startup attribute A failover group attribute that determines whether a

failover group should be started up automatically or

manually when a cluster is started.

**Shared disk** A disk that multiple servers can access.

**Shared disk type cluster** A cluster system that uses one or more shared disks.

Switchable partition A disk partition connected to multiple computers and is

switchable among computers.

(Related terms: Disk heartbeat partition)

**Secondary server** A destination server where a failover group fails over to

during normal operations. (Related term: Primary server)

**Server Group** A group of servers connected to the same network or the

shared disk device

**Standby server** A server that is not an active server.

(Related term: Active server)

Virtual IP address IP address used to configure a remote cluster.

# **Appendix B Index**

#### A

Account tab. 140 Activation and deactivation error of recovery target, 578 Adding an object, 115 Adjusting time-out temporarily, 279 Alert Log tab, 135 Alert service tab, 143 Alert view fields, 56 Alert view operation, 58 Application monitor resource, 850 application monitor resources, 595, 603 Application resource, 840 application resources, 432 Application resources, 432 Auto Recovery tab, 141 Automatically recovering from mirroring, 798

#### B

backing up configuration data, 110, 111, 201, 272
Backing up the cluster configuration data, 276
Behavior of reporting icon, 755
Behavior when an error is detected by a monitor resource, 562

#### $\mathbf{C}$

Changing the name of a monitor resource, 595 Changing the screen layout, 30 Checking alerts, 23, 25, 56, 314 Checking the cluster status, 23, 25, 51 Checking the mirror break status from the WebManager, 806 Checking the mirror break status with a command, 800 Checking the mirror recovery progress from the WebManager, 807 Checking the mirror recovery progress with a command, 802 Checking the status of each object, 23, 25, 31 Checking the status of individual server in the WebManager list view, 54 Checking the status of the whole monitor in the WebManager list view, 55 Checking the version information, 117 CIFS monitor resource, 850 CIFS resource, 840 Cluster properties, 118 Cluster shutdown, 76 cluster shutdown reboot, 76 Collecting information at emergency OS shutdown, 271 Collecting logs, 201, 266

Collecting logs by specifying a type, 269 Collecting logs by using the WebManager, 27 colors of the icons, 32 COM I/F tab, 157 COM network partition resolution resources, 740 Communication ports, 762 Configuration and range of NIC link up/down monitoring, 625 Configuring the settings to temporarily prevent execution of failover, 765 Connecting mirror disks manually, 797 Consideration for using the Builder, 97 Considerations for service resources, 504 Controlling monitor resources, 201, 316 Controlling path, 525 CPU frequency control, 327 Creating a cluster, 110, 111, 201, 272 Creating a new cluster, 108 Custom monitor resource, 855

#### D

DB2 monitor resource, 851 Delay warning of monitor resources, 586 Delay Warning tab, 136 Dependencies of disk resource, 499 Dependencies of floating IP resource, 439 Dependencies of mirror disk resource, 447 Dependencies of registry synchronization resources, 463 Dependencies of script resources, 470 Dependencies of service resources, 503 Dependencies of virtual computer name resources, 513 Dependencies of virtual IP resources, 523 Dependencies of VxVM related resources, 509 Detailed info in activating and deactivating group resources, 840 Detailed info of monitor resource errors, 850 Details on the Builder screen, 98 Determining virtual IP address, 525 Directory structure of ExpressCluster, 760 Disk filter driver, 837 Disk I/F tab, 159 DISK network partition resolution resources, 742 Disk resource, 845 Disk resources, 499 Disk RW monitor resource, 852 disk RW monitor resources, 605 Disk tab, 137 Disk TUR monitor resource, 869 disk TUR monitor resources, 637, 657 Displaying / changing the server group settings, Displaying a group map, 209 Displaying all cluster configuration data, 251

- Displaying and changing disk RW monitor resource details, 605
- Displaying and changing floating IP monitor resource details, 609
- Displaying and changing IP monitor resource details, 613
- Displaying and changing Logical Service, 416
- Displaying and changing the application resource details, 432
- Displaying and changing the comment of a group, 412, 428
- Displaying and changing the comment of a group resource, 418
- Displaying and changing the comment of a monitor resource, 595
- Displaying and changing the details of disk resource, 504
- Displaying and changing the details of disk resources, 500
- Displaying and changing the details of floating IP resource, 443
- Displaying and changing the details of mirror disk resource, 457
- Displaying and changing the details of print spooler resources, 509
- Displaying and changing the details of registry synchronization resources, 466
- Displaying and changing the details of the multi target monitor resource, 630
- Displaying and changing the details of the service monitor resources, 640
- Displaying and changing the details of the virtual computer name resources, 644
- Displaying and changing the details of the virtual IP monitor resources, 646
- Displaying and changing the details of virtual computer name resource, 519
- Displaying and changing the details of virtual IP resource, 527
- Displaying and changing the disk DB2 monitor resource details, 665
- Displaying and changing the disk TUR monitor resource details, 637
- Displaying and changing the FTP monitor resource details, 669
- Displaying and changing the group attribute, 415
- Displaying and changing the HTTP monitor resource details, 672
- Displaying and changing the hybrid disk monitor resource details, 654
- Displaying and changing the hybrid disk TUR monitor resource details, 657
- Displaying and changing the IMAP4 monitor resource details, 676
- Displaying and changing the mirror disk connect monitor resource details, 617
- Displaying and changing the mirror disk monitor resource details, 621
- Displaying and changing the NIC link up/down monitor resource details, 625
- Displaying and changing the ODBC monitor

- resource details, 680
- Displaying and changing the operation settings when a group resource error is detected, 420
- Displaying and changing the Oracle monitor resource details, 684
- Displaying and changing the OracleAS monitor resource details, 689
- Displaying and changing the OracleAS monitor resource properties, 691
- Displaying and changing the POP3 monitor resource details, 697
- Displaying and changing the PostgreSQL monitor resource details, 701
- Displaying and changing the script resource details, 493
- Displaying and changing the server group settings, 414
- Displaying and changing the settings of a monitor resource, 595
- Displaying and changing the settings of group properties, 412
- Displaying and changing the settings of group resources, 417
- Displaying and changing the settings of servers that starts up the group, 413
- Displaying and changing the settings of the script resource details, 493
- Displaying and changing the settings when an error is detected by a monitor resource, 598, 602
- Displaying and changing the SMTP monitor resource details, 705
- Displaying and changing the SQL Server monitor resource details, 709
- Displaying and changing the Tuxedo monitor resource details, 713
- Displaying and changing the Weblogic monitor resource details, 722
- Displaying and changing the WebOTX monitor resource details, 727
- Displaying and changing the Websphere monitor resource details, 718
- Displaying and configuring the settings of dependency among group resources, 419
- Displaying and/or changing the script resource script created by the Builder, 494
- Displaying hybrid disk resource properties with WebManager, 548
- Displaying only the configuration data of a certain group resource, 223
- Displaying only the configuration data of certain groups, 221
- Displaying only the configuration data of certain server groups, 221
- Displaying only the configuration data of certain servers, 216
- Displaying only the data of a certain monitor resource, 236
- Displaying the application monitor resource properties with the WebManager, 603
- Displaying the application resource properties with the WebManager, 437

Displaying the cluster configuration data, 212 Displaying the cluster status, 201, 204

Displaying the detailed information on the whole cluster in a list by the WebManager, 51

Displaying the disk resource properties with the WebManager, 502

Displaying the disk RW monitor resource properties with the WebManager, 606

Displaying the disk TUR monitor resources properties with the WebManager, 638

Displaying the floating IP monitor resource properties with the WebManager, 610

Displaying the FTP monitor resource properties, 670

Displaying the HTTP monitor resource properties, 674

Displaying the hybrid disk monitor resource properties with the WebManager, 655

Displaying the hybrid disk TUR monitor resources properties with the WebManager, 659

Displaying the IMAP4 monitor resource properties, 677

Displaying the IP monitor resource properties with the WebManager, 615

Displaying the mirror connect monitor resource properties with the WebManager, 619

Displaying the mirror disk monitor resource properties with the WebManager, 623

Displaying the mirror disk resource properties with the WebManager, 461

Displaying the NIC link up/down monitor resource properties with the WebManager, 627

Displaying the ODBC monitor resource properties, 681

Displaying the Oracle monitor resource properties, 686

Displaying the POP3 monitor resource properties,  $699\,$ 

Displaying the PostgreSQL monitor resource properties, 703

Displaying the print spooler monitor resources properties with the WebManager, 642

Displaying the print spooler resource properties with the WebManager, 511

Displaying the properties of COM network partition resolution resources with the WebManager, 740

Displaying the properties of DISK network partition resolution resources with the WebManager, 743

Displaying the properties of floating IP resource with the WebManager, 445

Displaying the properties of kernel mode LAN heartbeat resources with the WebManager, 734

Displaying the properties of majority network partition resolution resources with the WebManager, 747

Displaying the properties of PING network partition resolution resources with the WebManager, 745 Displaying the properties of the multi target monitor resource with the WebManager, 633

Displaying the property of a certain group by using the WebManager, 426

Displaying the property of the whole groups by using the WebManager, 426

Displaying the registry synchronization monitor resources properties with the WebManager, 635

Displaying the registry synchronization resource properties with the WebManager, 469

Displaying the script resource properties with the WebManager, 497

Displaying the server group properties, 431 Displaying the service monitor resources properties with the WebManager, 640

Displaying the service resource properties with the WebManager, 507

Displaying the SMTP monitor resource properties, 707

Displaying the SQL Server monitor resource properties, 711

Displaying the status of heartbeat resources, 210 Displaying the status of monitor resources, 209 Displaying the status of network partition resolution resources, 211

Displaying the Tuxedo monitor resource properties, 715

Displaying the virtual computer name monitor resource properties with the WebManager, 644

Displaying the virtual computer name resource properties with the WebManager, 521

Displaying the virtual IP monitor resource properties with the WebManager, 646

Displaying the virtual IP resource properties with the WebManager, 532

Displaying the Weblogic monitor resource properties, 724

Displaying the WebOTX monitor resource properties, 728

Displaying the Websphere monitor resource properties, 720

Downloading the configuration file, 110 Driver event log messages, 837

#### $\mathbf{E}$

Edit menu, 115
Emergency cluster shutdown, 763
Emergency server restart, 765
Environment variables in script of script
resource, 471
Error messages, 23, 78
Examples of mirror disk construction, 455
Execution timing of script resource scripts, 473
Exiting from the Builder, 114
ExpressCluster commands, 202

#### ${f F}$

failover policy, 397 File menu, 107 Final action, 763, 406
Floating IP, 439
Floating IP monitor resource, 854
floating IP monitor resources, 609
Floating IP resource, 841
Forced stop action, 763
Forcibly connecting mirror disk when mirroring is not available, 797
FTP monitor resource, 854
FTP monitor resources, 669

### $\mathbf{G}$

Group resources, 394

#### Η

HBA tab, 167 Heartbeat I/F tab, 119 Heartbeat resources, 732 How to register a cluster to the integrated WebManager, 89 How to replace a server with a new one, 759, 766 How to start up the WebManager from the integrated WebManager, 91 How to update the information on the integrated WebManager, 91 HTTP monitor resource, 857 HTTP monitor resources, 672 Hybrid disk monitor resource, 857 hybrid disk resource, 842 Hybrid disk resource operation command, 310 Hybrid disk status display command, 305 Hybrid disk TUR monitor resource, 856

#### Ι

IMAP4 monitor resource, 859 IMAP4 monitor resources, 676 Info tab, 118, 152 Integrated WebManager, 85, 86, 87 Integrated WebManager tab, 134 Interconnect LAN I/F tab, 153 Interface of each server, 150 IP monitor resource, 860 IP monitor resources, 612 Isolated, 756

#### K

Kernel mode LAN heartbeat driver, 839

#### $\mathbf{L}$

Limitations of the WebManager, 77 limitations on the connection and operation, 23, 72 Limitations on using the Builder, 97 Linking to ESMPRO Agent, 779 list view, 51

#### M

Mail report, 755 main window, 87 Majority I/F tab, 163 Majority network partition resolution resources, 746 Manually stopping and starting the WebManager, 71 Master Server tab, 124 Media sense function becomes invalid, 811 Message output command, 314 Messages, 814 Mirror connect I/F tab, 153, 164 Mirror connect monitor resource, 861 Mirror disk, 447 mirror disk connect monitor resources, 617 mirror disk helper, 76 Mirror disk helper, 59 Mirror disk monitor resource, 860 mirror disk monitor resources, 621 Mirror disk resource, 842, 76 Mirror disk resource operation command, 296 mirror disk resources, 447 Mirror disk tab, 138 mirror parameters, 452 Mirror related commands, 291 Mirror status display commands, 291 Modifying the log level and size, 282 Monitor resources, 553 Monitor timing of monitor resources, 557 Monitoring by application monitor resources, 603 Monitoring by disk RW monitor resources, 605 Monitoring by floating IP monitor resources, 609 Monitoring by IP monitor resources, 612 Monitoring by service monitor resources, 640 Monitoring by virtual computer name monitor resources, 644 Monitoring by virtual IP monitor resources, 646 Monitoring interval for monitor resources, 558 Multi target monitor resource, 861 Multi target monitor resource status, 629 multi target monitor resources, 629

#### N

NAS monitor resource, 861
NAS resource, 849
network partition resolution by COM method, 739
network partition resolution by COM method and DISK method, 748
network partition resolution by DISK method, 741
network partition resolution by majority method, 746
network partition resolution by PING method, 744
network partition resolution by PING method and DISK method, 748
Network Partition Resolution I/F tab, 121

ExpressCluster X 2.1 for Windows Reference Guide

Network partition resolution resource becomes

unavailable, 789 network partition resolution resources, 736 Network warning light switch off command, 325 NIC Linc Up/Down monitor resource, 862 NIC link up/down monitor resources, 625 Normally connecting mirror disk when mirroring is available, 797

Not resolving network partition, 748

Note on, 617

Note on application resources, 432

Note on disk resources, 500

Note on hybrid disk monitor resources, 654 Note on mirror disk monitor resources, 621

Note on mirror disk resources, 456

Note on NIC link up/down monitor resources, 625

notes, 689

Notes on, 526

Notes on disk TUR monitor resources, 637

Notes on floating IP resources, 441

Notes on hybrid disk TUR monitor resources, 657

Notes on print spooler resources, 509

Notes on registry synchronization resources, 465

ODBC monitor resource, 862 ODBC monitor resources, 680 Opening the configuration file, 108 Operating a cluster by using the WebManager, Operating groups, 201, 261 Operating the cluster, 201, 254, 259, 260 Operating the cluster from the command line, 202

Operations, 42 Operations at detection of activation and inactivation errors, 402 Oracle monitor resource, 863 Oracle monitor resources, 684 OracleAS monitor resource, 864, 865, 866 Output paths of log files, 270 Overview of the Builder, 96 Overview of the ExpressCluster X Builder, 98

### P

Parameter details, 118 Parameters list, 172 Partition size tuning command, 300 Ping I/F tab, 161 PING network partition resolution resource, 745 Pop up menu, 105 POP3 monitor resource, 866 POP3 monitor resources, 697 Port No. tab, 126 PostgreSQL monitor resource, 867 PostgreSQL monitor resources, 701 Power saving tab, 149 Print spooler monitor resource, 870 print spooler monitor resources, 642

Print spooler resource, 847

print spooler resources, 509 Print spooler resources, 509 Properties, 117 Public LAN I/F tab, 155

#### $\mathbf{R}$

Reboot count limit, 407 recover mirror (forcefully), 66 Recovering from mirror breaks, 798 Recovering mirror using the WebManager, 809 Recovering mirror with a command, 802 Recovering servers, 76 Recovery, 765 Recovery tab, 127 Registry synchronization monitor resource, 868 registry synchronization monitor resources, 635 Registry synchronization resource, 843 registry synchronization resources, 463 Registry synchronization resources, 463 Removing an object, 116 Renaming a group, 412, 428 Renaming a group resource, 417 Renaming an object, 117 Requirement to use virtual IP address, 525 Resetting the reboot count, 411 Resource deactivation error, 764 Resuming and stopping a monitor resource temporarily, 76 Returning from monitor error (Normal), 574 RIP tab, 142 Running the forcible mirror recovery from the WebManager only on one Server, 811 Running the forcible mirror recovery using the WebManager, 809 Running the forcible mirror recovery with a command, 804 Running the forcible mirror recovery with a command only on one server, 805 running the mirror status display command, 292

#### S

Saving the configuration file, 109 Script resource, 845 script resources, 470 Scripts in script resources, 470 Searching an alert, 25, 56 Server properties, 150 Service monitor resource, 870 service monitor resources, 640 Service resource, 846 service resources, 503 Service resources, 504 Settings of the COM network partition resolution resources, 739 Settings of the DISK network partition resolution resources, 741 Settings of the kernel mode LAN heartbeat resources, 733 Settings of the majority network partition resolution resources, 746

#### Appendix B Index

Settings of the PING network partition resolution resources, 744 Shutting down a specified server, 201, 259 Shutting down and rebooting an individual server, 76 Shutting down the entire cluster, 201, 260 SMTP monitor resource, 871 SMTP monitor resources, 705 Snapshot backup, 302 Specifying log collector server, 270 SQL Server monitor resource, 872 SQL Server monitor resources, 709 Starting and stopping a group resource, 76 Starting, stopping, and moving an individual group, 76 Status Descriptions, 252 Stopping mirror recovery, 69 Switch authorization of the WebManager, 75

#### T

Table for cluster name selection, 99 Table for group name selection, 100 Table for group selection, 99 Table for monitor resource selection, 102 Table for server group name selection, 103 Table for server group selection, 103 Table for server name selection, 103 Table for server selection, 102 Table view, 99 the settings of dependency among group resources, 418 Timeout tab, 125 Tips for creating scripts, 493 Title view, 24, 25, 88 tree view, 23, 25, 31 Tree view, 98 Troubleshooting, 788 Tuning hybrid disk resources, 548 Tuning mirror disk resource, 459 Tuning multi target monitor resource, 631 Tuning registry synchronization resource, 467 Tuning script resource, 496 Tuxedo monitor resource, 873 Tuxedo monitor resources, 713 Type of limitation, 72

#### IJ

Unavailable commands when interconnections are disconnected, 796 Understanding disk resource, 499 Understanding floating IP resource, 439 Understanding kernel mode LAN heartbeat resources, 733 Updating the WebManager information, 29 Uploading, 110 Upper limits of registration, 199 Using a tool bar of the Builder, 106 Using menu bar of the Builder, 107

#### V

Virtual computer name monitor resource, 873, 644
virtual computer name monitor resources, 644
Virtual computer name resource, 848
virtual computer name resources, 513
Virtual computer name resources, 513, 515
Virtual IP monitor resource, 874
virtual IP monitor resources, 646
Virtual IP resource, 849
virtual IP resources, 523
Virtual IP resources, 523

W Waiting for monitor resource to start monitoring, 587 Warning Light, 755 Warning light tab, 168 Weblogic monitor resource, 875, 876 Weblogic monitor resources, 722 WebManager, 24, 92 WebManager tab, 129 WebOTX monitor resources, 726 Websphere monitor resource, 874 Websphere monitor resources, 717 What causes ExpressCluster to shut down servers, 763 What is a group, 395 When a heartbeat time-out occurs, 790 When a monitor resource error occurs, 790 When a network partition resolution resource error is detected, 789 When activating or deactivating group resources fails, 790 When activating or deactivating network partition resolution resource fails, 789 When network partitioning occurs, 792 When the ExpressCluster system does not start When you do not want to use the WebManager, 71 Window, 23, 24

Writing scripts, 488