

EXPRESSCLUSTER X 4.3

Supported distributions and kernel versions

<Notes>

- The distribution or kernel in the following list has been verified with EXPRESSCLUSTER.
 - ✓: Supported
 - ×: Not supported
- Any distribution or kernel not in the list has not been verified.
- EXPRESSCLUSTER X CD-ROM may not contain the latest rpm files to support the following kernel versions. Apply the latest update of EXPRESSCLUSTER to run with the latest kernel version.

IBM POWER LE

Distribution	Kernel version	Replicator Replicator DR support	clpka,clpkhb support	EXPRESSCLUSTER Version
Red Hat Enterprise Linux 8 (Update2)	4.18.0-193.el8.ppc64le	×	✓	4.3.0-1 or later
	4.18.0-193.28.1.el8_2.ppc64le	×	✓	4.3.0-1 or later
Red Hat Enterprise Linux 8 (Update1)	4.18.0-147.el8.ppc64le	×	✓	4.3.0-1 or later
Red Hat Enterprise Linux 7 (Update8)	3.10.0-1127.el7.ppc64le	×	✓	4.3.0-1 or later
Red Hat Enterprise Linux 7 (Update7)	3.10.0-1062.el7.ppc64le	×	✓	4.2.0-1 or later
Red Hat Enterprise Linux 7 (Update6)	3.10.0-957.el7.ppc64le	×	✓	4.2.0-1 or later
	3.10.0-957.27.2.el7.ppc64le	×	✓	4.2.0-1 or later
Red Hat Enterprise Linux 7 (Update5)	3.10.0-862.el7.ppc64le	×	✓	4.1.0-1 or later
	3.10.0-862.14.4.el7.ppc64le	×	✓	4.1.0-1 or later
	3.10.0-862.37.1.el7.ppc64le	×	✓	4.2.0-1 or later
Red Hat Enterprise Linux 7 (Update4)	3.10.0-693.el7.ppc64le	×	✓	4.0.0-1 or later
	3.10.0-693.2.2.el7.ppc64le	×	✓	4.0.0-1 or later
	3.10.0-693.5.2.el7.ppc64le	×	✓	4.0.0-1 or later
	3.10.0-693.11.6.el7.ppc64le	×	✓	4.0.0-1 or later
	3.10.0-693.21.1.el7.ppc64le	×	✓	4.1.0-1 or later
	3.10.0-693.39.1.el7.ppc64le	×	✓	4.1.0-1 or later
Red Hat Enterprise Linux 7 (Update3)	3.10.0-514.el7.ppc64le	×	✓	4.0.0-1 or later
	3.10.0-514.21.1.el7.ppc64le	×	✓	4.0.0-1 or later
	3.10.0-514.21.2.el7.ppc64le	×	×	—
	3.10.0-514.26.2.el7.ppc64le	×	✓	4.0.0-1 or later
	3.10.0-514.58.1.el7.ppc64le	×	✓	4.1.0-1 or later

Distribution	Kernel version	Replicator Replicator DR support	clpka,clpkhb support	EXPRESSCLUSTER Version
Novell SUSE LINUX Enterprise Server 15 (SP2)	5.3.18-22-default	×	×	4.3.0-1 or later
Novell SUSE LINUX Enterprise Server 12 (SP5)	4.12.14-120-default	×	×	4.3.0-1 or later
Novell SUSE LINUX Enterprise Server 12 (SP2)	4.4.21-69.1-default	×	✓	4.1.0-1 or later
	4.4.120-92.70.1-default	×	✓	4.1.0-1 or later
Novell SUSE LINUX Enterprise Server 12 (SP1)	3.12.49-11.1-default	×	✓	4.0.0-1 or later
	3.12.74-60.64.40.1-default	×	✓	4.0.0-1 or later